



# NVIDIA OptiX 8.0

## API Reference Manual

1 August 2023  
Version 8.0



## Table of Contents

<b>1</b>	<b>NVIDIA OptiX 8.0 API</b>	<b>1</b>
<b>2</b>	<b>Module Index</b>	<b>1</b>
2.1	Modules . . . . .	1
<b>3</b>	<b>Class Index</b>	<b>1</b>
3.1	Class List . . . . .	1
<b>4</b>	<b>File Index</b>	<b>4</b>
4.1	File List . . . . .	4
<b>5</b>	<b>Module Documentation</b>	<b>5</b>
5.1	Device API . . . . .	5
5.2	Function Table . . . . .	54
5.3	Host API . . . . .	55
5.4	Error handling . . . . .	55
5.5	Device context . . . . .	55
5.6	Pipelines . . . . .	55
5.7	Modules . . . . .	55
5.8	Tasks . . . . .	55
5.9	Program groups . . . . .	55
5.10	Launches . . . . .	55
5.11	Acceleration structures . . . . .	55
5.12	Denoiser . . . . .	55
5.13	Utilities . . . . .	55
5.14	Types . . . . .	63
<b>6</b>	<b>Namespace Documentation</b>	<b>111</b>
6.1	optix_impl Namespace Reference . . . . .	111
6.2	optix_internal Namespace Reference . . . . .	115
<b>7</b>	<b>Class Documentation</b>	<b>115</b>
7.1	OptixAabb Struct Reference . . . . .	115
7.2	OptixAccelBufferSizes Struct Reference . . . . .	116
7.3	OptixAccelBuildOptions Struct Reference . . . . .	117
7.4	OptixAccelEmitDesc Struct Reference . . . . .	118
7.5	OptixBuildInput Struct Reference . . . . .	118
7.6	OptixBuildInputCurveArray Struct Reference . . . . .	119
7.7	OptixBuildInputCustomPrimitiveArray Struct Reference . . . . .	122
7.8	OptixBuildInputDisplacementMicromap Struct Reference . . . . .	123
7.9	OptixBuildInputInstanceArray Struct Reference . . . . .	125
7.10	OptixBuildInputOpacityMicromap Struct Reference . . . . .	126
7.11	OptixBuildInputSphereArray Struct Reference . . . . .	128
7.12	OptixBuildInputTriangleArray Struct Reference . . . . .	130
7.13	OptixBuiltinISOOptions Struct Reference . . . . .	132
7.14	OptixDenoiserGuideLayer Struct Reference . . . . .	133
7.15	OptixDenoiserLayer Struct Reference . . . . .	134
7.16	OptixDenoiserOptions Struct Reference . . . . .	134
7.17	OptixDenoiserParams Struct Reference . . . . .	135
7.18	OptixDenoiserSizes Struct Reference . . . . .	136
7.19	OptixDeviceContextOptions Struct Reference . . . . .	137
7.20	OptixDisplacementMicromapArrayBuildInput Struct Reference . . . . .	138
7.21	OptixDisplacementMicromapDesc Struct Reference . . . . .	139

7.22	OptixDisplacementMicromapHistogramEntry Struct Reference	139
7.23	OptixDisplacementMicromapUsageCount Struct Reference	140
7.24	OptixFunctionTable Struct Reference	141
7.25	OptixImage2D Struct Reference	150
7.26	OptixInstance Struct Reference	151
7.27	OptixMatrixMotionTransform Struct Reference	152
7.28	OptixMicromapBuffers Struct Reference	153
7.29	OptixMicromapBufferSizes Struct Reference	154
7.30	OptixModuleCompileBoundValueEntry Struct Reference	154
7.31	OptixModuleCompileOptions Struct Reference	155
7.32	OptixMotionOptions Struct Reference	157
7.33	OptixOpacityMicromapArrayBuildInput Struct Reference	157
7.34	OptixOpacityMicromapDesc Struct Reference	158
7.35	OptixOpacityMicromapHistogramEntry Struct Reference	159
7.36	OptixOpacityMicromapUsageCount Struct Reference	160
7.37	OptixPayloadType Struct Reference	160
7.38	OptixPipelineCompileOptions Struct Reference	161
7.39	OptixPipelineLinkOptions Struct Reference	162
7.40	OptixProgramGroupCallables Struct Reference	162
7.41	OptixProgramGroupDesc Struct Reference	163
7.42	OptixProgramGroupHitgroup Struct Reference	164
7.43	OptixProgramGroupOptions Struct Reference	165
7.44	OptixProgramGroupSingleModule Struct Reference	166
7.45	OptixRelocateInput Struct Reference	166
7.46	OptixRelocateInputInstanceArray Struct Reference	167
7.47	OptixRelocateInputOpacityMicromap Struct Reference	168
7.48	OptixRelocateInputTriangleArray Struct Reference	168
7.49	OptixRelocationInfo Struct Reference	169
7.50	OptixShaderBindingTable Struct Reference	169
7.51	OptixSRTData Struct Reference	171
7.52	OptixSRTMotionTransform Struct Reference	173
7.53	OptixStackSizes Struct Reference	174
7.54	OptixStaticTransform Struct Reference	175
7.55	OptixUtilDenoiserImageTile Struct Reference	176
7.56	optix_internal::TypePack<... > Struct Template Reference	176
<b>8</b>	<b>File Documentation</b>	<b>176</b>
8.1	optix_device_impl.h File Reference	176
8.2	optix_device_impl.h	208
8.3	optix_device_impl_transformations.h File Reference	243
8.4	optix_device_impl_transformations.h	244
8.5	optix_micromap_impl.h File Reference	251
8.6	optix_micromap_impl.h	252
8.7	optix.h File Reference	255
8.8	optix.h	255
8.9	optix_denoiser_tiling.h File Reference	256
8.10	optix_denoiser_tiling.h	256
8.11	optix_device.h File Reference	261
8.12	optix_device.h	268
8.13	optix_function_table.h File Reference	277
8.14	optix_function_table.h	277
8.15	optix_function_table_definition.h File Reference	282
8.16	optix_function_table_definition.h	283

8.17	optix_host.h File Reference . . . . .	283
8.18	optix_host.h . . . . .	310
8.19	optix_micromap.h File Reference . . . . .	315
8.20	optix_micromap.h . . . . .	316
8.21	optix_stack_size.h File Reference . . . . .	317
8.22	optix_stack_size.h . . . . .	318
8.23	optix_stubs.h File Reference . . . . .	322
8.24	optix_stubs.h . . . . .	322
8.25	optix_types.h File Reference . . . . .	334
8.26	optix_types.h . . . . .	344
8.27	main.dox File Reference . . . . .	363

# 1 NVIDIA OptiX 8.0 API

This document describes the NVIDIA OptiX application programming interface. See <https://raytracing-docs.nvidia.com/> for more information about programming with NVIDIA OptiX.

## 2 Module Index

### 2.1 Modules

Here is a list of all modules:

Device API	5
Function Table	54
Host API	55
Error handling	55
Device context	55
Pipelines	55
Modules	55
Tasks	55
Program groups	55
Launches	55
Acceleration structures	55
Denoiser	55
Utilities	55
Types	63

## 3 Class Index

### 3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<code>OptixAabb</code>	
AABB inputs	115
<code>OptixAccelBufferSizes</code>	
Struct for querying builder allocation requirements	116
<code>OptixAccelBuildOptions</code>	
Build options for acceleration structures	117
<code>OptixAccelEmitDesc</code>	
Specifies a type and output destination for emitted post-build properties	118
<code>OptixBuildInput</code>	
Build inputs	118
<code>OptixBuildInputCurveArray</code>	
Curve inputs	119
<code>OptixBuildInputCustomPrimitiveArray</code>	
Custom primitive inputs	122

<code>OptixBuildInputDisplacementMicromap</code>	Optional displacement part of a triangle array input	123
<code>OptixBuildInputInstanceArray</code>	Instance and instance pointer inputs	125
<code>OptixBuildInputOpacityMicromap</code>		126
<code>OptixBuildInputSphereArray</code>	Sphere inputs	128
<code>OptixBuildInputTriangleArray</code>	Triangle inputs	130
<code>OptixBuiltinISOptions</code>	Specifies the options for retrieving an intersection program for a built-in primitive type. The primitive type must not be <code>OPTIX_PRIMITIVE_TYPE_CUSTOM</code>	132
<code>OptixDenoiserGuideLayer</code>	Guide layer for the denoiser	133
<code>OptixDenoiserLayer</code>	Input/Output layers for the denoiser	134
<code>OptixDenoiserOptions</code>	Options used by the denoiser	134
<code>OptixDenoiserParams</code>	Various parameters used by the denoiser	135
<code>OptixDenoiserSizes</code>	Various sizes related to the denoiser	136
<code>OptixDeviceContextOptions</code>	Parameters used for <code>optixDeviceContextCreate()</code>	137
<code>OptixDisplacementMicromapArrayBuildInput</code>	Inputs to displacement micromaps array construction	138
<code>OptixDisplacementMicromapDesc</code>		139
<code>OptixDisplacementMicromapHistogramEntry</code>	Displacement micromap histogram entry. Specifies how many displacement micromaps of a specific type are input to the displacement micromap array build. Note that while this is similar to <code>OptixDisplacementMicromapUsageCount</code> , the histogram entry specifies how many displacement micromaps of a specific type are combined into a displacement micromap array	139
<code>OptixDisplacementMicromapUsageCount</code>	Displacement micromap usage count for acceleration structure builds. Specifies how many displacement micromaps of a specific type are referenced by triangles when building the AS. Note that while this is similar to <code>OptixDisplacementMicromapHistogramEntry</code> , the usage count specifies how many displacement micromaps of a specific type are referenced by triangles in the AS	140
<code>OptixFunctionTable</code>	The function table containing all API functions	141
<code>OptixImage2D</code>	Image descriptor used by the denoiser	150

<code>OptixInstance</code>	
Instances	151
<code>OptixMatrixMotionTransform</code>	
Represents a matrix motion transformation	152
<code>OptixMicromapBuffers</code>	
Buffer inputs for opacity/displacement micromap array builds	153
<code>OptixMicromapBufferSizes</code>	
Conservative memory requirements for building a opacity/displacement micromap array	154
<code>OptixModuleCompileBoundValueEntry</code>	
Struct for specifying specializations for pipelineParams as specified in <code>OptixPipelineCompileOptions::pipelineLaunchParamsVariableName</code>	154
<code>OptixModuleCompileOptions</code>	
Compilation options for module	155
<code>OptixMotionOptions</code>	
Motion options	157
<code>OptixOpacityMicromapArrayBuildInput</code>	
Inputs to opacity micromap array construction	157
<code>OptixOpacityMicromapDesc</code>	
Opacity micromap descriptor	158
<code>OptixOpacityMicromapHistogramEntry</code>	
Opacity micromap histogram entry. Specifies how many opacity micromaps of a specific type are input to the opacity micromap array build. Note that while this is similar to <code>OptixOpacityMicromapUsageCount</code> , the histogram entry specifies how many opacity micromaps of a specific type are combined into a opacity micromap array	159
<code>OptixOpacityMicromapUsageCount</code>	
Opacity micromap usage count for acceleration structure builds. Specifies how many opacity micromaps of a specific type are referenced by triangles when building the AS. Note that while this is similar to <code>OptixOpacityMicromapHistogramEntry</code> , the usage count specifies how many opacity micromaps of a specific type are referenced by triangles in the AS	160
<code>OptixPayloadType</code>	
Specifies a single payload type	160
<code>OptixPipelineCompileOptions</code>	
Compilation options for all modules of a pipeline	161
<code>OptixPipelineLinkOptions</code>	
Link options for a pipeline	162
<code>OptixProgramGroupCallables</code>	
Program group representing callables	162
<code>OptixProgramGroupDesc</code>	
Descriptor for program groups	163
<code>OptixProgramGroupHitgroup</code>	
Program group representing the hitgroup	164

<code>OptixProgramGroupOptions</code>	
Program group options	165
<code>OptixProgramGroupSingleModule</code>	
Program group representing a single module	166
<code>OptixRelocateInput</code>	
Relocation inputs	166
<code>OptixRelocateInputInstanceArray</code>	
Instance and instance pointer inputs	167
<code>OptixRelocateInputOpacityMicromap</code>	168
<code>OptixRelocateInputTriangleArray</code>	
Triangle inputs	168
<code>OptixRelocationInfo</code>	
Used to store information related to relocation of optix data structures	169
<code>OptixShaderBindingTable</code>	
Describes the shader binding table (SBT)	169
<code>OptixSRTData</code>	
Represents an SRT transformation	171
<code>OptixSRTMotionTransform</code>	
Represents an SRT motion transformation	173
<code>OptixStackSizes</code>	
Describes the stack size requirements of a program group	174
<code>OptixStaticTransform</code>	
Static transform	175
<code>OptixUtilDenoiserImageTile</code>	
Tile definition	176
<code>optix_internal::TypePack&lt;... &gt;</code>	176

## 4 File Index

### 4.1 File List

Here is a list of all files with brief descriptions:

<code>optix_device_impl.h</code>	
OptiX public API	176
<code>optix_device_impl_transformations.h</code>	
OptiX public API	243
<code>optix_micromap_impl.h</code>	
OptiX micromap helper functions	251
<code>optix.h</code>	
OptiX public API header	255
<code>optix_denoiser_tiling.h</code>	
OptiX public API header	256



<a href="#">optix_device.h</a>	
OptiX public API header	261
<a href="#">optix_function_table.h</a>	
OptiX public API header	277
<a href="#">optix_function_table_definition.h</a>	
OptiX public API header	282
<a href="#">optix_host.h</a>	
OptiX public API header	283
<a href="#">optix_micromap.h</a>	
OptiX micromap helper functions	315
<a href="#">optix_stack_size.h</a>	
OptiX public API header	317
<a href="#">optix_stubs.h</a>	
OptiX public API header	322
<a href="#">optix_types.h</a>	
OptiX public API header	334

## 5 Module Documentation

### 5.1 Device API

#### Functions

- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTrace (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTraverse (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTrace (OptixPayloadTypeID type, OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTraverse (OptixPayloadTypeID type, OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)`
- `static __forceinline__ __device__ void optixReorder (unsigned int coherenceHint, unsigned int numCoherenceHintBitsFromLSB)`
- `static __forceinline__ __device__ void optixReorder ()`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixInvoke (Payload &... payload)`
- `template<typename... Payload>`

- ```
static __forceinline__ __device__ void optixInvoke (OptixPayloadTypeID type, Payload &...
payload)
```
- `template<typename... RegAttributes>`  
`static __forceinline__ __device__ void optixMakeHitObject (OptixTraversableHandle handle,`  
`float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int SBTOffset,`  
`unsigned int SBTStride, unsigned int instIdx, unsigned int sbtGASIdx, unsigned int primIdx,`  
`unsigned int hitKind, RegAttributes... regAttributes)`
  - `template<typename... RegAttributes>`  
`static __forceinline__ __device__ void optixMakeHitObject (OptixTraversableHandle handle,`  
`float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int SBTOffset,`  
`unsigned int SBTStride, unsigned int instIdx, const OptixTraversableHandle *transforms,`  
`unsigned int numTransforms, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int`  
`hitKind, RegAttributes... regAttributes)`
  - `template<typename... RegAttributes>`  
`static __forceinline__ __device__ void optixMakeHitObjectWithRecord (OptixTraversableHandle`  
`handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int`  
`sbtRecordIndex, unsigned int instIdx, const OptixTraversableHandle *transforms, unsigned int`  
`numTransforms, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind,`  
`RegAttributes... regAttributes)`
  - `static __forceinline__ __device__ void optixMakeMissHitObject (unsigned int missSBTIndex,`  
`float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime)`
  - `static __forceinline__ __device__ void optixMakeNopHitObject ()`
  - `static __forceinline__ __device__ bool optixHitObjectIsHit ()`
  - `static __forceinline__ __device__ bool optixHitObjectIsMiss ()`
  - `static __forceinline__ __device__ bool optixHitObjectIsNop ()`
  - `static __forceinline__ __device__ unsigned int optixHitObjectGetSbtRecordIndex ()`
  - `static __forceinline__ __device__ void optixSetPayload_0 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_1 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_2 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_3 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_4 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_5 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_6 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_7 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_8 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_9 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_10 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_11 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_12 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_13 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_14 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_15 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_16 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_17 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_18 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_19 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_20 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_21 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_22 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_23 (unsigned int p)`
  - `static __forceinline__ __device__ void optixSetPayload_24 (unsigned int p)`

- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_25 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_26 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_27 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_28 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_29 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_30 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_31 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_0 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_1 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_2 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_3 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_4 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_5 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_6 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_7 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_8 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_9 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_10 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_11 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_12 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_13 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_14 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_15 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_16 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_17 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_18 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_19 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_20 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_21 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_22 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_23 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_24 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_25 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_26 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_27 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_28 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_29 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_30 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_31 ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayloadTypes (unsigned int typeMask)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixUndefinedValue ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetWorldRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixHitObjectGetWorldRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetWorldRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixHitObjectGetWorldRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetObjectRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetObjectRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTmin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixHitObjectGetRayTmin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTmax ()

- static \_\_forceinline\_\_ \_\_device\_\_ float optixHitObjectGetRayTmax ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTime ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixHitObjectGetRayTime ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetRayFlags ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetRayVisibilityMask ()
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetInstanceTraversableFromIAS (OptixTraversableHandle ias, unsigned int instIdx)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetTriangleVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float3 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetMicroTriangleVertexData (float3 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetMicroTriangleBarycentricsData (float2 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetLinearCurveVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[2])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetQuadraticBSplineVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCubicBSplineVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCatmullRomVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCubicBezierVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetRibbonVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetRibbonNormal (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float2 ribbonParameters)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetSphereData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[1])
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetGASTraversableHandle ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetGASMotionTimeBegin (OptixTraversableHandle gas)
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetGASMotionTimeEnd (OptixTraversableHandle gas)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetGASMotionStepCount (OptixTraversableHandle gas)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetWorldToObjectTransformMatrix (float m[12])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetObjectToWorldTransformMatrix (float m[12])
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformPointFromWorldToObjectSpace (float3 point)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformVectorFromWorldToObjectSpace (float3 vec)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformNormalFromWorldToObjectSpace (float3 normal)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformPointFromObjectToWorldSpace (float3 point)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformVectorFromObjectToWorldSpace (float3 vec)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformNormalFromObjectToWorldSpace (float3 normal)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetTransformListSize ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetTransformListSize ()

- static `__forceinline__ __device__ OptixTraversableHandle optixGetTransformListHandle` (unsigned int index)
- static `__forceinline__ __device__ OptixTraversableHandle optixHitObjectGetTransformListHandle` (unsigned int index)
- static `__forceinline__ __device__ OptixTransformType optixGetTransformTypeFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const OptixStaticTransform * optixGetStaticTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const OptixSRTMotionTransform * optixGetSRTMotionTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const OptixMatrixMotionTransform * optixGetMatrixMotionTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ unsigned int optixGetInstanceIdFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ OptixTraversableHandle optixGetInstanceChildFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const float4 * optixGetInstanceTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const float4 * optixGetInstanceInverseTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5, unsigned int a6)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5, unsigned int a6, unsigned int a7)
- static `__forceinline__ __device__ unsigned int optixGetAttribute_0` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_1` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_2` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_3` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_4` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_5` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_6` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_7` ()
- static `__forceinline__ __device__ unsigned int optixHitObjectGetAttribute_0` ()
- static `__forceinline__ __device__ unsigned int optixHitObjectGetAttribute_1` ()
- static `__forceinline__ __device__ unsigned int optixHitObjectGetAttribute_2` ()



- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetAttribute\_3 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetAttribute\_4 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetAttribute\_5 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetAttribute\_6 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetAttribute\_7 ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixTerminateRay ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixIgnoreIntersection ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPrimitiveIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetPrimitiveIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetSbtGASIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetSbtGASIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetInstanceId ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetInstanceId ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetInstanceIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetInstanceIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetHitKind ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetHitKind ()
- static \_\_forceinline\_\_ \_\_device\_\_ OptixPrimitiveType optixGetPrimitiveType (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsFrontFaceHit (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsBackFaceHit (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ OptixPrimitiveType optixGetPrimitiveType ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsFrontFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsBackFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsTriangleHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsTriangleFrontFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsTriangleBackFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsDisplacedMicromeshTriangleHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsDisplacedMicromeshTriangleFrontFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsDisplacedMicromeshTriangleBackFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ float2 optixGetTriangleBarycentrics ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetCurveParameter ()
- static \_\_forceinline\_\_ \_\_device\_\_ float2 optixGetRibbonParameters ()
- static \_\_forceinline\_\_ \_\_device\_\_ uint3 optixGetLaunchIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ uint3 optixGetLaunchDimensions ()
- static \_\_forceinline\_\_ \_\_device\_\_ CUdeviceptr optixGetSbtDataPointer ()
- static \_\_forceinline\_\_ \_\_device\_\_ CUdeviceptr optixHitObjectGetSbtDataPointer ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4)

- static `__forceinline__ __device__ void optixThrowException` (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5)
- static `__forceinline__ __device__ void optixThrowException` (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int exceptionDetail6)
- static `__forceinline__ __device__ void optixThrowException` (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int exceptionDetail6, unsigned int exceptionDetail7)
- static `__forceinline__ __device__ int optixGetExceptionCode` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_0` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_1` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_2` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_3` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_4` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_5` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_6` ()
- static `__forceinline__ __device__ unsigned int optixGetExceptionDetail_7` ()
- static `__forceinline__ __device__ char * optixGetExceptionLineInfo` ()
- template<typename ReturnT , typename... ArgTypes>  
static `__forceinline__ __device__ ReturnT optixDirectCall` (unsigned int sbtIndex, ArgTypes... args)
- template<typename ReturnT , typename... ArgTypes>  
static `__forceinline__ __device__ ReturnT optixContinuationCall` (unsigned int sbtIndex, ArgTypes... args)
- static `__forceinline__ __device__ uint4 optixTexFootprint2D` (unsigned long long tex, unsigned int texInfo, float x, float y, unsigned int \*singleMipLevel)
- static `__forceinline__ __device__ uint4 optixTexFootprint2DLod` (unsigned long long tex, unsigned int texInfo, float x, float y, float level, bool coarse, unsigned int \*singleMipLevel)
- static `__forceinline__ __device__ uint4 optixTexFootprint2DGrad` (unsigned long long tex, unsigned int texInfo, float x, float y, float dPdx\_x, float dPdx\_y, float dPdy\_x, float dPdy\_y, bool coarse, unsigned int \*singleMipLevel)

### 5.1.1 Detailed Description

OptiX Device API.

### 5.1.2 Function Documentation

#### 5.1.2.1 optixContinuationCall()

```
template<typename ReturnT , typename... ArgTypes>
static __forceinline__ __device__ ReturnT optixContinuationCall (
    unsigned int sbtIndex,
    ArgTypes... args ) [static]
```

Creates a call to the continuation callable program at the specified SBT entry.

This will call the program that was specified in the `OptixProgramGroupCallables::entryFunctionNameCC` in the module specified by `OptixProgramGroupCallables::moduleCC`.

The address of the SBT entry is calculated by: `OptixShaderBindingTable::callablesRecordBase + (OptixShaderBindingTable::callablesRecordStrideInBytes * sbtIndex)`.

As opposed to direct callable programs, continuation callable programs are allowed to make secondary `optixTrace` calls.

Behavior is undefined if there is no continuation callable program at the specified SBT entry.

Behavior is undefined if the number of arguments that are being passed in does not match the number of parameters expected by the program that is called. In validation mode an exception will be generated.

#### Parameters

|    |                 |                                                                                                                                                  |
|----|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>sbtIndex</i> | The offset of the SBT entry of the continuation callable program to call relative to <code>OptixShaderBindingTable::callablesRecordBase</code> . |
| in | <i>args</i>     | The arguments to pass to the continuation callable program.                                                                                      |

Available in RG, CH, MS, CC

### 5.1.2.2 `optixDirectCall()`

```
template<typename ReturnT , typename... ArgTypes>
static __forceinline__ __device__ ReturnT optixDirectCall (
    unsigned int sbtIndex,
    ArgTypes... args ) [static]
```

Creates a call to the direct callable program at the specified SBT entry.

This will call the program that was specified in the `OptixProgramGroupCallables::entryFunctionNameDC` in the module specified by `OptixProgramGroupCallables::moduleDC`.

The address of the SBT entry is calculated by: `OptixShaderBindingTable::callablesRecordBase + (OptixShaderBindingTable::callablesRecordStrideInBytes * sbtIndex)`.

Direct callable programs are allowed to call `optixTrace`, but any secondary trace calls invoked from subsequently called CH, MS and callable programs will result an an error.

Behavior is undefined if there is no direct callable program at the specified SBT entry.

Behavior is undefined if the number of arguments that are being passed in does not match the number of parameters expected by the program that is called. In validation mode an exception will be generated.

#### Parameters

|    |                 |                                                                                                                                            |
|----|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------|
| in | <i>sbtIndex</i> | The offset of the SBT entry of the direct callable program to call relative to <code>OptixShaderBindingTable::callablesRecordBase</code> . |
| in | <i>args</i>     | The arguments to pass to the direct callable program.                                                                                      |

Available in RG, IS, AH, CH, MS, DC, CC

### 5.1.2.3 `optixGetAttribute_0()`

```
static __forceinline__ __device__ unsigned int optixGetAttribute_0 ( ) [static]
```

Returns the attribute at the given slot index. There are up to 8 attributes available. The number of attributes is configured with `OptixPipelineCompileOptions::numAttributeValues`.



Available in AH, CH

#### 5.1.2.4 optixGetAttribute\_1()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_1 ( ) [static]
```

#### 5.1.2.5 optixGetAttribute\_2()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_2 ( ) [static]
```

#### 5.1.2.6 optixGetAttribute\_3()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_3 ( ) [static]
```

#### 5.1.2.7 optixGetAttribute\_4()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_4 ( ) [static]
```

#### 5.1.2.8 optixGetAttribute\_5()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_5 ( ) [static]
```

#### 5.1.2.9 optixGetAttribute\_6()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_6 ( ) [static]
```

#### 5.1.2.10 optixGetAttribute\_7()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_7 ( ) [static]
```

#### 5.1.2.11 optixGetCatmullRomVertexData()

```
static __forceinline__ __device__ void optixGetCatmullRomVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[4] ) [static]
```

Return the object space curve control vertex data of a CatmullRom spline curve in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS`.

$data[i] = \{x, y, z, w\}$  with  $\{x, y, z\}$  the position and  $w$  the radius of control vertex  $i$ .

If motion is disabled via `OptixPipelineCompileOptions::usesMotionBlur`, or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

#### 5.1.2.12 optixGetCubicBezierVertexData()

```
static __forceinline__ __device__ void optixGetCubicBezierVertexData (
    OptixTraversableHandle gas,
```

```

    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[4] ) [static]

```

Return the object space curve control vertex data of a cubic Bezier curve in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS`.

$data[i] = \{x, y, z, w\}$  with  $\{x, y, z\}$  the position and  $w$  the radius of control vertex  $i$ .

If motion is disabled via `OptixPipelineCompileOptions::usesMotionBlur`, or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

#### 5.1.2.13 optixGetCubicBSplineVertexData()

```

static __forceinline__ __device__ void optixGetCubicBSplineVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[4] ) [static]

```

Return the object space curve control vertex data of a cubic BSpline curve in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS`.

$data[i] = \{x, y, z, w\}$  with  $\{x, y, z\}$  the position and  $w$  the radius of control vertex  $i$ .

If motion is disabled via `OptixPipelineCompileOptions::usesMotionBlur`, or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

#### 5.1.2.14 optixGetCurveParameter()

```

static __forceinline__ __device__ float optixGetCurveParameter ( ) [static]

```

Returns the curve parameter associated with the current intersection when using `OptixBuildInputCurveArray` objects.

Available in AH, CH

#### 5.1.2.15 optixGetExceptionCode()

```

static __forceinline__ __device__ int optixGetExceptionCode ( ) [static]

```

Returns the exception code.

Available in EX

#### 5.1.2.16 optixGetExceptionDetail\_0()

```

static __forceinline__ __device__ unsigned int optixGetExceptionDetail_0 ( )

```

*[static]*

Returns the 32-bit exception detail at slot 0.

The behavior is undefined if the exception is not a user exception, or the used overload [optixThrowException\(\)](#) did not provide the queried exception detail.

Available in EX

#### 5.1.2.17 [optixGetExceptionDetail\\_1\(\)](#)

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_1 ( )  
[static]
```

Returns the 32-bit exception detail at slot 1.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

#### 5.1.2.18 [optixGetExceptionDetail\\_2\(\)](#)

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_2 ( )  
[static]
```

Returns the 32-bit exception detail at slot 2.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

#### 5.1.2.19 [optixGetExceptionDetail\\_3\(\)](#)

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_3 ( )  
[static]
```

Returns the 32-bit exception detail at slot 3.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

#### 5.1.2.20 [optixGetExceptionDetail\\_4\(\)](#)

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_4 ( )  
[static]
```

Returns the 32-bit exception detail at slot 4.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

#### 5.1.2.21 [optixGetExceptionDetail\\_5\(\)](#)

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_5 ( )  
[static]
```

Returns the 32-bit exception detail at slot 5.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

#### 5.1.2.22 [optixGetExceptionDetail\\_6\(\)](#)

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_6 ( )  
[static]
```

Returns the 32-bit exception detail at slot 6.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

### 5.1.2.23 optixGetExceptionDetail\_7()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_7 ( )  
[static]
```

Returns the 32-bit exception detail at slot 7.

See also [optixGetExceptionDetail\\_0\(\)](#) Available in EX

### 5.1.2.24 optixGetExceptionLineInfo()

```
static __forceinline__ __device__ char * optixGetExceptionLineInfo ( ) [static]
```

Returns a string that includes information about the source location that caused the current exception.

The source location is only available for exceptions of type `OPTIX_EXCEPTION_CODE_CALLABLE_PARAMETER_MISMATCH`, `OPTIX_EXCEPTION_CODE_UNSUPPORTED_PRIMITIVE_TYPE`, `OPTIX_EXCEPTION_CODE_INVALID_RAY`, and for user exceptions. Line information needs to be present in the input PTX and [OptixModuleCompileOptions::debugLevel](#) may not be set to `OPTIX_COMPILE_DEBUG_LEVEL_NONE`.

Returns a NULL pointer if no line information is available.

Available in EX

### 5.1.2.25 optixGetGASMotionStepCount()

```
static __forceinline__ __device__ unsigned int optixGetGASMotionStepCount (   
    OptixTraversableHandle gas ) [static]
```

Returns the number of motion steps of a GAS (see [OptixMotionOptions](#))

Available in all OptiX program types

### 5.1.2.26 optixGetGASMotionTimeBegin()

```
static __forceinline__ __device__ float optixGetGASMotionTimeBegin (   
    OptixTraversableHandle gas ) [static]
```

Returns the motion begin time of a GAS (see [OptixMotionOptions](#))

Available in all OptiX program types

### 5.1.2.27 optixGetGASMotionTimeEnd()

```
static __forceinline__ __device__ float optixGetGASMotionTimeEnd (   
    OptixTraversableHandle gas ) [static]
```

Returns the motion end time of a GAS (see [OptixMotionOptions](#))

Available in all OptiX program types

### 5.1.2.28 optixGetGASTraversableHandle()

```
static __forceinline__ __device__ OptixTraversableHandle  
optixGetGASTraversableHandle ( ) [static]
```

Returns the traversable handle for the Geometry Acceleration Structure (GAS) containing the current hit.

Available in IS, AH, CH

### 5.1.2.29 optixGetHitKind()

```
static __forceinline__ __device__ unsigned int optixGetHitKind ( ) [static]
```

Returns the 8 bit hit kind associated with the current hit.

Use [optixGetPrimitiveType\(\)](#) to interpret the hit kind. For custom intersections (primitive type OPTIX\_PRIMITIVE\_TYPE\_CUSTOM), this is the 7-bit hitKind passed to [optixReportIntersection\(\)](#). Hit kinds greater than 127 are reserved for built-in primitives.

Available in AH and CH

### 5.1.2.30 optixGetInstanceChildFromHandle()

```
static __forceinline__ __device__ OptixTraversableHandle  
optixGetInstanceChildFromHandle (   
    OptixTraversableHandle handle ) [static]
```

Returns child traversable handle from an [OptixInstance](#) traversable.

Returns 0 if the traversable handle does not reference an [OptixInstance](#).

Available in all OptiX program types

### 5.1.2.31 optixGetInstanceId()

```
static __forceinline__ __device__ unsigned int optixGetInstanceId ( ) [static]
```

Returns the [OptixInstance::instanceId](#) of the instance within the top level acceleration structure associated with the current intersection.

When building an acceleration structure using [OptixBuildInputInstanceArray](#) each [OptixInstance](#) has a user supplied instanceId. [OptixInstance](#) objects reference another acceleration structure. During traversal the acceleration structures are visited top down. In the IS and AH programs the [OptixInstance::instanceId](#) corresponding to the most recently visited [OptixInstance](#) is returned when calling [optixGetInstanceId\(\)](#). In CH [optixGetInstanceId\(\)](#) returns the [OptixInstance::instanceId](#) when the hit was recorded with [optixReportIntersection](#). In the case where there is no [OptixInstance](#) visited, [optixGetInstanceId](#) returns 0

Available in IS, AH, CH

### 5.1.2.32 optixGetInstanceIdFromHandle()

```
static __forceinline__ __device__ unsigned int optixGetInstanceIdFromHandle  
(   
    OptixTraversableHandle handle ) [static]
```

Returns instanceId from an [OptixInstance](#) traversable.

Returns 0 if the traversable handle does not reference an [OptixInstance](#).

Available in all OptiX program types

### 5.1.2.33 optixGetInstanceIndex()

```
static __forceinline__ __device__ unsigned int optixGetInstanceIndex ( )  
[static]
```

Returns the zero-based index of the instance within its instance acceleration structure associated with the current intersection.

In the IS and AH programs the index corresponding to the most recently visited `OptixInstance` is returned when calling `optixGetInstanceIndex()`. In CH `optixGetInstanceIndex()` returns the index when the hit was recorded with `optixReportIntersection`. In the case where there is no `OptixInstance` visited, `optixGetInstanceIndex` returns 0

Available in IS, AH, CH

#### 5.1.2.34 `optixGetInstanceInverseTransformFromHandle()`

```
static __forceinline__ __device__ const float4 *
optixGetInstanceInverseTransformFromHandle (
    OptixTraversableHandle handle ) [static]
```

Returns world-to-object transform from an `OptixInstance` traversable.

Returns 0 if the traversable handle does not reference an `OptixInstance`.

Available in all OptiX program types

#### 5.1.2.35 `optixGetInstanceTransformFromHandle()`

```
static __forceinline__ __device__ const float4 *
optixGetInstanceTransformFromHandle (
    OptixTraversableHandle handle ) [static]
```

Returns object-to-world transform from an `OptixInstance` traversable.

Returns 0 if the traversable handle does not reference an `OptixInstance`.

Available in all OptiX program types

#### 5.1.2.36 `optixGetInstanceTraversableFromIAS()`

```
static __forceinline__ __device__ OptixTraversableHandle
optixGetInstanceTraversableFromIAS (
    OptixTraversableHandle ias,
    unsigned int instIdx ) [static]
```

Return the traversable handle of a given instance in an Instance Acceleration Structure (IAS)

To obtain instance traversables by index, the IAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS`.

Available in all OptiX program types

#### 5.1.2.37 `optixGetLaunchDimensions()`

```
static __forceinline__ __device__ uint3 optixGetLaunchDimensions ( ) [static]
```

Available in any program, it returns the dimensions of the current launch specified by `optixLaunch` on the host.

Available in all OptiX program types

#### 5.1.2.38 `optixGetLaunchIndex()`

```
static __forceinline__ __device__ uint3 optixGetLaunchIndex ( ) [static]
```

Available in any program, it returns the current launch index within the launch dimensions specified by `optixLaunch` on the host.

The raygen program is typically only launched once per launch index.

Available in all OptiX program types

#### 5.1.2.39 optixGetLinearCurveVertexData()

```
static __forceinline__ __device__ void optixGetLinearCurveVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[2] ) [static]
```

Return the object space curve control vertex data of a linear curve in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag OPTIX\_BUILD\_FLAG\_ALLOW\_RANDOM\_VERTEX\_ACCESS.

data[i] = {x,y,z,w} with {x,y,z} the position and w the radius of control vertex i.

If motion is disabled via [OptixPipelineCompileOptions::usesMotionBlur](#), or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

#### 5.1.2.40 optixGetMatrixMotionTransformFromHandle()

```
static __forceinline__ __device__ const OptixMatrixMotionTransform *
optixGetMatrixMotionTransformFromHandle (
    OptixTraversableHandle handle ) [static]
```

Returns a pointer to a [OptixMatrixMotionTransform](#) from its traversable handle.

Returns 0 if the traversable is not of type OPTIX\_TRANSFORM\_TYPE\_MATRIX\_MOTION\_TRANSFORM.

Available in all OptiX program types

#### 5.1.2.41 optixGetMicroTriangleBarycentricsData()

```
static __forceinline__ __device__ void optixGetMicroTriangleBarycentricsData
(
    float2 data[3] ) [static]
```

Returns the barycentrics of the vertices of the currently intersected micro triangle with respect to the base triangle.

Available in all OptiX program types

#### 5.1.2.42 optixGetMicroTriangleVertexData()

```
static __forceinline__ __device__ void optixGetMicroTriangleVertexData (
    float3 data[3] ) [static]
```

Return the object space micro triangle vertex positions of the current hit. The current hit must be a displacement micromap triangle hit.

Available in all OptiX program types

#### 5.1.2.43 optixGetObjectRayDirection()

```
static __forceinline__ __device__ float3 optixGetObjectRayDirection ( )  
[static]
```

Returns the current object space ray direction based on the current transform stack.

Available in IS and AH

#### 5.1.2.44 optixGetObjectRayOrigin()

```
static __forceinline__ __device__ float3 optixGetObjectRayOrigin ( ) [static]
```

Returns the current object space ray origin based on the current transform stack.

Available in IS and AH

#### 5.1.2.45 optixGetObjectToWorldTransformMatrix()

```
static __forceinline__ __device__ void optixGetObjectToWorldTransformMatrix  
(  
    float m[12] ) [static]
```

Returns the object-to-world transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

#### 5.1.2.46 optixGetPayload\_0()

```
static __forceinline__ __device__ unsigned int optixGetPayload_0 ( ) [static]
```

Returns the 32-bit payload at the given slot index. There are up to 32 attributes available. The number of attributes is configured with [OptixPipelineCompileOptions::numPayloadValues](#) or with [OptixPayloadType](#) parameters set in [OptixModuleCompileOptions](#).

Available in IS, AH, CH, MS

#### 5.1.2.47 optixGetPayload\_1()

```
static __forceinline__ __device__ unsigned int optixGetPayload_1 ( ) [static]
```

#### 5.1.2.48 optixGetPayload\_10()

```
static __forceinline__ __device__ unsigned int optixGetPayload_10 ( ) [static]
```

#### 5.1.2.49 optixGetPayload\_11()

```
static __forceinline__ __device__ unsigned int optixGetPayload_11 ( ) [static]
```

#### 5.1.2.50 optixGetPayload\_12()

```
static __forceinline__ __device__ unsigned int optixGetPayload_12 ( ) [static]
```

#### 5.1.2.51 optixGetPayload\_13()

```
static __forceinline__ __device__ unsigned int optixGetPayload_13 ( ) [static]
```



#### 5.1.2.52 optixGetPayload\_14()

```
static __forceinline__ __device__ unsigned int optixGetPayload_14 ( ) [static]
```

#### 5.1.2.53 optixGetPayload\_15()

```
static __forceinline__ __device__ unsigned int optixGetPayload_15 ( ) [static]
```

#### 5.1.2.54 optixGetPayload\_16()

```
static __forceinline__ __device__ unsigned int optixGetPayload_16 ( ) [static]
```

#### 5.1.2.55 optixGetPayload\_17()

```
static __forceinline__ __device__ unsigned int optixGetPayload_17 ( ) [static]
```

#### 5.1.2.56 optixGetPayload\_18()

```
static __forceinline__ __device__ unsigned int optixGetPayload_18 ( ) [static]
```

#### 5.1.2.57 optixGetPayload\_19()

```
static __forceinline__ __device__ unsigned int optixGetPayload_19 ( ) [static]
```

#### 5.1.2.58 optixGetPayload\_2()

```
static __forceinline__ __device__ unsigned int optixGetPayload_2 ( ) [static]
```

#### 5.1.2.59 optixGetPayload\_20()

```
static __forceinline__ __device__ unsigned int optixGetPayload_20 ( ) [static]
```

#### 5.1.2.60 optixGetPayload\_21()

```
static __forceinline__ __device__ unsigned int optixGetPayload_21 ( ) [static]
```

#### 5.1.2.61 optixGetPayload\_22()

```
static __forceinline__ __device__ unsigned int optixGetPayload_22 ( ) [static]
```

#### 5.1.2.62 optixGetPayload\_23()

```
static __forceinline__ __device__ unsigned int optixGetPayload_23 ( ) [static]
```

#### 5.1.2.63 optixGetPayload\_24()

```
static __forceinline__ __device__ unsigned int optixGetPayload_24 ( ) [static]
```

#### 5.1.2.64 optixGetPayload\_25()

```
static __forceinline__ __device__ unsigned int optixGetPayload_25 ( ) [static]
```

#### 5.1.2.65 optixGetPayload\_26()

```
static __forceinline__ __device__ unsigned int optixGetPayload_26 ( ) [static]
```

5.1.2.66 `optixGetPayload_27()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_27 ( ) [static]
```

5.1.2.67 `optixGetPayload_28()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_28 ( ) [static]
```

5.1.2.68 `optixGetPayload_29()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_29 ( ) [static]
```

5.1.2.69 `optixGetPayload_3()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_3 ( ) [static]
```

5.1.2.70 `optixGetPayload_30()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_30 ( ) [static]
```

5.1.2.71 `optixGetPayload_31()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_31 ( ) [static]
```

5.1.2.72 `optixGetPayload_4()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_4 ( ) [static]
```

5.1.2.73 `optixGetPayload_5()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_5 ( ) [static]
```

5.1.2.74 `optixGetPayload_6()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_6 ( ) [static]
```

5.1.2.75 `optixGetPayload_7()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_7 ( ) [static]
```

5.1.2.76 `optixGetPayload_8()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_8 ( ) [static]
```

5.1.2.77 `optixGetPayload_9()`

```
static __forceinline__ __device__ unsigned int optixGetPayload_9 ( ) [static]
```

5.1.2.78 `optixGetPrimitiveIndex()`

```
static __forceinline__ __device__ unsigned int optixGetPrimitiveIndex ( )  
[static]
```

For a given [OptixBuildInputTriangleArray](#) the number of primitives is defined as.

```
"(OptixBuildInputTriangleArray::indexBuffer == 0) ? OptixBuildInputTriangleArray::numVertices/3 :  
OptixBuildInputTriangleArray::numIndexTriplets;"
```

For a given `OptixBuildInputCustomPrimitiveArray` the number of primitives is defined as `numAabbs`.

The primitive index returns the index into the array of primitives plus the `primitiveIndexOffset`.

In IS and AH this corresponds to the currently intersected primitive.

In CH this corresponds to the primitive index of the closest intersected primitive.

Available in IS, AH, CH, EX

#### 5.1.2.79 `optixGetPrimitiveType()` [1/2]

```
static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType (
) [static]
```

Function interpreting the hit kind associated with the current `optixReportIntersection`.

Available in AH, CH

#### 5.1.2.80 `optixGetPrimitiveType()` [2/2]

```
static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType (
    unsigned int hitKind ) [static]
```

Function interpreting the result of `optixGetHitKind()`.

Available in all OptiX program types

#### 5.1.2.81 `optixGetQuadraticBSplineVertexData()`

```
static __forceinline__ __device__ void optixGetQuadraticBSplineVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[3] ) [static]
```

Return the object space curve control vertex data of a quadratic BSpline curve in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS`.

`data[i] = {x,y,z,w}` with `{x,y,z}` the position and `w` the radius of control vertex `i`.

If motion is disabled via `OptixPipelineCompileOptions::usesMotionBlur`, or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

#### 5.1.2.82 `optixGetRayFlags()`

```
static __forceinline__ __device__ unsigned int optixGetRayFlags ( ) [static]
```

Returns the `rayFlags` passed into `optixTrace`.

Available in IS, AH, CH, MS

#### 5.1.2.83 `optixGetRayTime()`

```
static __forceinline__ __device__ float optixGetRayTime ( ) [static]
```

Returns the rayTime passed into optixTrace.

Returns 0 if motion is disabled.

Available in IS, AH, CH, MS

#### 5.1.2.84 optixGetRayTmax()

```
static __forceinline__ __device__ float optixGetRayTmax ( ) [static]
```

In IS and CH returns the current smallest reported hitT or the tmax passed into optixTrace if no hit has been reported.

In AH returns the hitT value as passed in to optixReportIntersection

In MS returns the tmax passed into optixTrace

Available in IS, AH, CH, MS

#### 5.1.2.85 optixGetRayTmin()

```
static __forceinline__ __device__ float optixGetRayTmin ( ) [static]
```

Returns the tmin passed into optixTrace.

Available in IS, AH, CH, MS

#### 5.1.2.86 optixGetRayVisibilityMask()

```
static __forceinline__ __device__ unsigned int optixGetRayVisibilityMask ( ) [static]
```

Returns the visibilityMask passed into optixTrace.

Available in IS, AH, CH, MS

#### 5.1.2.87 optixGetRibbonNormal()

```
static __forceinline__ __device__ float3 optixGetRibbonNormal (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float2 ribbonParameters ) [static]
```

Return ribbon normal at intersection reported by optixReportIntersection.

Available in all OptiX program types

#### 5.1.2.88 optixGetRibbonParameters()

```
static __forceinline__ __device__ float2 optixGetRibbonParameters ( ) [static]
```

Returns the ribbon parameters along directrix (length) and generator (width) of the current intersection when using [OptixBuildInputCurveArray](#) objects with curveType OPTIX\_PRIMITIVE\_TYPE\_FLAT\_QUADRATIC\_BSPLINE.

Available in AH, CH

### 5.1.2.89 optixGetRibbonVertexData()

```
static __forceinline__ __device__ void optixGetRibbonVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[3] ) [static]
```

Return the object space curve control vertex data of a ribbon (flat quadratic BSpline) in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS`.

$data[i] = \{x, y, z, w\}$  with  $\{x, y, z\}$  the position and  $w$  the radius of control vertex  $i$ .

If motion is disabled via `OptixPipelineCompileOptions::usesMotionBlur`, or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

### 5.1.2.90 optixGetSbtDataPointer()

```
static __forceinline__ __device__ CUdeviceptr optixGetSbtDataPointer ( )
[static]
```

Returns the generic memory space pointer to the data region (past the header) of the currently active SBT record corresponding to the current program.

Available in RG, IS, AH, CH, MS, EX, DC(excluding optix enabled functions), CC

### 5.1.2.91 optixGetSbtGASIndex()

```
static __forceinline__ __device__ unsigned int optixGetSbtGASIndex ( ) [static]
```

Returns the Sbt GAS index of the primitive associated with the current intersection.

In IS and AH this corresponds to the currently intersected primitive.

In CH this corresponds to the SBT GAS index of the closest intersected primitive.

In EX with exception code `OPTIX_EXCEPTION_CODE_TRAVERSAL_INVALID_HIT_SBT` corresponds to the sbt index within the hit GAS. Returns zero for all other exceptions.

Available in IS, AH, CH, EX

### 5.1.2.92 optixGetSphereData()

```
static __forceinline__ __device__ void optixGetSphereData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[1] ) [static]
```

Return the object space sphere data, center point and radius, in a Geometry Acceleration Structure (GAS) at a given motion time.

To access sphere data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM`

`_VERTEX_ACCESS`.

`data[0] = {x,y,z,w}` with `{x,y,z}` the position of the sphere center and `w` the radius.

If motion is disabled via `OptixPipelineCompileOptions::usesMotionBlur`, or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

#### 5.1.2.93 `optixGetSRTMotionTransformFromHandle()`

```
static __forceinline__ __device__ const OptixSRTMotionTransform *
optixGetSRTMotionTransformFromHandle (
    OptixTraversableHandle handle ) [static]
```

Returns a pointer to a `OptixSRTMotionTransform` from its traversable handle.

Returns 0 if the traversable is not of type `OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM`.

Available in all OptiX program types

#### 5.1.2.94 `optixGetStaticTransformFromHandle()`

```
static __forceinline__ __device__ const OptixStaticTransform *
optixGetStaticTransformFromHandle (
    OptixTraversableHandle handle ) [static]
```

Returns a pointer to a `OptixStaticTransform` from its traversable handle.

Returns 0 if the traversable is not of type `OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM`.

Available in all OptiX program types

#### 5.1.2.95 `optixGetTransformListHandle()`

```
static __forceinline__ __device__ OptixTraversableHandle
optixGetTransformListHandle (
    unsigned int index ) [static]
```

Returns the traversable handle for a transform in the current transform list.

Available in IS, AH, CH, EX

#### 5.1.2.96 `optixGetTransformListSize()`

```
static __forceinline__ __device__ unsigned int optixGetTransformListSize ( )
[static]
```

Returns the number of transforms on the current transform list.

Available in IS, AH, CH, EX

#### 5.1.2.97 `optixGetTransformTypeFromHandle()`

```
static __forceinline__ __device__ OptixTransformType
optixGetTransformTypeFromHandle (
    OptixTraversableHandle handle ) [static]
```

Returns the transform type of a traversable handle from a transform list.

Available in all OptiX program types

### 5.1.2.98 optixGetTriangleBarycentrics()

```
static __forceinline__ __device__ float2 optixGetTriangleBarycentrics ( )  
[static]
```

Convenience function that returns the first two attributes as floats.

When using [OptixBuildInputTriangleArray](#) objects, during intersection the barycentric coordinates are stored into the first two attribute registers.

Available in AH, CH

### 5.1.2.99 optixGetTriangleVertexData()

```
static __forceinline__ __device__ void optixGetTriangleVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float3 data[3] ) [static]
```

Return the object space triangle vertex positions of a given triangle in a Geometry Acceleration Structure (GAS) at a given motion time.

To access vertex data, the GAS must be built using the flag `OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS`.

If motion is disabled via [OptixPipelineCompileOptions::usesMotionBlur](#), or the GAS does not contain motion, the time parameter is ignored.

Available in all OptiX program types

### 5.1.2.100 optixGetWorldRayDirection()

```
static __forceinline__ __device__ float3 optixGetWorldRayDirection ( ) [static]
```

Returns the rayDirection passed into optixTrace.

May be more expensive to call in IS and AH than their object space counterparts, so effort should be made to use the object space ray in those programs.

Available in IS, AH, CH, MS

### 5.1.2.101 optixGetWorldRayOrigin()

```
static __forceinline__ __device__ float3 optixGetWorldRayOrigin ( ) [static]
```

Returns the rayOrigin passed into optixTrace.

May be more expensive to call in IS and AH than their object space counterparts, so effort should be made to use the object space ray in those programs.

Available in IS, AH, CH, MS

### 5.1.2.102 optixGetWorldToObjectTransformMatrix()

```
static __forceinline__ __device__ void optixGetWorldToObjectTransformMatrix (
    float m[12] ) [static]
```

Returns the world-to-object transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

#### 5.1.2.103 optixHitObjectGetAttribute\_0()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_0
( ) [static]
```

Return the attribute at the given slot index for the current outgoing hit object. There are up to 8 attributes available. The number of attributes is configured with [OptixPipelineCompileOptions::numAttributeValues](#).

Results are undefined if the hit object is a miss.

Available in RG, CH, MS, CC, DC

#### 5.1.2.104 optixHitObjectGetAttribute\_1()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_1
( ) [static]
```

#### 5.1.2.105 optixHitObjectGetAttribute\_2()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_2
( ) [static]
```

#### 5.1.2.106 optixHitObjectGetAttribute\_3()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_3
( ) [static]
```

#### 5.1.2.107 optixHitObjectGetAttribute\_4()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_4
( ) [static]
```

#### 5.1.2.108 optixHitObjectGetAttribute\_5()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_5
( ) [static]
```

#### 5.1.2.109 optixHitObjectGetAttribute\_6()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_6
( ) [static]
```

#### 5.1.2.110 optixHitObjectGetAttribute\_7()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_7
( ) [static]
```

#### 5.1.2.111 optixHitObjectGetHitKind()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetHitKind ( )
[static]
```

Returns the 8 bit hit kind associated with the current outgoing hit object.



Results are undefined if the hit object is a miss.

See [optixGetHitKind\(\)](#).

Available in RG, CH, MS, CC, DC

#### 5.1.2.112 optixHitObjectGetInstanceId()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetInstanceId (
) [static]
```

Returns the [OptixInstance::instanceId](#) of the instance within the top level acceleration structure associated with the outgoing hit object.

Results are undefined if the hit object is a miss.

See [optixGetInstanceId\(\)](#).

Available in RG, CH, MS, CC, DC

#### 5.1.2.113 optixHitObjectGetInstanceIndex()

```
static __forceinline__ __device__ unsigned int
optixHitObjectGetInstanceIndex ( ) [static]
```

Returns the zero-based index of the instance within its instance acceleration structure associated with the outgoing hit object.

Results are undefined if the hit object is a miss.

See [optixGetInstanceIndex\(\)](#).

Available in RG, CH, MS, CC, DC

#### 5.1.2.114 optixHitObjectGetPrimitiveIndex()

```
static __forceinline__ __device__ unsigned int
optixHitObjectGetPrimitiveIndex ( ) [static]
```

Return the primitive index associated with the current outgoing hit object.

Results are undefined if the hit object is a miss.

See [optixGetPrimitiveIndex\(\)](#) for more details.

Available in RG, CH, MS, CC, DC

#### 5.1.2.115 optixHitObjectGetRayTime()

```
static __forceinline__ __device__ float optixHitObjectGetRayTime ( ) [static]
```

Returns the rayTime passed into [optixTraverse](#), [optixMakeHitObject](#), [optixMakeHitObjectWithRecord](#), or [optixMakeMissHitObject](#).

Returns 0 for nop hit objects or when motion is disabled.

Available in RG, CH, MS, CC, DC

#### 5.1.2.116 optixHitObjectGetRayTmax()

```
static __forceinline__ __device__ float optixHitObjectGetRayTmax ( ) [static]
```

If the hit object is a hit, returns the smallest reported hitT.

If the hit object is a miss, returns the tmax passed into [optixTraverse](#) or [optixMakeMissHitObject](#).

Returns 0 for nop hit objects.

Available in RG, CH, MS, CC, DC

#### 5.1.2.117 optixHitObjectGetRayTmin()

```
static __forceinline__ __device__ float optixHitObjectGetRayTmin ( ) [static]
```

Returns the tmin passed into `optixTraverse`, `optixMakeHitObject`, `optixMakeHitObjectWithRecord`, or `optixMakeMissHitObject`.

Returns 0.0f for nop hit objects.

Available in RG, CH, MS, CC, DC

#### 5.1.2.118 optixHitObjectGetSbtDataPointer()

```
static __forceinline__ __device__ CUdeviceptr  
optixHitObjectGetSbtDataPointer ( ) [static]
```

Device pointer address for the SBT associated with the hit or miss program for the current outgoing hit object.

Returns 0 for nop hit objects.

Available in RG, CH, MS, CC, DC

#### 5.1.2.119 optixHitObjectGetSbtGASIndex()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetSbtGASIndex  
( ) [static]
```

Return the SBT GAS index of the closest intersected primitive associated with the current outgoing hit object.

Results are undefined if the hit object is a miss.

See `optixGetSbtGASIndex()` for details on the version for the incoming hit object.

Available in RG, CH, MS, CC, DC

#### 5.1.2.120 optixHitObjectGetSbtRecordIndex()

```
static __forceinline__ __device__ unsigned int  
optixHitObjectGetSbtRecordIndex ( ) [static]
```

Returns the SBT record index associated with the hit or miss program for the current outgoing hit object.

Returns 0 for nop hit objects.

Available in RG, CH, MS, CC, DC

#### 5.1.2.121 optixHitObjectGetTransformListHandle()

```
static __forceinline__ __device__ OptixTraversableHandle  
optixHitObjectGetTransformListHandle (  
    unsigned int index ) [static]
```

Returns the traversable handle for a transform in the current transform list associated with the outgoing hit object.

Results are undefined if the hit object is a miss.

See [optixGetTransformListHandle\(\)](#)

Available in RG, CH, MS, CC, DC

#### 5.1.2.122 optixHitObjectGetTransformListSize()

```
static __forceinline__ __device__ unsigned int
optixHitObjectGetTransformListSize ( ) [static]
```

Returns the number of transforms associated with the current outgoing hit object's transform list.

Returns zero when there is no hit (miss and nop).

See [optixGetTransformListSize\(\)](#)

Available in RG, CH, MS, CC, DC

#### 5.1.2.123 optixHitObjectGetWorldRayDirection()

```
static __forceinline__ __device__ float3 optixHitObjectGetWorldRayDirection
( ) [static]
```

Returns the rayDirection passed into optixTraverse, optixMakeHitObject, optixMakeHitObjectWithRecord, or optixMakeMissHitObject.

Returns [0, 0, 0] for nop hit objects.

Available in RG, CH, MS, CC, DC

#### 5.1.2.124 optixHitObjectGetWorldRayOrigin()

```
static __forceinline__ __device__ float3 optixHitObjectGetWorldRayOrigin ( )
[static]
```

Returns the rayOrigin passed into optixTraverse, optixMakeHitObject, optixMakeHitObjectWithRecord, or optixMakeMissHitObject.

Returns [0, 0, 0] for nop hit objects.

Available in RG, CH, MS, CC, DC

#### 5.1.2.125 optixHitObjectIsHit()

```
static __forceinline__ __device__ bool optixHitObjectIsHit ( ) [static]
```

Returns true if the current outgoing hit object contains a hit.

Available in RG, CH, MS, CC, DC

#### 5.1.2.126 optixHitObjectIsMiss()

```
static __forceinline__ __device__ bool optixHitObjectIsMiss ( ) [static]
```

Returns true if the current outgoing hit object contains a miss.

Available in RG, CH, MS, CC, DC

#### 5.1.2.127 optixHitObjectIsNop()

```
static __forceinline__ __device__ bool optixHitObjectIsNop ( ) [static]
```

Returns true if the current outgoing hit object contains neither a hit nor miss. If executed with optixInvoke, no operation will result. An implied nop hit object is always assumed to exist even if there are no calls such as optixTraverse to explicitly create one.

Available in RG, CH, MS, CC, DC

### 5.1.2.128 optixIgnoreIntersection()

```
static __forceinline__ __device__ void optixIgnoreIntersection ( ) [static]
```

Discards the hit, and returns control to the calling optixReportIntersection or built-in intersection routine.

Available in AH

### 5.1.2.129 optixInvoke() [1/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixInvoke (
    OptixPayloadTypeID type,
    Payload &... payload ) [static]
```

Invokes closesthit, miss or nop based on the current outgoing hit object. After execution the current outgoing hit object will be set to nop. An implied nop hit object is always assumed to exist even if there are no calls to optixTraverse, optixMakeHitObject, optixMakeMissHitObject, or optixMakeNopHitObject.

Parameters

|         |                |                                                    |
|---------|----------------|----------------------------------------------------|
| in      | <i>type</i>    |                                                    |
| in, out | <i>payload</i> | up to 32 unsigned int values that hold the payload |

Available in RG, CH, MS, CC

### 5.1.2.130 optixInvoke() [2/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixInvoke (
    Payload &... payload ) [static]
```

Invokes closesthit, miss or nop based on the current outgoing hit object. After execution the current outgoing hit object will be set to nop. An implied nop hit object is always assumed to exist even if there are no calls to optixTraverse, optixMakeHitObject, optixMakeMissHitObject, or optixMakeNopHitObject.

Parameters

|         |                |                                                    |
|---------|----------------|----------------------------------------------------|
| in, out | <i>payload</i> | up to 32 unsigned int values that hold the payload |
|---------|----------------|----------------------------------------------------|

Available in RG, CH, MS, CC

### 5.1.2.131 optixIsBackFaceHit() [1/2]

```
static __forceinline__ __device__ bool optixIsBackFaceHit ( ) [static]
```

Function interpreting the hit kind associated with the current optixReportIntersection.

Available in AH, CH

5.1.2.132 `optixIsBackFaceHit()` [2/2]

```
static __forceinline__ __device__ bool optixIsBackFaceHit (
    unsigned int hitKind ) [static]
```

Function interpreting the result of `optixGetHitKind()`.

Available in all OptiX program types

5.1.2.133 `optixIsDisplacedMicromeshTriangleBackFaceHit()`

```
static __forceinline__ __device__ bool
optixIsDisplacedMicromeshTriangleBackFaceHit ( ) [static]
```

Convenience function interpreting the result of `optixGetHitKind()`.

Available in AH, CH

5.1.2.134 `optixIsDisplacedMicromeshTriangleFrontFaceHit()`

```
static __forceinline__ __device__ bool
optixIsDisplacedMicromeshTriangleFrontFaceHit ( ) [static]
```

Convenience function interpreting the result of `optixGetHitKind()`.

Available in AH, CH

5.1.2.135 `optixIsDisplacedMicromeshTriangleHit()`

```
static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleHit
( ) [static]
```

Convenience function interpreting the result of `optixGetHitKind()`.

Available in AH, CH

5.1.2.136 `optixIsFrontFaceHit()` [1/2]

```
static __forceinline__ __device__ bool optixIsFrontFaceHit ( ) [static]
```

Function interpreting the hit kind associated with the current `optixReportIntersection`.

Available in AH, CH

5.1.2.137 `optixIsFrontFaceHit()` [2/2]

```
static __forceinline__ __device__ bool optixIsFrontFaceHit (
    unsigned int hitKind ) [static]
```

Function interpreting the result of `optixGetHitKind()`.

Available in all OptiX program types

5.1.2.138 `optixIsTriangleBackFaceHit()`

```
static __forceinline__ __device__ bool optixIsTriangleBackFaceHit ( ) [static]
```

Convenience function interpreting the result of `optixGetHitKind()`.

Available in AH, CH

### 5.1.2.139 optixIsTriangleFrontFaceHit()

```
static __forceinline__ __device__ bool optixIsTriangleFrontFaceHit ( ) [static]
```

Convenience function interpreting the result of `optixGetHitKind()`.

Available in AH, CH

### 5.1.2.140 optixIsTriangleHit()

```
static __forceinline__ __device__ bool optixIsTriangleHit ( ) [static]
```

Convenience function interpreting the result of `optixGetHitKind()`.

Available in AH, CH

### 5.1.2.141 optixMakeHitObject() [1/2]

```
template<typename... RegAttributes>
static __forceinline__ __device__ void optixMakeHitObject (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    unsigned int SBTOffset,
    unsigned int SBTstride,
    unsigned int instIdx,
    const OptixTraversableHandle * transforms,
    unsigned int numTransforms,
    unsigned int sbtGASIdx,
    unsigned int primIdx,
    unsigned int hitKind,
    RegAttributes... regAttributes ) [static]
```

Constructs an outgoing hit object from the hit information provided. This hit object will now become the current outgoing hit object and will overwrite the current outgoing hit object. This method includes the ability to specify arbitrary numbers of `OptixTraversableHandle` pointers for scenes with 0 to `OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRAVERSABLE_GRAPH_DEPTH` levels of transforms.

#### Parameters

|    |                     |                    |
|----|---------------------|--------------------|
| in | <i>handle</i>       |                    |
| in | <i>rayOrigin</i>    |                    |
| in | <i>rayDirection</i> |                    |
| in | <i>tmin</i>         |                    |
| in | <i>tmax</i>         |                    |
| in | <i>rayTime</i>      |                    |
| in | <i>SBTOffset</i>    | really only 4 bits |

## Parameters

|    |                      |                             |
|----|----------------------|-----------------------------|
| in | <i>SBTstride</i>     | really only 4 bits          |
| in | <i>instIdx</i>       |                             |
| in | <i>transforms</i>    |                             |
| in | <i>numTransforms</i> |                             |
| in | <i>sbtGASIdx</i>     |                             |
| in | <i>primIdx</i>       |                             |
| in | <i>hitKind</i>       |                             |
| in | <i>regAttributes</i> | up to 8 attribute registers |

Available in RG, CH, MS, CC

## 5.1.2.142 optixMakeHitObject() [2/2]

```
template<typename... RegAttributes>
static __forceinline__ __device__ void optixMakeHitObject (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    unsigned int SBTOffset,
    unsigned int SBTstride,
    unsigned int instIdx,
    unsigned int sbtGASIdx,
    unsigned int primIdx,
    unsigned int hitKind,
    RegAttributes... regAttributes ) [static]
```

Constructs an outgoing hit object from the hit information provided. This hit object will now become the current outgoing hit object and will overwrite the current outgoing hit object.

## Parameters

|    |                     |                    |
|----|---------------------|--------------------|
| in | <i>handle</i>       |                    |
| in | <i>rayOrigin</i>    |                    |
| in | <i>rayDirection</i> |                    |
| in | <i>tmin</i>         |                    |
| in | <i>tmax</i>         |                    |
| in | <i>rayTime</i>      |                    |
| in | <i>SBTOffset</i>    | really only 4 bits |
| in | <i>SBTstride</i>    | really only 4 bits |
| in | <i>instIdx</i>      |                    |

## Parameters

|    |                      |                             |
|----|----------------------|-----------------------------|
| in | <i>sbtGASIdx</i>     |                             |
| in | <i>primIdx</i>       |                             |
| in | <i>hitKind</i>       |                             |
| in | <i>regAttributes</i> | up to 8 attribute registers |

Available in RG, CH, MS, CC

## 5.1.2.143 optixMakeHitObjectWithRecord()

```
template<typename... RegAttributes>
static __forceinline__ __device__ void optixMakeHitObjectWithRecord (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    unsigned int sbtRecordIndex,
    unsigned int instIdx,
    const OptixTraversableHandle * transforms,
    unsigned int numTransforms,
    unsigned int sbtGASIdx,
    unsigned int primIdx,
    unsigned int hitKind,
    RegAttributes... regAttributes ) [static]
```

Constructs an outgoing hit object from the hit information provided. The SBT record index is explicitly specified. This hit object will now become the current outgoing hit object and will overwrite the current outgoing hit object.

## Parameters

|    |                       |         |
|----|-----------------------|---------|
| in | <i>handle</i>         |         |
| in | <i>rayOrigin</i>      |         |
| in | <i>rayDirection</i>   |         |
| in | <i>tmin</i>           |         |
| in | <i>tmax</i>           |         |
| in | <i>rayTime</i>        |         |
| in | <i>sbtRecordIndex</i> | 32 bits |
| in | <i>instIdx</i>        |         |
| in | <i>transforms</i>     |         |
| in | <i>numTransforms</i>  |         |
| in | <i>sbtGASIdx</i>      |         |



## Parameters

|    |                      |                             |
|----|----------------------|-----------------------------|
| in | <i>primIdx</i>       |                             |
| in | <i>hitKind</i>       |                             |
| in | <i>regAttributes</i> | up to 8 attribute registers |

Available in RG, CH, MS, CC

5.1.2.144 `optixMakeMissHitObject()`

```
static __forceinline__ __device__ void optixMakeMissHitObject (
    unsigned int missSBTIndex,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime ) [static]
```

Constructs an outgoing hit object from the miss information provided. The SBT record index is explicitly specified as an argument. This hit object will now become the current outgoing hit object and will overwrite the current outgoing hit object.

## Parameters

|    |                     |                                              |
|----|---------------------|----------------------------------------------|
| in | <i>missSBTIndex</i> | specifies the miss program invoked on a miss |
| in | <i>rayOrigin</i>    |                                              |
| in | <i>rayDirection</i> |                                              |
| in | <i>tmin</i>         |                                              |
| in | <i>tmax</i>         |                                              |
| in | <i>rayTime</i>      |                                              |

Available in RG, CH, MS, CC

5.1.2.145 `optixMakeNopHitObject()`

```
static __forceinline__ __device__ void optixMakeNopHitObject ( ) [static]
```

Constructs an outgoing hit object that when invoked does nothing (neither the miss nor the closest hit shader will be invoked). This hit object will now become the current outgoing hit object and will overwrite the current outgoing hit object. Accessors such as `optixHitObjectGetInstanceId` will return 0 or 0 filled structs. Only `optixHitObjectGetIsNop()` will return a non-zero result.

Available in RG, CH, MS, CC

5.1.2.146 `optixReorder()` [1/2]

```
static __forceinline__ __device__ void optixReorder ( ) [static]
```

Reorder the current thread using the hit object only, ie without further coherence hints.

Available in RG

### 5.1.2.147 optixReorder() [2/2]

```
static __forceinline__ __device__ void optixReorder (
    unsigned int coherenceHint,
    unsigned int numCoherenceHintBitsFromLSB ) [static]
```

Reorder the current thread using the current outgoing hit object and the coherence hint bits provided. Note that the coherence hint will take away some of the bits used in the hit object for sorting, so care should be made to reduce the number of hint bits as much as possible. Nop hit objects can use more coherence hint bits. Bits are taken from the lowest significant bit range. The maximum value of numCoherenceHintBitsFromLSB is implementation defined and can vary.

#### Parameters

|    |                                    |
|----|------------------------------------|
| in | <i>coherenceHint</i>               |
| in | <i>numCoherenceHintBitsFromLSB</i> |

Available in RG

### 5.1.2.148 optixReportIntersection() [1/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind ) [static]
```

Reports an intersections (overload without attributes).

If `optixGetRayTmin() <= hitT <= optixGetRayTmax()`, the any hit program associated with this intersection program (via the SBT entry) is called.

The AH program can do one of three things:

1. call `optixIgnoreIntersection` - no hit is recorded, `optixReportIntersection` returns false
2. call `optixTerminateRay` - hit is recorded, `optixReportIntersection` does not return, no further traversal occurs, and the associated closest hit program is called
3. neither - hit is recorded, `optixReportIntersection` returns true

*hitKind* - Only the 7 least significant bits should be written [0..127]. Any values above 127 are reserved for built in intersection. The value can be queried with `optixGetHitKind()` in AH and CH.

The attributes specified with `a0..a7` are available in the AH and CH programs. Note that the attributes available in the CH program correspond to the closest recorded intersection. The number of attributes in registers and memory can be configured in the pipeline.

#### Parameters

|    |                |
|----|----------------|
| in | <i>hitT</i>    |
| in | <i>hitKind</i> |

Available in IS

### 5.1.2.149 optixReportIntersection() [2/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
```

```
float hitT,
unsigned int hitKind,
unsigned int a0 ) [static]
```

Reports an intersection (overload with 1 attribute register).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.150 optixReportIntersection() [3/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1 ) [static]
```

Reports an intersection (overload with 2 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.151 optixReportIntersection() [4/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2 ) [static]
```

Reports an intersection (overload with 3 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.152 optixReportIntersection() [5/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3 ) [static]
```

Reports an intersection (overload with 4 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.153 optixReportIntersection() [6/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
```

```

    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4 ) [static]

```

Reports an intersection (overload with 5 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.154 optixReportIntersection() [7/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4,
    unsigned int a5 ) [static]

```

Reports an intersection (overload with 6 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.155 optixReportIntersection() [8/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4,
    unsigned int a5,
    unsigned int a6 ) [static]

```

Reports an intersection (overload with 7 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.156 optixReportIntersection() [9/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,

```

```

        unsigned int a3,
        unsigned int a4,
        unsigned int a5,
        unsigned int a6,
        unsigned int a7 ) [static]

```

Reports an intersection (overload with 8 attribute registers).

See also [optixReportIntersection\(float,unsigned int\)](#) Available in IS

#### 5.1.2.157 optixSetPayload\_0()

```

static __forceinline__ __device__ void optixSetPayload_0 (
    unsigned int p ) [static]

```

Writes the 32-bit payload at the given slot index. There are up to 32 attributes available. The number of attributes is configured with [OptixPipelineCompileOptions::numPayloadValues](#) or with [OptixPayloadType](#) parameters set in [OptixModuleCompileOptions](#).

Available in IS, AH, CH, MS

#### 5.1.2.158 optixSetPayload\_1()

```

static __forceinline__ __device__ void optixSetPayload_1 (
    unsigned int p ) [static]

```

#### 5.1.2.159 optixSetPayload\_10()

```

static __forceinline__ __device__ void optixSetPayload_10 (
    unsigned int p ) [static]

```

#### 5.1.2.160 optixSetPayload\_11()

```

static __forceinline__ __device__ void optixSetPayload_11 (
    unsigned int p ) [static]

```

#### 5.1.2.161 optixSetPayload\_12()

```

static __forceinline__ __device__ void optixSetPayload_12 (
    unsigned int p ) [static]

```

#### 5.1.2.162 optixSetPayload\_13()

```

static __forceinline__ __device__ void optixSetPayload_13 (
    unsigned int p ) [static]

```

#### 5.1.2.163 optixSetPayload\_14()

```

static __forceinline__ __device__ void optixSetPayload_14 (
    unsigned int p ) [static]

```

#### 5.1.2.164 optixSetPayload\_15()

```

static __forceinline__ __device__ void optixSetPayload_15 (

```

```
    unsigned int p ) [static]
```

#### 5.1.2.165 optixSetPayload\_16()

```
static __forceinline__ __device__ void optixSetPayload_16 (  
    unsigned int p ) [static]
```

#### 5.1.2.166 optixSetPayload\_17()

```
static __forceinline__ __device__ void optixSetPayload_17 (  
    unsigned int p ) [static]
```

#### 5.1.2.167 optixSetPayload\_18()

```
static __forceinline__ __device__ void optixSetPayload_18 (  
    unsigned int p ) [static]
```

#### 5.1.2.168 optixSetPayload\_19()

```
static __forceinline__ __device__ void optixSetPayload_19 (  
    unsigned int p ) [static]
```

#### 5.1.2.169 optixSetPayload\_20()

```
static __forceinline__ __device__ void optixSetPayload_20 (  
    unsigned int p ) [static]
```

#### 5.1.2.170 optixSetPayload\_21()

```
static __forceinline__ __device__ void optixSetPayload_21 (  
    unsigned int p ) [static]
```

#### 5.1.2.171 optixSetPayload\_22()

```
static __forceinline__ __device__ void optixSetPayload_22 (  
    unsigned int p ) [static]
```

#### 5.1.2.172 optixSetPayload\_23()

```
static __forceinline__ __device__ void optixSetPayload_23 (  
    unsigned int p ) [static]
```

#### 5.1.2.173 optixSetPayload\_24()

```
static __forceinline__ __device__ void optixSetPayload_24 (  
    unsigned int p ) [static]
```

#### 5.1.2.174 optixSetPayload\_25()

```
static __forceinline__ __device__ void optixSetPayload_25 (  
    unsigned int p ) [static]
```

## 5.1.2.175 optixSetPayload\_25()

```
static __forceinline__ __device__ void optixSetPayload_25 (  
    unsigned int p ) [static]
```

## 5.1.2.176 optixSetPayload\_26()

```
static __forceinline__ __device__ void optixSetPayload_26 (  
    unsigned int p ) [static]
```

## 5.1.2.177 optixSetPayload\_27()

```
static __forceinline__ __device__ void optixSetPayload_27 (  
    unsigned int p ) [static]
```

## 5.1.2.178 optixSetPayload\_28()

```
static __forceinline__ __device__ void optixSetPayload_28 (  
    unsigned int p ) [static]
```

## 5.1.2.179 optixSetPayload\_29()

```
static __forceinline__ __device__ void optixSetPayload_29 (  
    unsigned int p ) [static]
```

## 5.1.2.180 optixSetPayload\_3()

```
static __forceinline__ __device__ void optixSetPayload_3 (  
    unsigned int p ) [static]
```

## 5.1.2.181 optixSetPayload\_30()

```
static __forceinline__ __device__ void optixSetPayload_30 (  
    unsigned int p ) [static]
```

## 5.1.2.182 optixSetPayload\_31()

```
static __forceinline__ __device__ void optixSetPayload_31 (  
    unsigned int p ) [static]
```

## 5.1.2.183 optixSetPayload\_4()

```
static __forceinline__ __device__ void optixSetPayload_4 (  
    unsigned int p ) [static]
```

## 5.1.2.184 optixSetPayload\_5()

```
static __forceinline__ __device__ void optixSetPayload_5 (  
    unsigned int p ) [static]
```

## 5.1.2.185 optixSetPayload\_6()

```
static __forceinline__ __device__ void optixSetPayload_6 (  

```

```
    unsigned int p ) [static]
```

#### 5.1.2.186 optixSetPayload\_7()

```
static __forceinline__ __device__ void optixSetPayload_7 (
    unsigned int p ) [static]
```

#### 5.1.2.187 optixSetPayload\_8()

```
static __forceinline__ __device__ void optixSetPayload_8 (
    unsigned int p ) [static]
```

#### 5.1.2.188 optixSetPayload\_9()

```
static __forceinline__ __device__ void optixSetPayload_9 (
    unsigned int p ) [static]
```

#### 5.1.2.189 optixSetPayloadTypes()

```
static __forceinline__ __device__ void optixSetPayloadTypes (
    unsigned int typeMask ) [static]
```

Specify the supported payload types for a program.

The supported types are specified as a bitwise combination of payload types. (See OptixPayloadTypeID) May only be called once per program.

Must be called at the top of the program.

Available in IS, AH, CH, MS

#### 5.1.2.190 optixTerminateRay()

```
static __forceinline__ __device__ void optixTerminateRay ( ) [static]
```

Record the hit, stops traversal, and proceeds to CH.

Available in AH

#### 5.1.2.191 optixTexFootprint2D()

```
static __forceinline__ __device__ uint4 optixTexFootprint2D (
    unsigned long long tex,
    unsigned int texInfo,
    float x,
    float y,
    unsigned int * singleMipLevel ) [static]
```

optixTexFootprint2D calculates the footprint of a corresponding 2D texture fetch (non-mipmapped).

On Turing and subsequent architectures, a texture footprint instruction allows user programs to determine the set of texels that would be accessed by an equivalent filtered texture lookup.

#### Parameters

|    |            |                                              |
|----|------------|----------------------------------------------|
| in | <i>tex</i> | CUDA texture object (cast to 64-bit integer) |
|----|------------|----------------------------------------------|



## Parameters

|     |                       |                                                                       |
|-----|-----------------------|-----------------------------------------------------------------------|
| in  | <i>texInfo</i>        | Texture info packed into 32-bit integer, described below.             |
| in  | <i>x</i>              | Texture coordinate                                                    |
| in  | <i>y</i>              | Texture coordinate                                                    |
| out | <i>singleMipLevel</i> | Result indicating whether the footprint spans only a single miplevel. |

The texture info argument is a packed 32-bit integer with the following layout:

texInfo[31:29] = reserved (3 bits) texInfo[28:24] = miplevel count (5 bits) texInfo[23:20] = log2 of tile width (4 bits) texInfo[19:16] = log2 of tile height (4 bits) texInfo[15:10] = reserved (6 bits) texInfo[9:8] = horizontal wrap mode (2 bits) (CUaddress\_mode) texInfo[7:6] = vertical wrap mode (2 bits) (CUaddress\_mode) texInfo[5] = mipmap filter mode (1 bit) (CUfilter\_mode) texInfo[4:0] = maximum anisotropy (5 bits)

Returns a 16-byte structure (as a uint4) that stores the footprint of a texture request at a particular "granularity", which has the following layout:

```
struct Texture2DFootprint { unsigned long long mask; unsigned int tileY : 12; unsigned int reserved1 : 4; unsigned int dx : 3; unsigned int dy : 3; unsigned int reserved2 : 2; unsigned int granularity : 4; unsigned int reserved3 : 4; unsigned int tileX : 12; unsigned int level : 4; unsigned int reserved4 : 16; };
```

The granularity indicates the size of texel groups that are represented by an 8x8 bitmask. For example, a granularity of 12 indicates texel groups that are 128x64 texels in size. In a footprint call, The returned granularity will either be the actual granularity of the result, or 0 if the footprint call was able to honor the requested granularity (the usual case).

level is the mip level of the returned footprint. Two footprint calls are needed to get the complete footprint when a texture call spans multiple mip levels.

mask is an 8x8 bitmask of texel groups that are covered, or partially covered, by the footprint. tileX and tileY give the starting position of the mask in 8x8 texel-group blocks. For example, suppose a granularity of 12 (128x64 texels), and tileX=3 and tileY=4. In this case, bit 0 of the mask (the low order bit) corresponds to texel group coordinates (3\*8, 4\*8), and texel coordinates (3\*8\*128, 4\*8\*64), within the specified mip level.

If nonzero, dx and dy specify a "toroidal rotation" of the bitmask. Toroidal rotation of a coordinate in the mask simply means that its value is reduced by 8. Continuing the example from above, if dx=0 and dy=0 the mask covers texel groups (3\*8, 4\*8) to (3\*8+7, 4\*8+7) inclusive. If, on the other hand, dx=2, the rightmost 2 columns in the mask have their x coordinates reduced by 8, and similarly for dy.

See the OptiX SDK for sample code that illustrates how to unpack the result.

Available anywhere

### 5.1.2.192 optixTexFootprint2DGrad()

```
static __forceinline__ __device__ uint4 optixTexFootprint2DGrad (
    unsigned long long tex,
    unsigned int texInfo,
    float x,
    float y,
    float dPdx_x,
    float dPdx_y,
    float dPdy_x,
```

```

float dPdy_y,
bool coarse,
unsigned int * singleMipLevel ) [static]

```

optixTexFootprint2DGrad calculates the footprint of a corresponding 2D texture fetch (tex2DGrad)

#### Parameters

|     |                       |                                                                               |
|-----|-----------------------|-------------------------------------------------------------------------------|
| in  | <i>tex</i>            | CUDA texture object (cast to 64-bit integer)                                  |
| in  | <i>texInfo</i>        | Texture info packed into 32-bit integer, described below.                     |
| in  | <i>x</i>              | Texture coordinate                                                            |
| in  | <i>y</i>              | Texture coordinate                                                            |
| in  | <i>dPdx_x</i>         | Derivative of x coordinte, which determines level of detail.                  |
| in  | <i>dPdx_y</i>         | Derivative of x coordinte, which determines level of detail.                  |
| in  | <i>dPdy_x</i>         | Derivative of y coordinte, which determines level of detail.                  |
| in  | <i>dPdy_y</i>         | Derivative of y coordinte, which determines level of detail.                  |
| in  | <i>coarse</i>         | Requests footprint from coarse miplevel, when the footprint spans two levels. |
| out | <i>singleMipLevel</i> | Result indicating whether the footprint spans only a single miplevel.         |

See also [optixTexFootprint2D\(unsigned long long,unsigned int,float,float,unsigned int\\*\)](#) Available anywhere

#### 5.1.2.193 optixTexFootprint2DLod()

```

static __forceinline__ __device__ uint4 optixTexFootprint2DLod (
    unsigned long long tex,
    unsigned int texInfo,
    float x,
    float y,
    float level,
    bool coarse,
    unsigned int * singleMipLevel ) [static]

```

optixTexFootprint2DLod calculates the footprint of a corresponding 2D texture fetch (tex2DLod)

#### Parameters

|     |                       |                                                                               |
|-----|-----------------------|-------------------------------------------------------------------------------|
| in  | <i>tex</i>            | CUDA texture object (cast to 64-bit integer)                                  |
| in  | <i>texInfo</i>        | Texture info packed into 32-bit integer, described below.                     |
| in  | <i>x</i>              | Texture coordinate                                                            |
| in  | <i>y</i>              | Texture coordinate                                                            |
| in  | <i>level</i>          | Level of detail (lod)                                                         |
| in  | <i>coarse</i>         | Requests footprint from coarse miplevel, when the footprint spans two levels. |
| out | <i>singleMipLevel</i> | Result indicating whether the footprint spans only a single miplevel.         |

See also [optixTexFootprint2D\(unsigned long long,unsigned int,float,float,unsigned int\\*\)](#) Available anywhere

5.1.2.194 `optixThrowException()` [1/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode ) [static]
```

Throws a user exception with the given exception code (overload without exception details).

The exception code must be in the range from 0 to  $2^{30} - 1$ . Up to 8 optional exception details can be passed. They can be queried in the EX program using [optixGetExceptionDetail\\_0\(\)](#) to [...\\_8\(\)](#).

The exception details must not be used to encode pointers to the stack since the current stack is not preserved in the EX program.

Not available in EX

Parameters

|    |                      |                                  |
|----|----------------------|----------------------------------|
| in | <i>exceptionCode</i> | The exception code to be thrown. |
|----|----------------------|----------------------------------|

Available in RG, IS, AH, CH, MS, DC, CC

5.1.2.195 `optixThrowException()` [2/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0 ) [static]
```

Throws a user exception with the given exception code (overload with 1 exception detail).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

5.1.2.196 `optixThrowException()` [3/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1 ) [static]
```

Throws a user exception with the given exception code (overload with 2 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

5.1.2.197 `optixThrowException()` [4/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2 ) [static]
```

Throws a user exception with the given exception code (overload with 3 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

5.1.2.198 `optixThrowException()` [5/9]

```
static __forceinline__ __device__ void optixThrowException (
```

```

    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3 ) [static]

```

Throws a user exception with the given exception code (overload with 4 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

#### 5.1.2.199 optixThrowException() [6/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4 ) [static]

```

Throws a user exception with the given exception code (overload with 5 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

#### 5.1.2.200 optixThrowException() [7/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4,
    unsigned int exceptionDetail5 ) [static]

```

Throws a user exception with the given exception code (overload with 6 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

#### 5.1.2.201 optixThrowException() [8/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4,
    unsigned int exceptionDetail5,
    unsigned int exceptionDetail6 ) [static]

```

Throws a user exception with the given exception code (overload with 7 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

#### 5.1.2.202 optixThrowException() [9/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4,
    unsigned int exceptionDetail5,
    unsigned int exceptionDetail6,
    unsigned int exceptionDetail7 ) [static]
```

Throws a user exception with the given exception code (overload with 8 exception details).

See also [optixThrowException\(int\)](#) Available in RG, IS, AH, CH, MS, DC, CC

#### 5.1.2.203 optixTrace() [1/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixTrace (
    OptixPayloadTypeID type,
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBToffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]
```

Initiates a ray tracing query starting with the given traversable.

##### Parameters

|    |                     |  |
|----|---------------------|--|
| in | <i>type</i>         |  |
| in | <i>handle</i>       |  |
| in | <i>rayOrigin</i>    |  |
| in | <i>rayDirection</i> |  |
| in | <i>tmin</i>         |  |

## Parameters

|         |                       |                                                    |
|---------|-----------------------|----------------------------------------------------|
| in      | <i>tmax</i>           |                                                    |
| in      | <i>rayTime</i>        |                                                    |
| in      | <i>visibilityMask</i> | really only 8 bits                                 |
| in      | <i>rayFlags</i>       | really only 16 bits, combination of OptixRayFlags  |
| in      | <i>SBTOffset</i>      | really only 4 bits                                 |
| in      | <i>SBTstride</i>      | really only 4 bits                                 |
| in      | <i>missSBTIndex</i>   | specifies the miss program invoked on a miss       |
| in, out | <i>payload</i>        | up to 32 unsigned int values that hold the payload |

Available in RG, CH, MS, CC, DC

## 5.1.2.204 optixTrace() [2/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixTrace (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBTOffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]
```

Initiates a ray tracing query starting with the given traversable.

## Parameters

|    |                       |                                                   |
|----|-----------------------|---------------------------------------------------|
| in | <i>handle</i>         |                                                   |
| in | <i>rayOrigin</i>      |                                                   |
| in | <i>rayDirection</i>   |                                                   |
| in | <i>tmin</i>           |                                                   |
| in | <i>tmax</i>           |                                                   |
| in | <i>rayTime</i>        |                                                   |
| in | <i>visibilityMask</i> | really only 8 bits                                |
| in | <i>rayFlags</i>       | really only 16 bits, combination of OptixRayFlags |
| in | <i>SBTOffset</i>      | really only 4 bits                                |
| in | <i>SBTstride</i>      | really only 4 bits                                |

## Parameters

|                |                     |                                                    |
|----------------|---------------------|----------------------------------------------------|
| <b>in</b>      | <i>missSBTIndex</i> | specifies the miss program invoked on a miss       |
| <b>in, out</b> | <i>payload</i>      | up to 32 unsigned int values that hold the payload |

Available in RG, CH, MS, CC, DC

5.1.2.205 `optixTransformNormalFromObjectToWorldSpace()`

```
static __forceinline__ __device__ float3
optixTransformNormalFromObjectToWorldSpace (
    float3 normal ) [static]
```

Transforms the normal using object-to-world transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

5.1.2.206 `optixTransformNormalFromWorldToObjectSpace()`

```
static __forceinline__ __device__ float3
optixTransformNormalFromWorldToObjectSpace (
    float3 normal ) [static]
```

Transforms the normal using world-to-object transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

5.1.2.207 `optixTransformPointFromObjectToWorldSpace()`

```
static __forceinline__ __device__ float3
optixTransformPointFromObjectToWorldSpace (
    float3 point ) [static]
```

Transforms the point using object-to-world transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

5.1.2.208 `optixTransformPointFromWorldToObjectSpace()`

```
static __forceinline__ __device__ float3
optixTransformPointFromWorldToObjectSpace (
    float3 point ) [static]
```

Transforms the point using world-to-object transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

### 5.1.2.209 optixTransformVectorFromObjectToWorldSpace()

```
static __forceinline__ __device__ float3
optixTransformVectorFromObjectToWorldSpace (
    float3 vec ) [static]
```

Transforms the vector using object-to-world transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

### 5.1.2.210 optixTransformVectorFromWorldToObjectSpace()

```
static __forceinline__ __device__ float3
optixTransformVectorFromWorldToObjectSpace (
    float3 vec ) [static]
```

Transforms the vector using world-to-object transformation matrix resulting from the current active transformation list.

The cost of this function may be proportional to the size of the transformation list.

Available in IS, AH, CH

### 5.1.2.211 optixTraverse() [1/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixTraverse (
    OptixPayloadTypeID type,
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBToffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]
```

Similar to `optixTrace`, but does not invoke `closesthit` or `miss`. Instead, it overwrites the current outgoing hit object with the results of traversing the ray. The outgoing hit object may be invoked at some later point with `optixInvoke`. The outgoing hit object can also be queried through various functions such as `optixHitObjectIsHit` or `optixHitObjectGetAttribute_0`.

#### Parameters

|    |               |  |
|----|---------------|--|
| in | <i>type</i>   |  |
| in | <i>handle</i> |  |



## Parameters

|         |                       |                                                    |
|---------|-----------------------|----------------------------------------------------|
| in      | <i>rayOrigin</i>      |                                                    |
| in      | <i>rayDirection</i>   |                                                    |
| in      | <i>tmin</i>           |                                                    |
| in      | <i>tmax</i>           |                                                    |
| in      | <i>rayTime</i>        |                                                    |
| in      | <i>visibilityMask</i> | really only 8 bits                                 |
| in      | <i>rayFlags</i>       | really only 16 bits, combination of OptixRayFlags  |
| in      | <i>SBToffset</i>      | really only 4 bits                                 |
| in      | <i>SBTstride</i>      | really only 4 bits                                 |
| in      | <i>missSBTIndex</i>   | specifies the miss program invoked on a miss       |
| in, out | <i>payload</i>        | up to 32 unsigned int values that hold the payload |

Available in RG, CH, MS, CC, DC

## 5.1.2.212 optixTraverse() [2/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixTraverse (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBToffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]
```

Similar to optixTrace, but does not invoke closesthit or miss. Instead, it overwrites the current outgoing hit object with the results of traversing the ray. The outgoing hit object may be invoked at some later point with optixInvoke. The outgoing hit object can also be queried through various functions such as optixHitObjectIsHit or optixHitObjectGetAttribute\_0.

## Parameters

|    |                     |  |
|----|---------------------|--|
| in | <i>handle</i>       |  |
| in | <i>rayOrigin</i>    |  |
| in | <i>rayDirection</i> |  |
| in | <i>tmin</i>         |  |
| in | <i>tmax</i>         |  |

## Parameters

|         |                       |                                                    |
|---------|-----------------------|----------------------------------------------------|
| in      | <i>rayTime</i>        |                                                    |
| in      | <i>visibilityMask</i> | really only 8 bits                                 |
| in      | <i>rayFlags</i>       | really only 16 bits, combination of OptixRayFlags  |
| in      | <i>SBTOffset</i>      | really only 4 bits                                 |
| in      | <i>SBTstride</i>      | really only 4 bits                                 |
| in      | <i>missSBTIndex</i>   | specifies the miss program invoked on a miss       |
| in, out | <i>payload</i>        | up to 32 unsigned int values that hold the payload |

Available in RG, CH, MS, CC, DC

## 5.1.2.213 optixUndefinedValue()

```
static __forceinline__ __device__ unsigned int optixUndefinedValue ( ) [static]
```

Returns an undefined value.

Available anywhere

## 5.2 Function Table

## Classes

- struct [OptixFunctionTable](#)

## Typedefs

- typedef struct [OptixFunctionTable](#) [OptixFunctionTable](#)

## Variables

- [OptixFunctionTable](#) [g\\_optixFunctionTable](#)

## 5.2.1 Detailed Description

OptiX Function Table.

## 5.2.2 Typedef Documentation

## 5.2.2.1 OptixFunctionTable

```
typedef struct OptixFunctionTable OptixFunctionTable
```

The function table containing all API functions.

See [optixInit\(\)](#) and [optixInitWithHandle\(\)](#).

## 5.2.3 Variable Documentation

## 5.2.3.1 g\_optixFunctionTable

[OptixFunctionTable](#) [g\\_optixFunctionTable](#)

If the stubs in [optix\\_stubs.h](#) are used, then the function table needs to be defined in exactly one translation unit. This can be achieved by including this header file in that translation unit.

## 5.3 Host API

### Modules

- [Error handling](#)
- [Device context](#)
- [Pipelines](#)
- [Modules](#)
- [Tasks](#)
- [Program groups](#)
- [Launches](#)
- [Acceleration structures](#)
- [Denoiser](#)

### 5.3.1 Detailed Description

OptiX Host API.

### 5.4 Error handling

### 5.5 Device context

### 5.6 Pipelines

### 5.7 Modules

### 5.8 Tasks

### 5.9 Program groups

### 5.10 Launches

### 5.11 Acceleration structures

### 5.12 Denoiser

### 5.13 Utilities

### Classes

- [struct `OptixUtilDenoiserImageTile`](#)

### Macros

- [#define `OPTIX\_MICROMAP\_INLINE\_FUNC` `OPTIX\_MICROMAP\_FUNC` inline](#)
- [#define `OPTIX\_MICROMAP\_FLOAT2\_SUB\(a, b\)` { `a.x - b.x, a.y - b.y` }](#)

### Functions

- [OPTIX\\_MICROMAP\\_INLINE\\_FUNC `float optix\_impl::\_\_uint\_as\_float` \(unsigned int x\)](#)
- [OPTIX\\_MICROMAP\\_INLINE\\_FUNC unsigned int `optix\_impl::extractEvenBits` \(unsigned int x\)](#)
- [OPTIX\\_MICROMAP\\_INLINE\\_FUNC unsigned int `optix\_impl::prefixEor` \(unsigned int x\)](#)
- [OPTIX\\_MICROMAP\\_INLINE\\_FUNC void `optix\_impl::index2dbary` \(unsigned int index, unsigned int &u, unsigned int &v, unsigned int &w\)](#)

- `OPTIX_MICROMAP_INLINE_FUNC` void `optix_impl::micro2bary` (unsigned int index, unsigned int subdivisionLevel, float2 &bary0, float2 &bary1, float2 &bary2)
- `OPTIX_MICROMAP_INLINE_FUNC` float2 `optix_impl::base2micro` (const float2 &baseBarycentrics, const float2 microVertexBaseBarycentrics[3])
- `OptixResult` `optixUtilGetPixelStride` (const `OptixImage2D` &image, unsigned int &pixelStrideInBytes)
- `OptixResult` `optixUtilDenoiserSplitImage` (const `OptixImage2D` &input, const `OptixImage2D` &output, unsigned int overlapWindowSizeInPixels, unsigned int tileWidth, unsigned int tileHeight, std::vector< `OptixUtilDenoiserImageTile` > &tiles)
- `OptixResult` `optixUtilDenoiserInvokeTiled` (`OptixDenoiser` denoiser, `CUstream` stream, const `OptixDenoiserParams` \*params, `CUdeviceptr` denoiserState, size\_t denoiserStateSizeInBytes, const `OptixDenoiserGuideLayer` \*guideLayer, const `OptixDenoiserLayer` \*layers, unsigned int numLayers, `CUdeviceptr` scratch, size\_t scratchSizeInBytes, unsigned int overlapWindowSizeInPixels, unsigned int tileWidth, unsigned int tileHeight)
- `OptixResult` `optixUtilAccumulateStackSizes` (`OptixProgramGroup` programGroup, `OptixStackSizes` \*stackSizes, `OptixPipeline` pipeline)
- `OptixResult` `optixUtilComputeStackSizes` (const `OptixStackSizes` \*stackSizes, unsigned int maxTraceDepth, unsigned int maxCCDepth, unsigned int maxDCDepth, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize)
- `OptixResult` `optixUtilComputeStackSizesDCSplit` (const `OptixStackSizes` \*stackSizes, unsigned int dssDCFromTraversal, unsigned int dssDCFromState, unsigned int maxTraceDepth, unsigned int maxCCDepth, unsigned int maxDCDepthFromTraversal, unsigned int maxDCDepthFromState, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize)
- `OptixResult` `optixUtilComputeStackSizesCssCCTree` (const `OptixStackSizes` \*stackSizes, unsigned int cssCCTree, unsigned int maxTraceDepth, unsigned int maxDCDepth, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize)
- `OptixResult` `optixUtilComputeStackSizesSimplePathTracer` (`OptixProgramGroup` programGroupRG, `OptixProgramGroup` programGroupMS1, const `OptixProgramGroup` \*programGroupCH1, unsigned int programGroupCH1Count, `OptixProgramGroup` programGroupMS2, const `OptixProgramGroup` \*programGroupCH2, unsigned int programGroupCH2Count, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize, `OptixPipeline` pipeline)
- `OptixResult` `optixInitWithHandle` (void \*\*handlePtr)
- `OptixResult` `optixInit` (void)
- `OptixResult` `optixUninitWithHandle` (void \*handle)

### 5.13.1 Detailed Description

OptiX Utilities.

### 5.13.2 Macro Definition Documentation

#### 5.13.2.1 OPTIX\_MICROMAP\_FLOAT2\_SUB

```
#define OPTIX_MICROMAP_FLOAT2_SUB(
    a,
    b ) { a.x - b.x, a.y - b.y }
```

## 5.13.2.2 OPTIX\_MICROMAP\_INLINE\_FUNC

```
#define OPTIX_MICROMAP_INLINE_FUNC OPTIX_MICROMAP_FUNC inline
```

## 5.13.3 Function Documentation

## 5.13.3.1 \_\_uint\_as\_float()

```
OPTIX_MICROMAP_INLINE_FUNC float optix_impl::__uint_as_float (
    unsigned int x )
```

## 5.13.3.2 base2micro()

```
OPTIX_MICROMAP_INLINE_FUNC float2 optix_impl::base2micro (
    const float2 & baseBarycentrics,
    const float2 microVertexBaseBarycentrics[3] )
```

## 5.13.3.3 extractEvenBits()

```
OPTIX_MICROMAP_INLINE_FUNC unsigned int optix_impl::extractEvenBits (
    unsigned int x )
```

## 5.13.3.4 index2dbary()

```
OPTIX_MICROMAP_INLINE_FUNC void optix_impl::index2dbary (
    unsigned int index,
    unsigned int & u,
    unsigned int & v,
    unsigned int & w )
```

## 5.13.3.5 micro2bary()

```
OPTIX_MICROMAP_INLINE_FUNC void optix_impl::micro2bary (
    unsigned int index,
    unsigned int subdivisionLevel,
    float2 & bary0,
    float2 & bary1,
    float2 & bary2 )
```

## 5.13.3.6 optixInit()

```
OptixResult optixInit (
    void ) [inline]
```

Loads the OptiX library and initializes the function table used by the stubs below.

A variant of [optixInitWithHandle\(\)](#) that does not make the handle to the loaded library available.

## 5.13.3.7 optixInitWithHandle()

```
OptixResult optixInitWithHandle (
    void ** handlePtr ) [inline]
```

Loads the OptiX library and initializes the function table used by the stubs below.

If `handlePtr` is not nullptr, an OS-specific handle to the library will be returned in `*handlePtr`.

See also [optixUninitWithHandle](#)

### 5.13.3.8 optixUninitWithHandle()

```
OptixResult optixUninitWithHandle (
    void * handle ) [inline]
```

Unloads the OptiX library and zeros the function table used by the stubs below. Takes the handle returned by `optixInitWithHandle`. All `OptixDeviceContext` objects must be destroyed before calling this function, or the behavior is undefined.

See also [optixInitWithHandle](#)

### 5.13.3.9 optixUtilAccumulateStackSizes()

```
OptixResult optixUtilAccumulateStackSizes (
    OptixProgramGroup programGroup,
    OptixStackSizes * stackSizes,
    OptixPipeline pipeline ) [inline]
```

Retrieves direct and continuation stack sizes for each program in the program group and accumulates the upper bounds in the corresponding output variables based on the semantic type of the program. Before the first invocation of this function with a given instance of `OptixStackSizes`, the members of that instance should be set to 0. If the programs rely on external functions, passing the current pipeline will consider these as well. Otherwise, a null pointer can be passed instead. When external functions are present, a warning will be issued for these cases.

### 5.13.3.10 optixUtilComputeStackSizes()

```
OptixResult optixUtilComputeStackSizes (
    const OptixStackSizes * stackSizes,
    unsigned int maxTraceDepth,
    unsigned int maxCCDepth,
    unsigned int maxDCDepth,
    unsigned int * directCallableStackSizeFromTraversal,
    unsigned int * directCallableStackSizeFromState,
    unsigned int * continuationStackSize ) [inline]
```

Computes the stack size values needed to configure a pipeline.

See the programming guide for an explanation of the formula.

#### Parameters

|    |                      |                                                            |
|----|----------------------|------------------------------------------------------------|
| in | <i>stackSizes</i>    | Accumulated stack sizes of all programs in the call graph. |
| in | <i>maxTraceDepth</i> | Maximum depth of <code>optixTrace()</code> calls.          |
| in | <i>maxCCDepth</i>    | Maximum depth of calls trees of continuation callables.    |
| in | <i>maxDCDepth</i>    | Maximum depth of calls trees of direct callables.          |

## Parameters

|     |                                             |                                                                                |
|-----|---------------------------------------------|--------------------------------------------------------------------------------|
| out | <i>directCallableStackSizeFromTraversal</i> | Direct stack size requirement for direct callables invoked from IS or AH.      |
| out | <i>directCallableStackSizeFromState</i>     | Direct stack size requirement for direct callables invoked from RG, MS, or CH. |
| out | <i>continuationStackSize</i>                | Continuation stack requirement.                                                |

5.13.3.11 `optixUtilComputeStackSizesCssCCTree()`

```

OptixResult optixUtilComputeStackSizesCssCCTree (
    const OptixStackSizes * stackSizes,
    unsigned int cssCCTree,
    unsigned int maxTraceDepth,
    unsigned int maxDCDepth,
    unsigned int * directCallableStackSizeFromTraversal,
    unsigned int * directCallableStackSizeFromState,
    unsigned int * continuationStackSize ) [inline]

```

Computes the stack size values needed to configure a pipeline.

This variant is similar to `optixUtilComputeStackSizes()`, except that it expects the value `cssCCTree` instead of `cssCC` and `maxCCDepth`.

See programming guide for an explanation of the formula.

## Parameters

|     |                                             |                                                                                |
|-----|---------------------------------------------|--------------------------------------------------------------------------------|
| in  | <i>stackSizes</i>                           | Accumulated stack sizes of all programs in the call graph.                     |
| in  | <i>cssCCTree</i>                            | Maximum stack size used by calls trees of continuation callables.              |
| in  | <i>maxTraceDepth</i>                        | Maximum depth of <code>optixTrace()</code> calls.                              |
| in  | <i>maxDCDepth</i>                           | Maximum depth of calls trees of direct callables.                              |
| out | <i>directCallableStackSizeFromTraversal</i> | Direct stack size requirement for direct callables invoked from IS or AH.      |
| out | <i>directCallableStackSizeFromState</i>     | Direct stack size requirement for direct callables invoked from RG, MS, or CH. |
| out | <i>continuationStackSize</i>                | Continuation stack requirement.                                                |

5.13.3.12 `optixUtilComputeStackSizesDCSplit()`

```

OptixResult optixUtilComputeStackSizesDCSplit (
    const OptixStackSizes * stackSizes,
    unsigned int dssDCFromTraversal,
    unsigned int dssDCFromState,
    unsigned int maxTraceDepth,
    unsigned int maxCCDepth,

```

```

    unsigned int maxDCDepthFromTraversal,
    unsigned int maxDCDepthFromState,
    unsigned int * directCallableStackSizeFromTraversal,
    unsigned int * directCallableStackSizeFromState,
    unsigned int * continuationStackSize ) [inline]

```

Computes the stack size values needed to configure a pipeline.

This variant is similar to `optixUtilComputeStackSizes()`, except that it expects the values `dssDC` and `maxDCDepth` split by call site semantic.

See programming guide for an explanation of the formula.

#### Parameters

|     |                                             |                                                                                |
|-----|---------------------------------------------|--------------------------------------------------------------------------------|
| in  | <i>stackSizes</i>                           | Accumulated stack sizes of all programs in the call graph.                     |
| in  | <i>dssDCFromTraversal</i>                   | Accumulated direct stack size of all DC programs invoked from IS or AH.        |
| in  | <i>dssDCFromState</i>                       | Accumulated direct stack size of all DC programs invoked from RG, MS, or CH.   |
| in  | <i>maxTraceDepth</i>                        | Maximum depth of <code>optixTrace()</code> calls.                              |
| in  | <i>maxCCDepth</i>                           | Maximum depth of calls trees of continuation callables.                        |
| in  | <i>maxDCDepthFromTraversal</i>              | Maximum depth of calls trees of direct callables invoked from IS or AH.        |
| in  | <i>maxDCDepthFromState</i>                  | Maximum depth of calls trees of direct callables invoked from RG, MS, or CH.   |
| out | <i>directCallableStackSizeFromTraversal</i> | Direct stack size requirement for direct callables invoked from IS or AH.      |
| out | <i>directCallableStackSizeFromState</i>     | Direct stack size requirement for direct callables invoked from RG, MS, or CH. |
| out | <i>continuationStackSize</i>                | Continuation stack requirement.                                                |

#### 5.13.3.13 optixUtilComputeStackSizesSimplePathTracer()

```

OptixResult optixUtilComputeStackSizesSimplePathTracer (
    OptixProgramGroup programGroupRG,
    OptixProgramGroup programGroupMS1,
    const OptixProgramGroup * programGroupCH1,
    unsigned int programGroupCH1Count,
    OptixProgramGroup programGroupMS2,
    const OptixProgramGroup * programGroupCH2,
    unsigned int programGroupCH2Count,
    unsigned int * directCallableStackSizeFromTraversal,
    unsigned int * directCallableStackSizeFromState,
    unsigned int * continuationStackSize,
    OptixPipeline pipeline ) [inline]

```



Computes the stack size values needed to configure a pipeline.

This variant is a specialization of `optixUtilComputeStackSizes()` for a simple path tracer with the following assumptions: There are only two ray types, camera rays and shadow rays. There are only RG, MS, and CH programs, and no AH, IS, CC, or DC programs. The camera rays invoke only the miss and closest hit programs MS1 and CH1, respectively. The CH1 program might trace shadow rays, which invoke only the miss and closest hit programs MS2 and CH2, respectively.

For flexibility, we allow for each of CH1 and CH2 not just one single program group, but an array of programs groups, and compute the maximas of the stack size requirements per array.

See programming guide for an explanation of the formula.

If the programs rely on external functions, passing the current pipeline will consider these as well. Otherwise, a null pointer can be passed instead. When external functions are present, a warning will be issued for these cases.

#### 5.13.3.14 `optixUtilDenoiserInvokeTiled()`

```
OptixResult optixUtilDenoiserInvokeTiled (
    OptixDenoiser denoiser,
    CUstream stream,
    const OptixDenoiserParams * params,
    CUdeviceptr denoiserState,
    size_t denoiserStateSizeInBytes,
    const OptixDenoiserGuideLayer * guideLayer,
    const OptixDenoiserLayer * layers,
    unsigned int numLayers,
    CUdeviceptr scratch,
    size_t scratchSizeInBytes,
    unsigned int overlapWindowSizeInPixels,
    unsigned int tileWidth,
    unsigned int tileHeight ) [inline]
```

Run denoiser on input layers see `optixDenoiserInvoke` additional parameters:

Runs the denoiser on the input layers on a single GPU and stream using `optixDenoiserInvoke`. If the input layers' dimensions are larger than the specified tile size, the image is divided into tiles using `optixUtilDenoiserSplitImage`, and multiple back-to-back invocations are performed in order to reuse the scratch space. Multiple tiles can be invoked concurrently if `optixUtilDenoiserSplitImage` is used directly and multiple scratch allocations for each concurrent invocation are used. The input parameters are the same as `optixDenoiserInvoke` except for the addition of the maximum tile size.

##### Parameters

|    |                                 |
|----|---------------------------------|
| in | <i>denoiser</i>                 |
| in | <i>stream</i>                   |
| in | <i>params</i>                   |
| in | <i>denoiserState</i>            |
| in | <i>denoiserStateSizeInBytes</i> |
| in | <i>guideLayer</i>               |

## Parameters

|    |                                  |
|----|----------------------------------|
| in | <i>layers</i>                    |
| in | <i>numLayers</i>                 |
| in | <i>scratch</i>                   |
| in | <i>scratchSizeInBytes</i>        |
| in | <i>overlapWindowSizeInPixels</i> |
| in | <i>tileWidth</i>                 |
| in | <i>tileHeight</i>                |

## 5.13.3.15 optixUtilDenoiserSplitImage()

```
OptixResult optixUtilDenoiserSplitImage (
    const OptixImage2D & input,
    const OptixImage2D & output,
    unsigned int overlapWindowSizeInPixels,
    unsigned int tileWidth,
    unsigned int tileHeight,
    std::vector< OptixUtilDenoiserImageTile > & tiles ) [inline]
```

Split image into 2D tiles given horizontal and vertical tile size.

## Parameters

|     |                                  |                                                                                              |
|-----|----------------------------------|----------------------------------------------------------------------------------------------|
| in  | <i>input</i>                     | full resolution input image to be split                                                      |
| in  | <i>output</i>                    | full resolution output image                                                                 |
| in  | <i>overlapWindowSizeInPixels</i> | see <a href="#">OptixDenoiserSizes</a> , <a href="#">optixDenoiserComputeMemoryResources</a> |
| in  | <i>tileWidth</i>                 | maximum width of tiles                                                                       |
| in  | <i>tileHeight</i>                | maximum height of tiles                                                                      |
| out | <i>tiles</i>                     | list of tiles covering the input image                                                       |

## 5.13.3.16 optixUtilGetPixelStride()

```
OptixResult optixUtilGetPixelStride (
    const OptixImage2D & image,
    unsigned int & pixelStrideInBytes ) [inline]
```

Return pixel stride in bytes for the given pixel format if the pixelStrideInBytes member of the image is zero. Otherwise return pixelStrideInBytes from the image.

## Parameters

|    |                           |                                   |
|----|---------------------------|-----------------------------------|
| in | <i>image</i>              | Image containing the pixel stride |
| in | <i>pixelStrideInBytes</i> | Pixel stride in bytes             |

### 5.13.3.17 prefixEor()

```
OPTIX_MICROMAP_INLINE_FUNC unsigned int optix_impl::prefixEor (
    unsigned int x )
```

## 5.14 Types

### Classes

- struct OptixDeviceContextOptions
- struct OptixOpacityMicromapUsageCount
- struct OptixBuildInputOpacityMicromap
- struct OptixRelocateInputOpacityMicromap
- struct OptixDisplacementMicromapDesc
- struct OptixDisplacementMicromapHistogramEntry
- struct OptixDisplacementMicromapArrayBuildInput
- struct OptixDisplacementMicromapUsageCount
- struct OptixBuildInputDisplacementMicromap
- struct OptixBuildInputTriangleArray
- struct OptixRelocateInputTriangleArray
- struct OptixBuildInputCurveArray
- struct OptixBuildInputSphereArray
- struct OptixAabb
- struct OptixBuildInputCustomPrimitiveArray
- struct OptixBuildInputInstanceArray
- struct OptixRelocateInputInstanceArray
- struct OptixBuildInput
- struct OptixRelocateInput
- struct OptixInstance
- struct OptixOpacityMicromapDesc
- struct OptixOpacityMicromapHistogramEntry
- struct OptixOpacityMicromapArrayBuildInput
- struct OptixMicromapBufferSizes
- struct OptixMicromapBuffers
- struct OptixMotionOptions
- struct OptixAccelBuildOptions
- struct OptixAccelBufferSizes
- struct OptixAccelEmitDesc
- struct OptixRelocationInfo
- struct OptixStaticTransform
- struct OptixMatrixMotionTransform
- struct OptixSRTData
- struct OptixSRTMotionTransform
- struct OptixImage2D
- struct OptixDenoiserOptions
- struct OptixDenoiserGuideLayer
- struct OptixDenoiserLayer
- struct OptixDenoiserParams
- struct OptixDenoiserSizes
- struct OptixModuleCompileBoundValueEntry
- struct OptixPayloadType

- struct OptixModuleCompileOptions
- struct OptixProgramGroupSingleModule
- struct OptixProgramGroupHitgroup
- struct OptixProgramGroupCallables
- struct OptixProgramGroupDesc
- struct OptixProgramGroupOptions
- struct OptixPipelineCompileOptions
- struct OptixPipelineLinkOptions
- struct OptixShaderBindingTable
- struct OptixStackSizes
- struct OptixBuiltinISOOptions

## Macros

- #define OPTIX\_SBT\_RECORD\_HEADER\_SIZE ((size\_t)32)
- #define OPTIX\_SBT\_RECORD\_ALIGNMENT 16ull
- #define OPTIX\_ACCEL\_BUFFER\_BYTE\_ALIGNMENT 128ull
- #define OPTIX\_INSTANCE\_BYTE\_ALIGNMENT 16ull
- #define OPTIX\_AABB\_BUFFER\_BYTE\_ALIGNMENT 8ull
- #define OPTIX\_GEOMETRY\_TRANSFORM\_BYTE\_ALIGNMENT 16ull
- #define OPTIX\_TRANSFORM\_BYTE\_ALIGNMENT 64ull
- #define OPTIX\_OPACITY\_MICROMAP\_DESC\_BUFFER\_BYTE\_ALIGNMENT 8ull
- #define OPTIX\_COMPILE\_DEFAULT\_MAX\_REGISTER\_COUNT 0
- #define OPTIX\_COMPILE\_DEFAULT\_MAX\_PAYLOAD\_TYPE\_COUNT 8
- #define OPTIX\_COMPILE\_DEFAULT\_MAX\_PAYLOAD\_VALUE\_COUNT 32
- #define OPTIX\_OPACITY\_MICROMAP\_STATE\_TRANSPARENT (0)
- #define OPTIX\_OPACITY\_MICROMAP\_STATE\_OPAQUE (1)
- #define OPTIX\_OPACITY\_MICROMAP\_STATE\_UNKNOWN\_TRANSPARENT (2)
- #define OPTIX\_OPACITY\_MICROMAP\_STATE\_UNKNOWN\_OPAQUE (3)
- #define OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_TRANSPARENT (-1)
- #define OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_OPAQUE (-2)
- #define OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_UNKNOWN\_TRANSPARENT (-3)
- #define OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_UNKNOWN\_OPAQUE (-4)
- #define OPTIX\_OPACITY\_MICROMAP\_ARRAY\_BUFFER\_BYTE\_ALIGNMENT 128ull
- #define OPTIX\_OPACITY\_MICROMAP\_MAX\_SUBDIVISION\_LEVEL 12
- #define OPTIX\_DISPLACEMENT\_MICROMAP\_MAX\_SUBDIVISION\_LEVEL 5
- #define OPTIX\_DISPLACEMENT\_MICROMAP\_DESC\_BUFFER\_BYTE\_ALIGNMENT 8ull
- #define OPTIX\_DISPLACEMENT\_MICROMAP\_ARRAY\_BUFFER\_BYTE\_ALIGNMENT 128ull

## Typedefs

- typedef unsigned long long CUdeviceptr
- typedef struct OptixDeviceContext\_t \* OptixDeviceContext
- typedef struct OptixModule\_t \* OptixModule
- typedef struct OptixProgramGroup\_t \* OptixProgramGroup
- typedef struct OptixPipeline\_t \* OptixPipeline
- typedef struct OptixDenoiser\_t \* OptixDenoiser
- typedef struct OptixTask\_t \* OptixTask
- typedef unsigned long long OptixTraversableHandle

- typedef unsigned int OptixVisibilityMask
- typedef enum OptixResult OptixResult
- typedef enum OptixDeviceProperty OptixDeviceProperty
- typedef void(\* OptixLogCallback) (unsigned int level, const char \*tag, const char \*message, void \*cbdata)
- typedef enum OptixDeviceContextValidationMode OptixDeviceContextValidationMode
- typedef struct OptixDeviceContextOptions OptixDeviceContextOptions
- typedef enum OptixDevicePropertyShaderExecutionReorderingFlags OptixDevicePropertyShaderExecutionReorderingFlags
- typedef enum OptixGeometryFlags OptixGeometryFlags
- typedef enum OptixHitKind OptixHitKind
- typedef enum OptixIndicesFormat OptixIndicesFormat
- typedef enum OptixVertexFormat OptixVertexFormat
- typedef enum OptixTransformFormat OptixTransformFormat
- typedef enum OptixDisplacementMicromapBiasAndScaleFormat OptixDisplacementMicromapBiasAndScaleFormat
- typedef enum OptixDisplacementMicromapDirectionFormat OptixDisplacementMicromapDirectionFormat
- typedef enum OptixOpacityMicromapFormat OptixOpacityMicromapFormat
- typedef enum OptixOpacityMicromapArrayIndexingMode OptixOpacityMicromapArrayIndexingMode
- typedef struct OptixOpacityMicromapUsageCount OptixOpacityMicromapUsageCount
- typedef struct OptixBuildInputOpacityMicromap OptixBuildInputOpacityMicromap
- typedef struct OptixRelocateInputOpacityMicromap OptixRelocateInputOpacityMicromap
- typedef enum OptixDisplacementMicromapFormat OptixDisplacementMicromapFormat
- typedef enum OptixDisplacementMicromapFlags OptixDisplacementMicromapFlags
- typedef enum OptixDisplacementMicromapTriangleFlags OptixDisplacementMicromapTriangleFlags
- typedef struct OptixDisplacementMicromapDesc OptixDisplacementMicromapDesc
- typedef struct OptixDisplacementMicromapHistogramEntry OptixDisplacementMicromapHistogramEntry
- typedef struct OptixDisplacementMicromapArrayBuildInput OptixDisplacementMicromapArrayBuildInput
- typedef struct OptixDisplacementMicromapUsageCount OptixDisplacementMicromapUsageCount
- typedef enum OptixDisplacementMicromapArrayIndexingMode OptixDisplacementMicromapArrayIndexingMode
- typedef struct OptixBuildInputDisplacementMicromap OptixBuildInputDisplacementMicromap
- typedef struct OptixBuildInputTriangleArray OptixBuildInputTriangleArray
- typedef struct OptixRelocateInputTriangleArray OptixRelocateInputTriangleArray
- typedef enum OptixPrimitiveType OptixPrimitiveType
- typedef enum OptixPrimitiveTypeFlags OptixPrimitiveTypeFlags
- typedef enum OptixCurveEndcapFlags OptixCurveEndcapFlags
- typedef struct OptixBuildInputCurveArray OptixBuildInputCurveArray
- typedef struct OptixBuildInputSphereArray OptixBuildInputSphereArray
- typedef struct OptixAabb OptixAabb
- typedef struct OptixBuildInputCustomPrimitiveArray OptixBuildInputCustomPrimitiveArray
- typedef struct OptixBuildInputInstanceArray OptixBuildInputInstanceArray
- typedef struct OptixRelocateInputInstanceArray OptixRelocateInputInstanceArray
- typedef enum OptixBuildInputType OptixBuildInputType

- typedef struct OptixBuildInput OptixBuildInput
- typedef struct OptixRelocateInput OptixRelocateInput
- typedef enum OptixInstanceFlags OptixInstanceFlags
- typedef struct OptixInstance OptixInstance
- typedef enum OptixBuildFlags OptixBuildFlags
- typedef enum OptixOpacityMicromapFlags OptixOpacityMicromapFlags
- typedef struct OptixOpacityMicromapDesc OptixOpacityMicromapDesc
- typedef struct OptixOpacityMicromapHistogramEntry OptixOpacityMicromapHistogramEntry
- typedef struct OptixOpacityMicromapArrayBuildInput OptixOpacityMicromapArrayBuildInput
- typedef struct OptixMicromapBufferSizes OptixMicromapBufferSizes
- typedef struct OptixMicromapBuffers OptixMicromapBuffers
- typedef enum OptixBuildOperation OptixBuildOperation
- typedef enum OptixMotionFlags OptixMotionFlags
- typedef struct OptixMotionOptions OptixMotionOptions
- typedef struct OptixAccelBuildOptions OptixAccelBuildOptions
- typedef struct OptixAccelBufferSizes OptixAccelBufferSizes
- typedef enum OptixAccelPropertyType OptixAccelPropertyType
- typedef struct OptixAccelEmitDesc OptixAccelEmitDesc
- typedef struct OptixRelocationInfo OptixRelocationInfo
- typedef struct OptixStaticTransform OptixStaticTransform
- typedef struct OptixMatrixMotionTransform OptixMatrixMotionTransform
- typedef struct OptixSRTData OptixSRTData
- typedef struct OptixSRTMotionTransform OptixSRTMotionTransform
- typedef enum OptixTraversableType OptixTraversableType
- typedef enum OptixPixelFormat OptixPixelFormat
- typedef struct OptixImage2D OptixImage2D
- typedef enum OptixDenoiserModelKind OptixDenoiserModelKind
- typedef enum OptixDenoiserAlphaMode OptixDenoiserAlphaMode
- typedef struct OptixDenoiserOptions OptixDenoiserOptions
- typedef struct OptixDenoiserGuideLayer OptixDenoiserGuideLayer
- typedef enum OptixDenoiserAOVType OptixDenoiserAOVType
- typedef struct OptixDenoiserLayer OptixDenoiserLayer
- typedef struct OptixDenoiserParams OptixDenoiserParams
- typedef struct OptixDenoiserSizes OptixDenoiserSizes
- typedef enum OptixRayFlags OptixRayFlags
- typedef enum OptixTransformType OptixTransformType
- typedef enum OptixTraversableGraphFlags OptixTraversableGraphFlags
- typedef enum OptixCompileOptimizationLevel OptixCompileOptimizationLevel
- typedef enum OptixCompileDebugLevel OptixCompileDebugLevel
- typedef enum OptixModuleCompileState OptixModuleCompileState
- typedef struct OptixModuleCompileBoundValueEntry OptixModuleCompileBoundValueEntry
- typedef enum OptixPayloadTypeID OptixPayloadTypeID
- typedef enum OptixPayloadSemantics OptixPayloadSemantics
- typedef struct OptixPayloadType OptixPayloadType
- typedef struct OptixModuleCompileOptions OptixModuleCompileOptions
- typedef enum OptixProgramGroupKind OptixProgramGroupKind
- typedef enum OptixProgramGroupFlags OptixProgramGroupFlags
- typedef struct OptixProgramGroupSingleModule OptixProgramGroupSingleModule
- typedef struct OptixProgramGroupHitgroup OptixProgramGroupHitgroup
- typedef struct OptixProgramGroupCallables OptixProgramGroupCallables



- typedef struct OptixProgramGroupDesc OptixProgramGroupDesc
- typedef struct OptixProgramGroupOptions OptixProgramGroupOptions
- typedef enum OptixExceptionCodes OptixExceptionCodes
- typedef enum OptixExceptionFlags OptixExceptionFlags
- typedef struct OptixPipelineCompileOptions OptixPipelineCompileOptions
- typedef struct OptixPipelineLinkOptions OptixPipelineLinkOptions
- typedef struct OptixShaderBindingTable OptixShaderBindingTable
- typedef struct OptixStackSizes OptixStackSizes
- typedef enum OptixQueryFunctionTableOptions OptixQueryFunctionTableOptions
- typedef OptixResult() OptixQueryFunctionTable\_t(int abiId, unsigned int numOptions, OptixQueryFunctionTableOptions \*, const void \*\*, void \*functionTable, size\_t sizeOfTable)
- typedef struct OptixBuiltinISOOptions OptixBuiltinISOOptions

## Enumerations

- enum OptixResult {  
 OPTIX\_SUCCESS = 0 ,  
 OPTIX\_ERROR\_INVALID\_VALUE = 7001 ,  
 OPTIX\_ERROR\_HOST\_OUT\_OF\_MEMORY = 7002 ,  
 OPTIX\_ERROR\_INVALID\_OPERATION = 7003 ,  
 OPTIX\_ERROR\_FILE\_IO\_ERROR = 7004 ,  
 OPTIX\_ERROR\_INVALID\_FILE\_FORMAT = 7005 ,  
 OPTIX\_ERROR\_DISK\_CACHE\_INVALID\_PATH = 7010 ,  
 OPTIX\_ERROR\_DISK\_CACHE\_PERMISSION\_ERROR = 7011 ,  
 OPTIX\_ERROR\_DISK\_CACHE\_DATABASE\_ERROR = 7012 ,  
 OPTIX\_ERROR\_DISK\_CACHE\_INVALID\_DATA = 7013 ,  
 OPTIX\_ERROR\_LAUNCH\_FAILURE = 7050 ,  
 OPTIX\_ERROR\_INVALID\_DEVICE\_CONTEXT = 7051 ,  
 OPTIX\_ERROR\_CUDA\_NOT\_INITIALIZED = 7052 ,  
 OPTIX\_ERROR\_VALIDATION\_FAILURE = 7053 ,  
 OPTIX\_ERROR\_INVALID\_INPUT = 7200 ,  
 OPTIX\_ERROR\_INVALID\_LAUNCH\_PARAMETER = 7201 ,  
 OPTIX\_ERROR\_INVALID\_PAYLOAD\_ACCESS = 7202 ,  
 OPTIX\_ERROR\_INVALID\_ATTRIBUTE\_ACCESS = 7203 ,  
 OPTIX\_ERROR\_INVALID\_FUNCTION\_USE = 7204 ,  
 OPTIX\_ERROR\_INVALID\_FUNCTION\_ARGUMENTS = 7205 ,  
 OPTIX\_ERROR\_PIPELINE\_OUT\_OF\_CONSTANT\_MEMORY = 7250 ,  
 OPTIX\_ERROR\_PIPELINE\_LINK\_ERROR = 7251 ,  
 OPTIX\_ERROR\_ILLEGAL\_DURING\_TASK\_EXECUTE = 7270 ,  
 OPTIX\_ERROR\_INTERNAL\_COMPILER\_ERROR = 7299 ,  
 OPTIX\_ERROR\_DENOISER\_MODEL\_NOT\_SET = 7300 ,  
 OPTIX\_ERROR\_DENOISER\_NOT\_INITIALIZED = 7301 ,  
 OPTIX\_ERROR\_NOT\_COMPATIBLE = 7400 ,  
 OPTIX\_ERROR\_PAYLOAD\_TYPE\_MISMATCH = 7500 ,  
 OPTIX\_ERROR\_PAYLOAD\_TYPE\_RESOLUTION\_FAILED = 7501 ,  
 OPTIX\_ERROR\_PAYLOAD\_TYPE\_ID\_INVALID = 7502 ,  
 OPTIX\_ERROR\_NOT\_SUPPORTED = 7800 ,  
 OPTIX\_ERROR\_UNSUPPORTED\_ABI\_VERSION = 7801 ,  
 OPTIX\_ERROR\_FUNCTION\_TABLE\_SIZE\_MISMATCH = 7802 ,  
 OPTIX\_ERROR\_INVALID\_ENTRY\_FUNCTION\_OPTIONS = 7803 ,  
 OPTIX\_ERROR\_LIBRARY\_NOT\_FOUND = 7804 ,  
 OPTIX\_ERROR\_ENTRY\_SYMBOL\_NOT\_FOUND = 7805 ,  
 OPTIX\_ERROR\_LIBRARY\_UNLOAD\_FAILURE = 7806 ,  
 }

```

OPTIX_ERROR_DEVICE_OUT_OF_MEMORY = 7807 ,
OPTIX_ERROR_CUDA_ERROR = 7900 ,
OPTIX_ERROR_INTERNAL_ERROR = 7990 ,
OPTIX_ERROR_UNKNOWN = 7999 }

• enum OptixDeviceProperty {
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRACE_DEPTH = 0x2001 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRAVERSABLE_GRAPH_DEPTH = 0x2002 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_PRIMITIVES_PER_GAS = 0x2003 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCES_PER_IAS = 0x2004 ,
    OPTIX_DEVICE_PROPERTY_RTCORE_VERSION = 0x2005 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCE_ID = 0x2006 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_NUM_BITS_INSTANCE_VISIBILITY_MASK = 0x2007 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_RECORDS_PER_GAS = 0x2008 ,
    OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_OFFSET = 0x2009 ,
    OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING = 0x200A }

• enum OptixDeviceContextValidationMode {
    OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_OFF = 0 ,
    OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_ALL = 0xFFFFFFFF }

• enum OptixDevicePropertyShaderExecutionReorderingFlags {
    OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_NONE = 0 ,
    OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_STANDARD = 1
    << 0 }

• enum OptixGeometryFlags {
    OPTIX_GEOMETRY_FLAG_NONE = 0 ,
    OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT = 1u << 0 ,
    OPTIX_GEOMETRY_FLAG_REQUIRE_SINGLE_ANYHIT_CALL = 1u << 1 ,
    OPTIX_GEOMETRY_FLAG_DISABLE_TRIANGLE_FACE_CULLING = 1u << 2 }

• enum OptixHitKind {
    OPTIX_HIT_KIND_TRIANGLE_FRONT_FACE = 0xFE ,
    OPTIX_HIT_KIND_TRIANGLE_BACK_FACE = 0xFF }

• enum OptixIndicesFormat {
    OPTIX_INDICES_FORMAT_NONE = 0 ,
    OPTIX_INDICES_FORMAT_UNSIGNED_SHORT3 = 0x2102 ,
    OPTIX_INDICES_FORMAT_UNSIGNED_INT3 = 0x2103 }

• enum OptixVertexFormat {
    OPTIX_VERTEX_FORMAT_NONE = 0 ,
    OPTIX_VERTEX_FORMAT_FLOAT3 = 0x2121 ,
    OPTIX_VERTEX_FORMAT_FLOAT2 = 0x2122 ,
    OPTIX_VERTEX_FORMAT_HALF3 = 0x2123 ,
    OPTIX_VERTEX_FORMAT_HALF2 = 0x2124 ,
    OPTIX_VERTEX_FORMAT_SNORM16_3 = 0x2125 ,
    OPTIX_VERTEX_FORMAT_SNORM16_2 = 0x2126 }

• enum OptixTransformFormat {
    OPTIX_TRANSFORM_FORMAT_NONE = 0 ,
    OPTIX_TRANSFORM_FORMAT_MATRIX_FLOAT12 = 0x21E1 }

• enum OptixDisplacementMicromapBiasAndScaleFormat {
    OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_NONE = 0 ,
    OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_FLOAT2 = 0x2241 ,
    OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_HALF2 = 0x2242 }

• enum OptixDisplacementMicromapDirectionFormat {
    OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_NONE = 0 ,
    OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_FLOAT3 = 0x2261 ,
    OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_HALF3 = 0x2262 }

```



- enum OptixOpacityMicromapFormat {  
OPTIX\_OPACITY\_MICROMAP\_FORMAT\_NONE = 0 ,  
OPTIX\_OPACITY\_MICROMAP\_FORMAT\_2\_STATE = 1 ,  
OPTIX\_OPACITY\_MICROMAP\_FORMAT\_4\_STATE = 2 }
- enum OptixOpacityMicromapArrayIndexingMode {  
OPTIX\_OPACITY\_MICROMAP\_ARRAY\_INDEXING\_MODE\_NONE = 0 ,  
OPTIX\_OPACITY\_MICROMAP\_ARRAY\_INDEXING\_MODE\_LINEAR = 1 ,  
OPTIX\_OPACITY\_MICROMAP\_ARRAY\_INDEXING\_MODE\_INDEXED = 2 }
- enum OptixDisplacementMicromapFormat {  
OPTIX\_DISPLACEMENT\_MICROMAP\_FORMAT\_NONE = 0 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_FORMAT\_64\_MICRO\_TRIS\_64\_BYTES = 1 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_FORMAT\_256\_MICRO\_TRIS\_128\_BYTES = 2 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_FORMAT\_1024\_MICRO\_TRIS\_128\_BYTES = 3 }
- enum OptixDisplacementMicromapFlags {  
OPTIX\_DISPLACEMENT\_MICROMAP\_FLAG\_NONE = 0 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_FLAG\_PREFER\_FAST\_TRACE = 1 << 0 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_FLAG\_PREFER\_FAST\_BUILD = 1 << 1 }
- enum OptixDisplacementMicromapTriangleFlags {  
OPTIX\_DISPLACEMENT\_MICROMAP\_TRIANGLE\_FLAG\_NONE = 0 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_TRIANGLE\_FLAG\_DECIMATE\_EDGE\_01 = 1 << 0 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_TRIANGLE\_FLAG\_DECIMATE\_EDGE\_12 = 1 << 1 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_TRIANGLE\_FLAG\_DECIMATE\_EDGE\_20 = 1 << 2 }
- enum OptixDisplacementMicromapArrayIndexingMode {  
OPTIX\_DISPLACEMENT\_MICROMAP\_ARRAY\_INDEXING\_MODE\_NONE = 0 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_ARRAY\_INDEXING\_MODE\_LINEAR = 1 ,  
OPTIX\_DISPLACEMENT\_MICROMAP\_ARRAY\_INDEXING\_MODE\_INDEXED = 2 }
- enum OptixPrimitiveType {  
OPTIX\_PRIMITIVE\_TYPE\_CUSTOM = 0x2500 ,  
OPTIX\_PRIMITIVE\_TYPE\_ROUND\_QUADRATIC\_BSPLINE = 0x2501 ,  
OPTIX\_PRIMITIVE\_TYPE\_ROUND\_CUBIC\_BSPLINE = 0x2502 ,  
OPTIX\_PRIMITIVE\_TYPE\_ROUND\_LINEAR = 0x2503 ,  
OPTIX\_PRIMITIVE\_TYPE\_ROUND\_CATMULLROM = 0x2504 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAT\_QUADRATIC\_BSPLINE = 0x2505 ,  
OPTIX\_PRIMITIVE\_TYPE\_SPHERE = 0x2506 ,  
OPTIX\_PRIMITIVE\_TYPE\_ROUND\_CUBIC\_BEZIER = 0x2507 ,  
OPTIX\_PRIMITIVE\_TYPE\_TRIANGLE = 0x2531 ,  
OPTIX\_PRIMITIVE\_TYPE\_DISPLACED\_MICROMESH\_TRIANGLE = 0x2532 }
- enum OptixPrimitiveTypeFlags {  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_CUSTOM = 1 << 0 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_ROUND\_QUADRATIC\_BSPLINE = 1 << 1 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_ROUND\_CUBIC\_BSPLINE = 1 << 2 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_ROUND\_LINEAR = 1 << 3 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_ROUND\_CATMULLROM = 1 << 4 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_FLAT\_QUADRATIC\_BSPLINE = 1 << 5 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_SPHERE = 1 << 6 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_ROUND\_CUBIC\_BEZIER = 1 << 7 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_TRIANGLE = 1 << 31 ,  
OPTIX\_PRIMITIVE\_TYPE\_FLAGS\_DISPLACED\_MICROMESH\_TRIANGLE = 1 << 30 }
- enum OptixCurveEndcapFlags {  
OPTIX\_CURVE\_ENDCAP\_DEFAULT = 0 ,  
OPTIX\_CURVE\_ENDCAP\_ON = 1 << 0 }
- enum OptixBuildInputType {  
OPTIX\_BUILD\_INPUT\_TYPE\_TRIANGLES = 0x2141 ,

```

OPTIX_BUILD_INPUT_TYPE_CUSTOM_PRIMITIVES = 0x2142 ,
OPTIX_BUILD_INPUT_TYPE_INSTANCES = 0x2143 ,
OPTIX_BUILD_INPUT_TYPE_INSTANCE_POINTERS = 0x2144 ,
OPTIX_BUILD_INPUT_TYPE_CURVES = 0x2145 ,
OPTIX_BUILD_INPUT_TYPE_SPHERES = 0x2146 }

• enum OptixInstanceFlags {
    OPTIX_INSTANCE_FLAG_NONE = 0 ,
    OPTIX_INSTANCE_FLAG_DISABLE_TRIANGLE_FACE_CULLING = 1u << 0 ,
    OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING = 1u << 1 ,
    OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT = 1u << 2 ,
    OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT = 1u << 3 ,
    OPTIX_INSTANCE_FLAG_FORCE_OPACITY_MICROMAP_2_STATE = 1u << 4 ,
    OPTIX_INSTANCE_FLAG_DISABLE_OPACITY_MICROMAPS = 1u << 5 }

• enum OptixBuildFlags {
    OPTIX_BUILD_FLAG_NONE = 0 ,
    OPTIX_BUILD_FLAG_ALLOW_UPDATE = 1u << 0 ,
    OPTIX_BUILD_FLAG_ALLOW_COMPACTION = 1u << 1 ,
    OPTIX_BUILD_FLAG_PREFER_FAST_TRACE = 1u << 2 ,
    OPTIX_BUILD_FLAG_PREFER_FAST_BUILD = 1u << 3 ,
    OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS = 1u << 4 ,
    OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS = 1u << 5 ,
    OPTIX_BUILD_FLAG_ALLOW_OPACITY_MICROMAP_UPDATE = 1u << 6 ,
    OPTIX_BUILD_FLAG_ALLOW_DISABLE_OPACITY_MICROMAPS = 1u << 7 }

• enum OptixOpacityMicromapFlags {
    OPTIX_OPACITY_MICROMAP_FLAG_NONE = 0 ,
    OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_TRACE = 1 << 0 ,
    OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_BUILD = 1 << 1 }

• enum OptixBuildOperation {
    OPTIX_BUILD_OPERATION_BUILD = 0x2161 ,
    OPTIX_BUILD_OPERATION_UPDATE = 0x2162 }

• enum OptixMotionFlags {
    OPTIX_MOTION_FLAG_NONE = 0 ,
    OPTIX_MOTION_FLAG_START_VANISH = 1u << 0 ,
    OPTIX_MOTION_FLAG_END_VANISH = 1u << 1 }

• enum OptixAccelPropertyType {
    OPTIX_PROPERTY_TYPE_COMPACTED_SIZE = 0x2181 ,
    OPTIX_PROPERTY_TYPE_AABBS = 0x2182 }

• enum OptixTraversableType {
    OPTIX_TRAVERSABLE_TYPE_STATIC_TRANSFORM = 0x21C1 ,
    OPTIX_TRAVERSABLE_TYPE_MATRIX_MOTION_TRANSFORM = 0x21C2 ,
    OPTIX_TRAVERSABLE_TYPE_SRT_MOTION_TRANSFORM = 0x21C3 }

• enum OptixPixelFormat {
    OPTIX_PIXEL_FORMAT_HALF1 = 0x220a ,
    OPTIX_PIXEL_FORMAT_HALF2 = 0x2207 ,
    OPTIX_PIXEL_FORMAT_HALF3 = 0x2201 ,
    OPTIX_PIXEL_FORMAT_HALF4 = 0x2202 ,
    OPTIX_PIXEL_FORMAT_FLOAT1 = 0x220b ,
    OPTIX_PIXEL_FORMAT_FLOAT2 = 0x2208 ,
    OPTIX_PIXEL_FORMAT_FLOAT3 = 0x2203 ,
    OPTIX_PIXEL_FORMAT_FLOAT4 = 0x2204 ,
    OPTIX_PIXEL_FORMAT_UCHAR3 = 0x2205 ,
    OPTIX_PIXEL_FORMAT_UCHAR4 = 0x2206 ,
    OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER = 0x2209 }

```

- enum OptixDenoiserModelKind {  
OPTIX\_DENOISER\_MODEL\_KIND\_LDR = 0x2322 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_HDR = 0x2323 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_AOV = 0x2324 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_TEMPORAL = 0x2325 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_TEMPORAL\_AOV = 0x2326 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_UPSCALE2X = 0x2327 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_TEMPORAL\_UPSCALE2X = 0x2328 }
- enum OptixDenoiserAlphaMode {  
OPTIX\_DENOISER\_ALPHA\_MODE\_COPY = 0 ,  
OPTIX\_DENOISER\_ALPHA\_MODE\_DENOISE = 1 }
- enum OptixDenoiserAOVType {  
OPTIX\_DENOISER\_AOV\_TYPE\_NONE = 0 ,  
OPTIX\_DENOISER\_AOV\_TYPE\_BEAUTY = 0x7000 ,  
OPTIX\_DENOISER\_AOV\_TYPE\_SPECULAR = 0x7001 ,  
OPTIX\_DENOISER\_AOV\_TYPE\_REFLECTION = 0x7002 ,  
OPTIX\_DENOISER\_AOV\_TYPE\_REFRACTION = 0x7003 ,  
OPTIX\_DENOISER\_AOV\_TYPE\_DIFFUSE = 0x7004 }
- enum OptixRayFlags {  
OPTIX\_RAY\_FLAG\_NONE = 0u ,  
OPTIX\_RAY\_FLAG\_DISABLE\_ANYHIT = 1u << 0 ,  
OPTIX\_RAY\_FLAG\_ENFORCE\_ANYHIT = 1u << 1 ,  
OPTIX\_RAY\_FLAG\_TERMINATE\_ON\_FIRST\_HIT = 1u << 2 ,  
OPTIX\_RAY\_FLAG\_DISABLE\_CLOSESTHIT = 1u << 3 ,  
OPTIX\_RAY\_FLAG\_CULL\_BACK\_FACING\_TRIANGLES = 1u << 4 ,  
OPTIX\_RAY\_FLAG\_CULL\_FRONT\_FACING\_TRIANGLES = 1u << 5 ,  
OPTIX\_RAY\_FLAG\_CULL\_DISABLED\_ANYHIT = 1u << 6 ,  
OPTIX\_RAY\_FLAG\_CULL\_ENFORCED\_ANYHIT = 1u << 7 ,  
OPTIX\_RAY\_FLAG\_FORCE\_OPACITY\_MICROMAP\_2\_STATE = 1u << 10 }
- enum OptixTransformType {  
OPTIX\_TRANSFORM\_TYPE\_NONE = 0 ,  
OPTIX\_TRANSFORM\_TYPE\_STATIC\_TRANSFORM = 1 ,  
OPTIX\_TRANSFORM\_TYPE\_MATRIX\_MOTION\_TRANSFORM = 2 ,  
OPTIX\_TRANSFORM\_TYPE\_SRT\_MOTION\_TRANSFORM = 3 ,  
OPTIX\_TRANSFORM\_TYPE\_INSTANCE = 4 }
- enum OptixTraversableGraphFlags {  
OPTIX\_TRAVERSABLE\_GRAPH\_FLAG\_ALLOW\_ANY = 0 ,  
OPTIX\_TRAVERSABLE\_GRAPH\_FLAG\_ALLOW\_SINGLE\_GAS = 1u << 0 ,  
OPTIX\_TRAVERSABLE\_GRAPH\_FLAG\_ALLOW\_SINGLE\_LEVEL\_INSTANCING = 1u << 1 }
- enum OptixCompileOptimizationLevel {  
OPTIX\_COMPILE\_OPTIMIZATION\_DEFAULT = 0 ,  
OPTIX\_COMPILE\_OPTIMIZATION\_LEVEL\_0 = 0x2340 ,  
OPTIX\_COMPILE\_OPTIMIZATION\_LEVEL\_1 = 0x2341 ,  
OPTIX\_COMPILE\_OPTIMIZATION\_LEVEL\_2 = 0x2342 ,  
OPTIX\_COMPILE\_OPTIMIZATION\_LEVEL\_3 = 0x2343 }
- enum OptixCompileDebugLevel {  
OPTIX\_COMPILE\_DEBUG\_LEVEL\_DEFAULT = 0 ,  
OPTIX\_COMPILE\_DEBUG\_LEVEL\_NONE = 0x2350 ,  
OPTIX\_COMPILE\_DEBUG\_LEVEL\_MINIMAL = 0x2351 ,  
OPTIX\_COMPILE\_DEBUG\_LEVEL\_MODERATE = 0x2353 ,  
OPTIX\_COMPILE\_DEBUG\_LEVEL\_FULL = 0x2352 }
- enum OptixModuleCompileState {  
OPTIX\_MODULE\_COMPILE\_STATE\_NOT\_STARTED = 0x2360 ,

```

OPTIX_MODULE_COMPILE_STATE_STARTED = 0x2361 ,
OPTIX_MODULE_COMPILE_STATE_IMPENDING_FAILURE = 0x2362 ,
OPTIX_MODULE_COMPILE_STATE_FAILED = 0x2363 ,
OPTIX_MODULE_COMPILE_STATE_COMPLETED = 0x2364 }

• enum OptixPayloadTypeID {
    OPTIX_PAYLOAD_TYPE_DEFAULT = 0 ,
    OPTIX_PAYLOAD_TYPE_ID_0 = (1 << 0u) ,
    OPTIX_PAYLOAD_TYPE_ID_1 = (1 << 1u) ,
    OPTIX_PAYLOAD_TYPE_ID_2 = (1 << 2u) ,
    OPTIX_PAYLOAD_TYPE_ID_3 = (1 << 3u) ,
    OPTIX_PAYLOAD_TYPE_ID_4 = (1 << 4u) ,
    OPTIX_PAYLOAD_TYPE_ID_5 = (1 << 5u) ,
    OPTIX_PAYLOAD_TYPE_ID_6 = (1 << 6u) ,
    OPTIX_PAYLOAD_TYPE_ID_7 = (1 << 7u) }

• enum OptixPayloadSemantics {
    OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_NONE = 0 ,
    OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ = 1u << 0 ,
    OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_WRITE = 2u << 0 ,
    OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ_WRITE = 3u << 0 ,
    OPTIX_PAYLOAD_SEMANTICS_CH_NONE = 0 ,
    OPTIX_PAYLOAD_SEMANTICS_CH_READ = 1u << 2 ,
    OPTIX_PAYLOAD_SEMANTICS_CH_WRITE = 2u << 2 ,
    OPTIX_PAYLOAD_SEMANTICS_CH_READ_WRITE = 3u << 2 ,
    OPTIX_PAYLOAD_SEMANTICS_MS_NONE = 0 ,
    OPTIX_PAYLOAD_SEMANTICS_MS_READ = 1u << 4 ,
    OPTIX_PAYLOAD_SEMANTICS_MS_WRITE = 2u << 4 ,
    OPTIX_PAYLOAD_SEMANTICS_MS_READ_WRITE = 3u << 4 ,
    OPTIX_PAYLOAD_SEMANTICS_AH_NONE = 0 ,
    OPTIX_PAYLOAD_SEMANTICS_AH_READ = 1u << 6 ,
    OPTIX_PAYLOAD_SEMANTICS_AH_WRITE = 2u << 6 ,
    OPTIX_PAYLOAD_SEMANTICS_AH_READ_WRITE = 3u << 6 ,
    OPTIX_PAYLOAD_SEMANTICS_IS_NONE = 0 ,
    OPTIX_PAYLOAD_SEMANTICS_IS_READ = 1u << 8 ,
    OPTIX_PAYLOAD_SEMANTICS_IS_WRITE = 2u << 8 ,
    OPTIX_PAYLOAD_SEMANTICS_IS_READ_WRITE = 3u << 8 }

• enum OptixProgramGroupKind {
    OPTIX_PROGRAM_GROUP_KIND_RAYGEN = 0x2421 ,
    OPTIX_PROGRAM_GROUP_KIND_MISS = 0x2422 ,
    OPTIX_PROGRAM_GROUP_KIND_EXCEPTION = 0x2423 ,
    OPTIX_PROGRAM_GROUP_KIND_HITGROUP = 0x2424 ,
    OPTIX_PROGRAM_GROUP_KIND_CALLABLES = 0x2425 }

• enum OptixProgramGroupFlags { OPTIX_PROGRAM_GROUP_FLAGS_NONE = 0 }

• enum OptixExceptionCodes {
    OPTIX_EXCEPTION_CODE_STACK_OVERFLOW = -1 ,
    OPTIX_EXCEPTION_CODE_TRACE_DEPTH_EXCEEDED = -2 }

• enum OptixExceptionFlags {
    OPTIX_EXCEPTION_FLAG_NONE = 0 ,
    OPTIX_EXCEPTION_FLAG_STACK_OVERFLOW = 1u << 0 ,
    OPTIX_EXCEPTION_FLAG_TRACE_DEPTH = 1u << 1 ,
    OPTIX_EXCEPTION_FLAG_USER = 1u << 2 }

• enum OptixQueryFunctionTableOptions { OPTIX_QUERY_FUNCTION_TABLE_OPTION_
    DUMMY = 0 }

```

### 5.14.1 Detailed Description

OptiX Types.

### 5.14.2 Macro Definition Documentation

#### 5.14.2.1 OPTIX\_AABB\_BUFFER\_BYTE\_ALIGNMENT

```
#define OPTIX_AABB_BUFFER_BYTE_ALIGNMENT 8u11
```

Alignment requirement for [OptixBuildInputCustomPrimitiveArray::aabbBuffers](#).

#### 5.14.2.2 OPTIX\_ACCEL\_BUFFER\_BYTE\_ALIGNMENT

```
#define OPTIX_ACCEL_BUFFER_BYTE_ALIGNMENT 128u11
```

Alignment requirement for output and temporary buffers for acceleration structures.

#### 5.14.2.3 OPTIX\_COMPILE\_DEFAULT\_MAX\_PAYLOAD\_TYPE\_COUNT

```
#define OPTIX_COMPILE_DEFAULT_MAX_PAYLOAD_TYPE_COUNT 8
```

Maximum number of payload types allowed.

#### 5.14.2.4 OPTIX\_COMPILE\_DEFAULT\_MAX\_PAYLOAD\_VALUE\_COUNT

```
#define OPTIX_COMPILE_DEFAULT_MAX_PAYLOAD_VALUE_COUNT 32
```

Maximum number of payload values allowed.

#### 5.14.2.5 OPTIX\_COMPILE\_DEFAULT\_MAX\_REGISTER\_COUNT

```
#define OPTIX_COMPILE_DEFAULT_MAX_REGISTER_COUNT 0
```

Maximum number of registers allowed. Defaults to no explicit limit.

#### 5.14.2.6 OPTIX\_DISPLACEMENT\_MICROMAP\_ARRAY\_BUFFER\_BYTE\_ALIGNMENT

```
#define OPTIX_DISPLACEMENT_MICROMAP_ARRAY_BUFFER_BYTE_ALIGNMENT 128u11
```

Alignment requirement for displacement micromap array buffers.

#### 5.14.2.7 OPTIX\_DISPLACEMENT\_MICROMAP\_DESC\_BUFFER\_BYTE\_ALIGNMENT

```
#define OPTIX_DISPLACEMENT_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT 8u11
```

Alignment requirement for displacement micromap descriptor buffers.

#### 5.14.2.8 OPTIX\_DISPLACEMENT\_MICROMAP\_MAX\_SUBDIVISION\_LEVEL

```
#define OPTIX_DISPLACEMENT_MICROMAP_MAX_SUBDIVISION_LEVEL 5
```

Maximum subdivision level for displacement micromaps.

#### 5.14.2.9 OPTIX\_GEOMETRY\_TRANSFORM\_BYTE\_ALIGNMENT

```
#define OPTIX_GEOMETRY_TRANSFORM_BYTE_ALIGNMENT 16u11
```

Alignment requirement for [OptixBuildInputTriangleArray::preTransform](#).

#### 5.14.2.10 OPTIX\_INSTANCE\_BYTE\_ALIGNMENT

```
#define OPTIX_INSTANCE_BYTE_ALIGNMENT 16u11
```

Alignment requirement for [OptixBuildInputInstanceArray::instances](#).

#### 5.14.2.11 OPTIX\_OPACITY\_MICROMAP\_ARRAY\_BUFFER\_BYTE\_ALIGNMENT

```
#define OPTIX_OPACITY_MICROMAP_ARRAY_BUFFER_BYTE_ALIGNMENT 128u11
```

Alignment requirement for opacity micromap array buffers.

#### 5.14.2.12 OPTIX\_OPACITY\_MICROMAP\_DESC\_BUFFER\_BYTE\_ALIGNMENT

```
#define OPTIX_OPACITY_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT 8u11
```

Alignment requirement for [OptixOpacityMicromapArrayBuildInput::perMicromapDescBuffer](#).

#### 5.14.2.13 OPTIX\_OPACITY\_MICROMAP\_MAX\_SUBDIVISION\_LEVEL

```
#define OPTIX_OPACITY_MICROMAP_MAX_SUBDIVISION_LEVEL 12
```

Maximum subdivision level for opacity micromaps.

#### 5.14.2.14 OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_OPAQUE

```
#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_OPAQUE (-2)
```

#### 5.14.2.15 OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_TRANSPARENT

```
#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_TRANSPARENT (-1)
```

Predefined index to indicate that a triangle in the BVH build doesn't have an associated opacity micromap, and that it should revert to one of the four possible states for the full triangle.

#### 5.14.2.16 OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_UNKNOWN\_OPAQUE

```
#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_OPAQUE (-4)
```

#### 5.14.2.17 OPTIX\_OPACITY\_MICROMAP\_PREDEFINED\_INDEX\_FULLY\_UNKNOWN\_TRANSPARENT

```
#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_TRANSPARENT (-3)
```

#### 5.14.2.18 OPTIX\_OPACITY\_MICROMAP\_STATE\_OPAQUE

```
#define OPTIX_OPACITY_MICROMAP_STATE_OPAQUE (1)
```

#### 5.14.2.19 OPTIX\_OPACITY\_MICROMAP\_STATE\_TRANSPARENT

```
#define OPTIX_OPACITY_MICROMAP_STATE_TRANSPARENT (0)
```

Opacity micromaps encode the states of microtriangles in either 1 bit (2-state) or 2 bits (4-state) using the following values.

#### 5.14.2.20 OPTIX\_OPACITY\_MICROMAP\_STATE\_UNKNOWN\_OPAQUE

```
#define OPTIX_OPACITY_MICROMAP_STATE_UNKNOWN_OPAQUE (3)
```

## 5.14.2.21 OPTIX\_OPACITY\_MICROMAP\_STATE\_UNKNOWN\_TRANSPARENT

```
#define OPTIX_OPACITY_MICROMAP_STATE_UNKNOWN_TRANSPARENT (2)
```

## 5.14.2.22 OPTIX\_SBT\_RECORD\_ALIGNMENT

```
#define OPTIX_SBT_RECORD_ALIGNMENT 16ull
```

Alignment requirement for device pointers in [OptixShaderBindingTable](#).

## 5.14.2.23 OPTIX\_SBT\_RECORD\_HEADER\_SIZE

```
#define OPTIX_SBT_RECORD_HEADER_SIZE ((size_t)32)
```

Size of the SBT record headers.

## 5.14.2.24 OPTIX\_TRANSFORM\_BYTE\_ALIGNMENT

```
#define OPTIX_TRANSFORM_BYTE_ALIGNMENT 64ull
```

Alignment requirement for [OptixStaticTransform](#), [OptixMatrixMotionTransform](#), [OptixSRTMotionTransform](#).

## 5.14.3 Typedef Documentation

## 5.14.3.1 CUdeviceptr

```
typedef unsigned long long CUdeviceptr
```

CUDA device pointer.

## 5.14.3.2 OptixAabb

```
typedef struct OptixAabb OptixAabb
```

AABB inputs.

## 5.14.3.3 OptixAccelBufferSizes

```
typedef struct OptixAccelBufferSizes OptixAccelBufferSizes
```

Struct for querying builder allocation requirements.

Once queried the sizes should be used to allocate device memory of at least these sizes.

See also [optixAccelComputeMemoryUsage\(\)](#)

## 5.14.3.4 OptixAccelBuildOptions

```
typedef struct OptixAccelBuildOptions OptixAccelBuildOptions
```

Build options for acceleration structures.

See also [optixAccelComputeMemoryUsage\(\)](#), [optixAccelBuild\(\)](#)

## 5.14.3.5 OptixAccelEmitDesc

```
typedef struct OptixAccelEmitDesc OptixAccelEmitDesc
```

Specifies a type and output destination for emitted post-build properties.

See also [optixAccelBuild\(\)](#)



#### 5.14.3.6 OptixAccelPropertyType

```
typedef enum OptixAccelPropertyType OptixAccelPropertyType
```

Properties which can be emitted during acceleration structure build.

See also [OptixAccelEmitDesc::type](#).

#### 5.14.3.7 OptixBuildFlags

```
typedef enum OptixBuildFlags OptixBuildFlags
```

Builder Options.

Used for [OptixAccelBuildOptions::buildFlags](#). Can be or'ed together.

#### 5.14.3.8 OptixBuildInput

```
typedef struct OptixBuildInput OptixBuildInput
```

Build inputs.

All of them support motion and the size of the data arrays needs to match the number of motion steps

See also [optixAccelComputeMemoryUsage\(\)](#), [optixAccelBuild\(\)](#)

#### 5.14.3.9 OptixBuildInputCurveArray

```
typedef struct OptixBuildInputCurveArray OptixBuildInputCurveArray
```

Curve inputs.

A curve is a swept surface defined by a 3D spline curve and a varying width (radius). A curve (or "strand") of degree  $d$  ( $3=\text{cubic}$ ,  $2=\text{quadratic}$ ,  $1=\text{linear}$ ) is represented by  $N > d$  vertices and  $N$  width values, and comprises  $N - d$  segments. Each segment is defined by  $d+1$  consecutive vertices. Each curve may have a different number of vertices.

OptiX describes the curve array as a list of curve segments. The primitive id is the segment number. It is the user's responsibility to maintain a mapping between curves and curve segments. Each index buffer entry  $i = \text{indexBuffer}[\text{primid}]$  specifies the start of a curve segment, represented by  $d+1$  consecutive vertices in the vertex buffer, and  $d+1$  consecutive widths in the width buffer. Width is interpolated the same way vertices are interpolated, that is, using the curve basis.

Each curves build input has only one SBT record. To create curves with different materials in the same BVH, use multiple build inputs.

See also [OptixBuildInput::curveArray](#)

#### 5.14.3.10 OptixBuildInputCustomPrimitiveArray

```
typedef struct OptixBuildInputCustomPrimitiveArray
OptixBuildInputCustomPrimitiveArray
```

Custom primitive inputs.

See also [OptixBuildInput::customPrimitiveArray](#)

#### 5.14.3.11 OptixBuildInputDisplacementMicromap

```
typedef struct OptixBuildInputDisplacementMicromap
OptixBuildInputDisplacementMicromap
```

Optional displacement part of a triangle array input.



#### 5.14.3.12 OptixBuildInputInstanceArray

```
typedef struct OptixBuildInputInstanceArray OptixBuildInputInstanceArray
```

Instance and instance pointer inputs.

See also [OptixBuildInput::instanceArray](#)

#### 5.14.3.13 OptixBuildInputOpacityMicromap

```
typedef struct OptixBuildInputOpacityMicromap OptixBuildInputOpacityMicromap
```

#### 5.14.3.14 OptixBuildInputSphereArray

```
typedef struct OptixBuildInputSphereArray OptixBuildInputSphereArray
```

Sphere inputs.

A sphere is defined by a center point and a radius. Each center point is represented by a vertex in the vertex buffer. There is either a single radius for all spheres, or the radii are represented by entries in the radius buffer.

The vertex buffers and radius buffers point to a host array of device pointers, one per motion step. Host array size must match the number of motion keys as set in [OptixMotionOptions](#) (or an array of size 1 if [OptixMotionOptions::numKeys](#) is set to 0 or 1). Each per motion key device pointer must point to an array of vertices corresponding to the center points of the spheres, or an array of 1 or N radii. Format `OPTIX_VERTEX_FORMAT_FLOAT3` is used for vertices, `OPTIX_VERTEX_FORMAT_FLOAT` for radii.

See also [OptixBuildInput::sphereArray](#)

#### 5.14.3.15 OptixBuildInputTriangleArray

```
typedef struct OptixBuildInputTriangleArray OptixBuildInputTriangleArray
```

Triangle inputs.

See also [OptixBuildInput::triangleArray](#)

#### 5.14.3.16 OptixBuildInputType

```
typedef enum OptixBuildInputType OptixBuildInputType
```

Enum to distinguish the different build input types.

See also [OptixBuildInput::type](#)

#### 5.14.3.17 OptixBuildOperation

```
typedef enum OptixBuildOperation OptixBuildOperation
```

Enum to specify the acceleration build operation.

Used in [OptixAccelBuildOptions](#), which is then passed to `optixAccelBuild` and `optixAccelComputeMemoryUsage`, this enum indicates whether to do a build or an update of the acceleration structure.

Acceleration structure updates utilize the same acceleration structure, but with updated bounds. Updates are typically much faster than builds, however, large perturbations can degrade the quality of the acceleration structure.

See also [optixAccelComputeMemoryUsage\(\)](#), [optixAccelBuild\(\)](#), [OptixAccelBuildOptions](#)

#### 5.14.3.18 OptixBuiltinISOptions

```
typedef struct OptixBuiltinISOptions OptixBuiltinISOptions
```

Specifies the options for retrieving an intersection program for a built-in primitive type. The primitive type must not be `OPTIX_PRIMITIVE_TYPE_CUSTOM`.

See also `optixBuiltinISModuleGet()`

#### 5.14.3.19 OptixCompileDebugLevel

```
typedef enum OptixCompileDebugLevel OptixCompileDebugLevel
```

Debug levels.

See also `OptixModuleCompileOptions::debugLevel`

#### 5.14.3.20 OptixCompileOptimizationLevel

```
typedef enum OptixCompileOptimizationLevel OptixCompileOptimizationLevel
```

Optimization levels.

See also `OptixModuleCompileOptions::optLevel`

#### 5.14.3.21 OptixCurveEndcapFlags

```
typedef enum OptixCurveEndcapFlags OptixCurveEndcapFlags
```

Curve end cap types, for non-linear curves.

#### 5.14.3.22 OptixDenoiser

```
typedef struct OptixDenoiser_t* OptixDenoiser
```

Opaque type representing a denoiser instance.

#### 5.14.3.23 OptixDenoiserAlphaMode

```
typedef enum OptixDenoiserAlphaMode OptixDenoiserAlphaMode
```

Alpha denoising mode.

See also `optixDenoiserCreate()`

#### 5.14.3.24 OptixDenoiserAOVType

```
typedef enum OptixDenoiserAOVType OptixDenoiserAOVType
```

AOV type used by the denoiser.

#### 5.14.3.25 OptixDenoiserGuideLayer

```
typedef struct OptixDenoiserGuideLayer OptixDenoiserGuideLayer
```

Guide layer for the denoiser.

See also `optixDenoiserInvoke()`

#### 5.14.3.26 OptixDenoiserLayer

```
typedef struct OptixDenoiserLayer OptixDenoiserLayer
```

Input/Output layers for the denoiser.

See also [optixDenoiserInvoke\(\)](#)

#### 5.14.3.27 OptixDenoiserModelKind

```
typedef enum OptixDenoiserModelKind OptixDenoiserModelKind
```

Model kind used by the denoiser.

See also [optixDenoiserCreate](#)

#### 5.14.3.28 OptixDenoiserOptions

```
typedef struct OptixDenoiserOptions OptixDenoiserOptions
```

Options used by the denoiser.

See also [optixDenoiserCreate\(\)](#)

#### 5.14.3.29 OptixDenoiserParams

```
typedef struct OptixDenoiserParams OptixDenoiserParams
```

Various parameters used by the denoiser.

See also [optixDenoiserInvoke\(\)](#)

[optixDenoiserComputeIntensity\(\)](#)

[optixDenoiserComputeAverageColor\(\)](#)

#### 5.14.3.30 OptixDenoiserSizes

```
typedef struct OptixDenoiserSizes OptixDenoiserSizes
```

Various sizes related to the denoiser.

See also [optixDenoiserComputeMemoryResources\(\)](#)

#### 5.14.3.31 OptixDeviceContext

```
typedef struct OptixDeviceContext_t* OptixDeviceContext
```

Opaque type representing a device context.

#### 5.14.3.32 OptixDeviceContextOptions

```
typedef struct OptixDeviceContextOptions OptixDeviceContextOptions
```

Parameters used for [optixDeviceContextCreate\(\)](#)

See also [optixDeviceContextCreate\(\)](#)

#### 5.14.3.33 OptixDeviceContextValidationMode

```
typedef enum OptixDeviceContextValidationMode  
OptixDeviceContextValidationMode
```

Validation mode settings.

When enabled, certain device code utilities will be enabled to provide as good debug and error checking facilities as possible.

See also [optixDeviceContextCreate\(\)](#)

#### 5.14.3.34 OptixDeviceProperty

```
typedef enum OptixDeviceProperty OptixDeviceProperty
```

Parameters used for `optixDeviceContextGetProperty()`

See also `optixDeviceContextGetProperty()`

#### 5.14.3.35 OptixDevicePropertyShaderExecutionReorderingFlags

```
typedef enum OptixDevicePropertyShaderExecutionReorderingFlags
OptixDevicePropertyShaderExecutionReorderingFlags
```

Flags used to interpret the result of `optixDeviceContextGetProperty()` and `OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING`.

See also `optixDeviceContextGetProperty()`

#### 5.14.3.36 OptixDisplacementMicromapArrayBuildInput

```
typedef struct OptixDisplacementMicromapArrayBuildInput
OptixDisplacementMicromapArrayBuildInput
```

Inputs to displacement micromaps array construction.

#### 5.14.3.37 OptixDisplacementMicromapArrayIndexingMode

```
typedef enum OptixDisplacementMicromapArrayIndexingMode
OptixDisplacementMicromapArrayIndexingMode
```

indexing mode of triangles to displacement micromaps in an array, used in `OptixBuildInputDisplacementMicromap`.

#### 5.14.3.38 OptixDisplacementMicromapBiasAndScaleFormat

```
typedef enum OptixDisplacementMicromapBiasAndScaleFormat
OptixDisplacementMicromapBiasAndScaleFormat
```

#### 5.14.3.39 OptixDisplacementMicromapDesc

```
typedef struct OptixDisplacementMicromapDesc OptixDisplacementMicromapDesc
```

#### 5.14.3.40 OptixDisplacementMicromapDirectionFormat

```
typedef enum OptixDisplacementMicromapDirectionFormat
OptixDisplacementMicromapDirectionFormat
```

#### 5.14.3.41 OptixDisplacementMicromapFlags

```
typedef enum OptixDisplacementMicromapFlags OptixDisplacementMicromapFlags
```

Flags defining behavior of DMMs in a DMM array.

#### 5.14.3.42 OptixDisplacementMicromapFormat

```
typedef enum OptixDisplacementMicromapFormat OptixDisplacementMicromapFormat
```

DMM input data format.

#### 5.14.3.43 OptixDisplacementMicromapHistogramEntry

```
typedef struct OptixDisplacementMicromapHistogramEntry
OptixDisplacementMicromapHistogramEntry
```

Displacement micromap histogram entry. Specifies how many displacement micromaps of a specific type are input to the displacement micromap array build. Note that while this is similar to [OptixDisplacementMicromapUsageCount](#), the histogram entry specifies how many displacement micromaps of a specific type are combined into a displacement micromap array.

#### 5.14.3.44 OptixDisplacementMicromapTriangleFlags

```
typedef enum OptixDisplacementMicromapTriangleFlags
OptixDisplacementMicromapTriangleFlags
```

#### 5.14.3.45 OptixDisplacementMicromapUsageCount

```
typedef struct OptixDisplacementMicromapUsageCount
OptixDisplacementMicromapUsageCount
```

Displacement micromap usage count for acceleration structure builds. Specifies how many displacement micromaps of a specific type are referenced by triangles when building the AS. Note that while this is similar to [OptixDisplacementMicromapHistogramEntry](#), the usage count specifies how many displacement micromaps of a specific type are referenced by triangles in the AS.

#### 5.14.3.46 OptixExceptionCodes

```
typedef enum OptixExceptionCodes OptixExceptionCodes
```

The following values are used to indicate which exception was thrown.

#### 5.14.3.47 OptixExceptionFlags

```
typedef enum OptixExceptionFlags OptixExceptionFlags
```

Exception flags.

See also [OptixPipelineCompileOptions::exceptionFlags](#), [OptixExceptionCodes](#)

#### 5.14.3.48 OptixGeometryFlags

```
typedef enum OptixGeometryFlags OptixGeometryFlags
```

Flags used by [OptixBuildInputTriangleArray::flags](#) and [OptixBuildInputCustomPrimitiveArray::flags](#).

#### 5.14.3.49 OptixHitKind

```
typedef enum OptixHitKind OptixHitKind
```

Legacy type: A subset of the hit kinds for built-in primitive intersections. It is preferred to use [optixGetPrimitiveType\(\)](#), together with [optixIsFrontFaceHit\(\)](#) or [optixIsBackFaceHit\(\)](#).

See also [optixGetHitKind\(\)](#)

#### 5.14.3.50 OptixImage2D

```
typedef struct OptixImage2D OptixImage2D
```

Image descriptor used by the denoiser.

See also [optixDenoiserInvoke\(\)](#), [optixDenoiserComputeIntensity\(\)](#)

### 5.14.3.51 OptixIndicesFormat

```
typedef enum OptixIndicesFormat OptixIndicesFormat
```

Format of indices used in `OptixBuildInputTriangleArray::indexFormat`.

### 5.14.3.52 OptixInstance

```
typedef struct OptixInstance OptixInstance
```

Instances.

See also `OptixBuildInputInstanceArray::instances`

### 5.14.3.53 OptixInstanceFlags

```
typedef enum OptixInstanceFlags OptixInstanceFlags
```

Flags set on the `OptixInstance::flags`.

These can be or'ed together to combine multiple flags.

### 5.14.3.54 OptixLogCallback

```
typedef void(* OptixLogCallback) (unsigned int level, const char *tag, const char *message, void *cbdata)
```

Type of the callback function used for log messages.

Parameters

|    |                |                                                                                     |
|----|----------------|-------------------------------------------------------------------------------------|
| in | <i>level</i>   | The log level indicates the severity of the message. See below for possible values. |
| in | <i>tag</i>     | A terse message category description (e.g., 'SCENE STAT').                          |
| in | <i>message</i> | Null terminated log message (without newline at the end).                           |
| in | <i>cbdata</i>  | Callback data that was provided with the callback pointer.                          |

It is the users responsibility to ensure thread safety within this function.

The following log levels are defined.

0 disable Setting the callback level will disable all messages. The callback function will not be called in this case. 1 fatal A non-recoverable error. The context and/or OptiX itself might no longer be in a usable state. 2 error A recoverable error, e.g., when passing invalid call parameters. 3 warning Hints that OptiX might not behave exactly as requested by the user or may perform slower than expected. 4 print Status or progress messages.

Higher levels might occur.

See also `optixDeviceContextSetLogCallback()`, `OptixDeviceContextOptions`

### 5.14.3.55 OptixMatrixMotionTransform

```
typedef struct OptixMatrixMotionTransform OptixMatrixMotionTransform
```

Represents a matrix motion transformation.

The device address of instances of this type must be a multiple of `OPTIX_TRANSFORM_BYTE_ALIGNMENT`.

This struct, as defined here, handles only N=2 motion keys due to the fixed array length of its transform member. The following example shows how to create instances for an arbitrary number N of

motion keys:

```
float matrixData[N][12];
... // setup matrixData
size_t transformSizeInBytes = sizeof(OptixMatrixMotionTransform) + (N-2) * 12 * sizeof(float);
OptixMatrixMotionTransform* matrixMoptionTransform = (OptixMatrixMotionTransform*)
malloc(transformSizeInBytes);
memset(matrixMoptionTransform, 0, transformSizeInBytes);
... // setup other members of matrixMoptionTransform
matrixMoptionTransform->motionOptions.numKeys
memcpy(matrixMoptionTransform->transform, matrixData, N * 12 * sizeof(float));
... // copy matrixMoptionTransform to device memory
free(matrixMoptionTransform)
```

See also [optixConvertPointerToTraversableHandle\(\)](#)

#### 5.14.3.56 OptixMicromapBuffers

```
typedef struct OptixMicromapBuffers OptixMicromapBuffers
```

Buffer inputs for opacity/displacement micromap array builds.

#### 5.14.3.57 OptixMicromapBufferSizes

```
typedef struct OptixMicromapBufferSizes OptixMicromapBufferSizes
```

Conservative memory requirements for building a opacity/displacement micromap array.

#### 5.14.3.58 OptixModule

```
typedef struct OptixModule_t* OptixModule
```

Opaque type representing a module.

#### 5.14.3.59 OptixModuleCompileBoundValueEntry

```
typedef struct OptixModuleCompileBoundValueEntry
OptixModuleCompileBoundValueEntry
```

Struct for specifying specializations for pipelineParams as specified in [OptixPipelineCompileOptions::pipelineLaunchParamsVariableName](#).

The bound values are supposed to represent a constant value in the pipelineParams. OptiX will attempt to locate all loads from the pipelineParams and correlate them to the appropriate bound value, but there are cases where OptiX cannot safely or reliably do this. For example if the pointer to the pipelineParams is passed as an argument to a non-inline function or the offset of the load to the pipelineParams cannot be statically determined (e.g. accessed in a loop). No module should rely on the value being specialized in order to work correctly. The values in the pipelineParams specified on optixLaunch should match the bound value. If validation mode is enabled on the context, OptiX will verify that the bound values specified matches the values in pipelineParams specified to optixLaunch.

These values are compiled in to the module as constants. Once the constants are inserted into the code, an optimization pass will be run that will attempt to propagate the constants and remove unreachable code.

If caching is enabled, changes in these values will result in newly compiled modules.

The pipelineParamOffset and sizeInBytes must be within the bounds of the pipelineParams variable. OPTIX\_ERROR\_INVALID\_VALUE will be returned from optixModuleCreate otherwise.

If more than one bound value overlaps or the size of a bound value is equal to 0, an OPTIX\_ERROR\_INVALID\_VALUE will be returned from optixModuleCreate.

The same set of bound values do not need to be used for all modules in a pipeline, but overlapping values between modules must have the same value. `OPTIX_ERROR_INVALID_VALUE` will be returned from `optixPipelineCreate` otherwise.

See also [OptixModuleCompileOptions](#)

#### 5.14.3.60 OptixModuleCompileOptions

```
typedef struct OptixModuleCompileOptions OptixModuleCompileOptions
```

Compilation options for module.

See also [optixModuleCreate\(\)](#)

#### 5.14.3.61 OptixModuleCompileState

```
typedef enum OptixModuleCompileState OptixModuleCompileState
```

Module compilation state.

See also [optixModuleGetCompilationState\(\)](#), [optixModuleCreateWithTasks\(\)](#)

#### 5.14.3.62 OptixMotionFlags

```
typedef enum OptixMotionFlags OptixMotionFlags
```

Enum to specify motion flags.

See also [OptixMotionOptions::flags](#).

#### 5.14.3.63 OptixMotionOptions

```
typedef struct OptixMotionOptions OptixMotionOptions
```

Motion options.

See also [OptixAccelBuildOptions::motionOptions](#), [OptixMatrixMotionTransform::motionOptions](#), [OptixSRTMotionTransform::motionOptions](#)

#### 5.14.3.64 OptixOpacityMicromapArrayBuildInput

```
typedef struct OptixOpacityMicromapArrayBuildInput  
OptixOpacityMicromapArrayBuildInput
```

Inputs to opacity micromap array construction.

#### 5.14.3.65 OptixOpacityMicromapArrayIndexingMode

```
typedef enum OptixOpacityMicromapArrayIndexingMode  
OptixOpacityMicromapArrayIndexingMode
```

indexing mode of triangles to opacity micromaps in an array, used in [OptixBuildInputOpacityMicromap](#).

#### 5.14.3.66 OptixOpacityMicromapDesc

```
typedef struct OptixOpacityMicromapDesc OptixOpacityMicromapDesc
```

Opacity micromap descriptor.



### 5.14.3.67 OptixOpacityMicromapFlags

```
typedef enum OptixOpacityMicromapFlags OptixOpacityMicromapFlags
```

Flags defining behavior of opacity micromaps in a opacity micromap array.

### 5.14.3.68 OptixOpacityMicromapFormat

```
typedef enum OptixOpacityMicromapFormat OptixOpacityMicromapFormat
```

Specifies whether to use a 2- or 4-state opacity micromap format.

### 5.14.3.69 OptixOpacityMicromapHistogramEntry

```
typedef struct OptixOpacityMicromapHistogramEntry
OptixOpacityMicromapHistogramEntry
```

Opacity micromap histogram entry. Specifies how many opacity micromaps of a specific type are input to the opacity micromap array build. Note that while this is similar to [OptixOpacityMicromapUsageCount](#), the histogram entry specifies how many opacity micromaps of a specific type are combined into a opacity micromap array.

### 5.14.3.70 OptixOpacityMicromapUsageCount

```
typedef struct OptixOpacityMicromapUsageCount OptixOpacityMicromapUsageCount
```

Opacity micromap usage count for acceleration structure builds. Specifies how many opacity micromaps of a specific type are referenced by triangles when building the AS. Note that while this is similar to [OptixOpacityMicromapHistogramEntry](#), the usage count specifies how many opacity micromaps of a specific type are referenced by triangles in the AS.

### 5.14.3.71 OptixPayloadSemantics

```
typedef enum OptixPayloadSemantics OptixPayloadSemantics
```

Semantic flags for a single payload word.

Used to specify the semantics of a payload word per shader type. "read": Shader of this type may read the payload word. "write": Shader of this type may write the payload word.

"trace\_caller\_write": Shaders may consume the value of the payload word passed to `optixTrace` by the caller. "trace\_caller\_read": The caller to `optixTrace` may read the payload word after the call to `optixTrace`.

Semantics can be bitwise combined. Combining "read" and "write" is equivalent to specifying "read\_write". A payload needs to be writable by the caller or at least one shader type. A payload needs to be readable by the caller or at least one shader type after a being writable.

### 5.14.3.72 OptixPayloadType

```
typedef struct OptixPayloadType OptixPayloadType
```

Specifies a single payload type.

### 5.14.3.73 OptixPayloadTypeID

```
typedef enum OptixPayloadTypeID OptixPayloadTypeID
```

Payload type identifiers.

#### 5.14.3.74 OptixPipeline

```
typedef struct OptixPipeline_t* OptixPipeline
```

Opaque type representing a pipeline.

#### 5.14.3.75 OptixPipelineCompileOptions

```
typedef struct OptixPipelineCompileOptions OptixPipelineCompileOptions
```

Compilation options for all modules of a pipeline.

Similar to [OptixModuleCompileOptions](#), but these options here need to be equal for all modules of a pipeline.

See also [optixModuleCreate\(\)](#), [optixPipelineCreate\(\)](#)

#### 5.14.3.76 OptixPipelineLinkOptions

```
typedef struct OptixPipelineLinkOptions OptixPipelineLinkOptions
```

Link options for a pipeline.

See also [optixPipelineCreate\(\)](#)

#### 5.14.3.77 OptixPixelFormat

```
typedef enum OptixPixelFormat OptixPixelFormat
```

Pixel formats used by the denoiser.

See also [OptixImage2D::format](#)

#### 5.14.3.78 OptixPrimitiveType

```
typedef enum OptixPrimitiveType OptixPrimitiveType
```

Builtin primitive types.

#### 5.14.3.79 OptixPrimitiveTypeFlags

```
typedef enum OptixPrimitiveTypeFlags OptixPrimitiveTypeFlags
```

Builtin flags may be bitwise combined.

See also [OptixPipelineCompileOptions::usesPrimitiveTypeFlags](#)

#### 5.14.3.80 OptixProgramGroup

```
typedef struct OptixProgramGroup_t* OptixProgramGroup
```

Opaque type representing a program group.

#### 5.14.3.81 OptixProgramGroupCallables

```
typedef struct OptixProgramGroupCallables OptixProgramGroupCallables
```

Program group representing callables.

Module and entry function name need to be valid for at least one of the two callables.

See also [#OptixProgramGroupDesc::callables](#)

#### 5.14.3.82 OptixProgramGroupDesc

```
typedef struct OptixProgramGroupDesc OptixProgramGroupDesc
```

Descriptor for program groups.

#### 5.14.3.83 OptixProgramGroupFlags

```
typedef enum OptixProgramGroupFlags OptixProgramGroupFlags
```

Flags for program groups.

#### 5.14.3.84 OptixProgramGroupHitgroup

```
typedef struct OptixProgramGroupHitgroup OptixProgramGroupHitgroup
```

Program group representing the hitgroup.

For each of the three program types, module and entry function name might both be `nullptr`.

See also `OptixProgramGroupDesc::hitgroup`

#### 5.14.3.85 OptixProgramGroupKind

```
typedef enum OptixProgramGroupKind OptixProgramGroupKind
```

Distinguishes different kinds of program groups.

#### 5.14.3.86 OptixProgramGroupOptions

```
typedef struct OptixProgramGroupOptions OptixProgramGroupOptions
```

Program group options.

See also `optixProgramGroupCreate()`

#### 5.14.3.87 OptixProgramGroupSingleModule

```
typedef struct OptixProgramGroupSingleModule OptixProgramGroupSingleModule
```

Program group representing a single module.

Used for raygen, miss, and exception programs. In case of raygen and exception programs, module and entry function name need to be valid. For miss programs, module and entry function name might both be `nullptr`.

See also `OptixProgramGroupDesc::raygen`, `OptixProgramGroupDesc::miss`, `OptixProgramGroupDesc::exception`

#### 5.14.3.88 OptixQueryFunctionTable\_t

```
typedef OptixResult() OptixQueryFunctionTable_t(int abiId, unsigned int numOptions, OptixQueryFunctionTableOptions *, const void **, void *functionTable, size_t sizeOfTable)
```

Type of the function `optixQueryFunctionTable()`

#### 5.14.3.89 OptixQueryFunctionTableOptions

```
typedef enum OptixQueryFunctionTableOptions OptixQueryFunctionTableOptions
```

Options that can be passed to `optixQueryFunctionTable()`

#### 5.14.3.90 OptixRayFlags

```
typedef enum OptixRayFlags OptixRayFlags
```

Ray flags passed to the device function `optixTrace()`. These affect the behavior of traversal per invocation.

See also `optixTrace()`

#### 5.14.3.91 OptixRelocateInput

```
typedef struct OptixRelocateInput OptixRelocateInput
```

Relocation inputs.

See also `optixAccelRelocate()`

#### 5.14.3.92 OptixRelocateInputInstanceArray

```
typedef struct OptixRelocateInputInstanceArray
OptixRelocateInputInstanceArray
```

Instance and instance pointer inputs.

See also `OptixRelocateInput::instanceArray`

#### 5.14.3.93 OptixRelocateInputOpacityMicromap

```
typedef struct OptixRelocateInputOpacityMicromap
OptixRelocateInputOpacityMicromap
```

#### 5.14.3.94 OptixRelocateInputTriangleArray

```
typedef struct OptixRelocateInputTriangleArray
OptixRelocateInputTriangleArray
```

Triangle inputs.

See also `OptixRelocateInput::triangleArray`

#### 5.14.3.95 OptixRelocationInfo

```
typedef struct OptixRelocationInfo OptixRelocationInfo
```

Used to store information related to relocation of optix data structures.

See also `optixOpacityMicromapArrayGetRelocationInfo()`, `optixOpacityMicromapArrayRelocate()`, `optixAccelGetRelocationInfo()`, `optixAccelRelocate()`, `optixCheckRelocationCompatibility()`

#### 5.14.3.96 OptixResult

```
typedef enum OptixResult OptixResult
```

Result codes returned from API functions.

All host side API functions return `OptixResult` with the exception of `optixGetErrorName` and `optixGetErrorString`. When successful `OPTIX_SUCCESS` is returned. All return codes except for `OPTIX_SUCCESS` should be assumed to be errors as opposed to a warning.

See also `optixGetErrorName()`, `optixGetErrorString()`

### 5.14.3.97 OptixShaderBindingTable

```
typedef struct OptixShaderBindingTable OptixShaderBindingTable
```

Describes the shader binding table (SBT)

See also [optixLaunch\(\)](#)

### 5.14.3.98 OptixSRTData

```
typedef struct OptixSRTData OptixSRTData
```

Represents an SRT transformation.

An SRT transformation can represent a smooth rotation with fewer motion keys than a matrix transformation. Each motion key is constructed from elements taken from a matrix S, a quaternion R, and a translation T.

The scaling matrix  $S = \begin{bmatrix} sx & a & b & pvx \\ 0 & sy & c & pvy \\ 0 & 0 & sz & pvz \end{bmatrix}$  defines an affine transformation that can include scale,

shear, and a translation. The translation allows to define the pivot point for the subsequent rotation.

The quaternion  $R = [qx, qy, qz, qw]$  describes a rotation with angular component  $qw = \cos(\theta/2)$  and other components  $[qx, qy, qz] = \sin(\theta/2) * [ax, ay, az]$  where the axis  $[ax, ay, az]$  is normalized.

The translation matrix  $T = \begin{bmatrix} 1 & 0 & 0 & tx \\ 0 & 1 & 0 & ty \\ 0 & 0 & 1 & tz \end{bmatrix}$  defines another translation that is applied after the rotation.

Typically, this translation includes the inverse translation from the matrix S to reverse the translation for the pivot point for R.

To obtain the effective transformation at time t, the elements of the components of S, R, and T will be interpolated linearly. The components are then multiplied to obtain the combined transformation  $C = T * R * S$ . The transformation C is the effective object-to-world transformations at time t, and  $C^{-1}$  is the effective world-to-object transformation at time t.

See also [OptixSRTMotionTransform::srtData](#), [optixConvertPointerToTraversableHandle\(\)](#)

### 5.14.3.99 OptixSRTMotionTransform

```
typedef struct OptixSRTMotionTransform OptixSRTMotionTransform
```

Represents an SRT motion transformation.

The device address of instances of this type must be a multiple of OPTIX\_TRANSFORM\_BYTE\_ALIGNMENT.

This struct, as defined here, handles only N=2 motion keys due to the fixed array length of its srtData member. The following example shows how to create instances for an arbitrary number N of motion keys:

```
OptixSRTData srtData[N];
... // setup srtData
size_t transformSizeInBytes = sizeof(OptixSRTMotionTransform) + (N-2) * sizeof(OptixSRTData);
OptixSRTMotionTransform* srtMotionTransform = (OptixSRTMotionTransform*) malloc(transformSizeInBytes);
memset(srtMotionTransform, 0, transformSizeInBytes);
... // setup other members of srtMotionTransform
srtMotionTransform->motionOptions.numKeys = N;
memcpy(srtMotionTransform->srtData, srtData, N * sizeof(OptixSRTData));
... // copy srtMotionTransform to device memory
free(srtMotionTransform)
```

See also [optixConvertPointerToTraversableHandle\(\)](#)

#### 5.14.3.100 OptixStackSizes

```
typedef struct OptixStackSizes OptixStackSizes
```

Describes the stack size requirements of a program group.

See also [optixProgramGroupGetStackSize\(\)](#)

#### 5.14.3.101 OptixStaticTransform

```
typedef struct OptixStaticTransform OptixStaticTransform
```

Static transform.

The device address of instances of this type must be a multiple of `OPTIX_TRANSFORM_BYTE_ALIGNMENT`.

See also [optixConvertPointerToTraversableHandle\(\)](#)

#### 5.14.3.102 OptixTask

```
typedef struct OptixTask_t* OptixTask
```

Opaque type representing a work task.

#### 5.14.3.103 OptixTransformFormat

```
typedef enum OptixTransformFormat OptixTransformFormat
```

Format of transform used in `OptixBuildInputTriangleArray::transformFormat`.

#### 5.14.3.104 OptixTransformType

```
typedef enum OptixTransformType OptixTransformType
```

Transform.

`OptixTransformType` is used by the device function `optixGetTransformTypeFromHandle()` to determine the type of the `OptixTraversableHandle` returned from `optixGetTransformListHandle()`.

#### 5.14.3.105 OptixTraversableGraphFlags

```
typedef enum OptixTraversableGraphFlags OptixTraversableGraphFlags
```

Specifies the set of valid traversable graphs that may be passed to invocation of `optixTrace()`. Flags may be bitwise combined.

#### 5.14.3.106 OptixTraversableHandle

```
typedef unsigned long long OptixTraversableHandle
```

Traversable handle.

#### 5.14.3.107 OptixTraversableType

```
typedef enum OptixTraversableType OptixTraversableType
```

Traversable Handles.

See also [optixConvertPointerToTraversableHandle\(\)](#)

### 5.14.3.108 OptixVertexFormat

typedef enum [OptixVertexFormat](#) [OptixVertexFormat](#)

Format of vertices used in [OptixBuildInputTriangleArray::vertexFormat](#).

### 5.14.3.109 OptixVisibilityMask

typedef unsigned int [OptixVisibilityMask](#)

Visibility mask.

## 5.14.4 Enumeration Type Documentation

### 5.14.4.1 OptixAccelPropertyType

enum [OptixAccelPropertyType](#)

Properties which can be emitted during acceleration structure build.

See also [OptixAccelEmitDesc::type](#).

Enumerator

|                                    |                                                                                    |
|------------------------------------|------------------------------------------------------------------------------------|
| OPTIX_PROPERTY_TYPE_COMPACTED_SIZE | Size of a compacted acceleration structure. The device pointer points to a uint64. |
| OPTIX_PROPERTY_TYPE_AABBS          | <a href="#">OptixAabb</a> * numMotionSteps.                                        |

### 5.14.4.2 OptixBuildFlags

enum [OptixBuildFlags](#)

Builder Options.

Used for [OptixAccelBuildOptions::buildFlags](#). Can be or'ed together.

Enumerator

|                                             |                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|---------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_BUILD_FLAG_NONE                       | No special flags set.                                                                                                                                                                                                                                                                                                                                                                                                           |
| OPTIX_BUILD_FLAG_ALLOW_UPDATE               | Allow updating the build with new vertex positions with subsequent calls to <a href="#">optixAccelBuild</a> .                                                                                                                                                                                                                                                                                                                   |
| OPTIX_BUILD_FLAG_ALLOW_COMPACTION           |                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| OPTIX_BUILD_FLAG_PREFER_FAST_TRACE          | This flag is mutually exclusive with OPTIX_BUILD_FLAG_PREFER_FAST_BUILD.                                                                                                                                                                                                                                                                                                                                                        |
| OPTIX_BUILD_FLAG_PREFER_FAST_BUILD          | This flag is mutually exclusive with OPTIX_BUILD_FLAG_PREFER_FAST_TRACE.                                                                                                                                                                                                                                                                                                                                                        |
| OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS | Allow random access to build input vertices See<br><a href="#">optixGetTriangleVertexData</a><br><a href="#">optixGetLinearCurveVertexData</a><br><a href="#">optixGetQuadraticBSplineVertexData</a><br><a href="#">optixGetCubicBSplineVertexData</a><br><a href="#">optixGetCatmullRomVertexData</a><br><a href="#">optixGetRibbonVertexData</a><br><a href="#">optixGetRibbonNormal</a> <a href="#">optixGetSphereData</a> . |

## Enumerator

|                                                  |                                                                                                                                                                                                                                                                                                                    |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS    | Allow random access to instances See <a href="#">optixGetInstanceTraversableFromIAS</a> .                                                                                                                                                                                                                          |
| OPTIX_BUILD_FLAG_ALLOW_OPACITY_MICROMAP_UPDATE   | Support updating the opacity micromap array and opacity micromap indices on refits. May increase AS size and may have a small negative impact on traversal performance. If this flag is absent, all opacity micromap inputs must remain unchanged between the initial AS builds and their subsequent refits.       |
| OPTIX_BUILD_FLAG_ALLOW_DISABLE_OPACITY_MICROMAPS | If enabled, any instances referencing this GAS are allowed to disable the opacity micromap test through the DISABLE_OPACITY_MICROMAPS flag instance flag. Note that the GAS will not be optimized for the attached opacity micromap Arrays if this flag is set, which may result in reduced traversal performance. |

## 5.14.4.3 OptixBuildInputType

enum [OptixBuildInputType](#)

Enum to distinguish the different build input types.

See also [OptixBuildInput::type](#)

## Enumerator

|                                          |                                                                                       |
|------------------------------------------|---------------------------------------------------------------------------------------|
| OPTIX_BUILD_INPUT_TYPE_TRIANGLES         | Triangle inputs. See also <a href="#">OptixBuildInputTriangleArray</a>                |
| OPTIX_BUILD_INPUT_TYPE_CUSTOM_PRIMITIVES | Custom primitive inputs. See also <a href="#">OptixBuildInputCustomPrimitiveArray</a> |
| OPTIX_BUILD_INPUT_TYPE_INSTANCES         | Instance inputs. See also <a href="#">OptixBuildInputInstanceArray</a>                |
| OPTIX_BUILD_INPUT_TYPE_INSTANCE_POINTERS | Instance pointer inputs. See also <a href="#">OptixBuildInputInstanceArray</a>        |
| OPTIX_BUILD_INPUT_TYPE_CURVES            | Curve inputs. See also <a href="#">OptixBuildInputCurveArray</a>                      |
| OPTIX_BUILD_INPUT_TYPE_SPHERES           | Sphere inputs. See also <a href="#">OptixBuildInputSphereArray</a>                    |

## 5.14.4.4 OptixBuildOperation

enum [OptixBuildOperation](#)

Enum to specify the acceleration build operation.

Used in [OptixAccelBuildOptions](#), which is then passed to [optixAccelBuild](#) and [optixAccelComputeMemoryUsage](#), this enum indicates whether to do a build or an update of the acceleration structure.



Acceleration structure updates utilize the same acceleration structure, but with updated bounds. Updates are typically much faster than builds, however, large perturbations can degrade the quality of the acceleration structure.

See also [optixAccelComputeMemoryUsage\(\)](#), [optixAccelBuild\(\)](#), [OptixAccelBuildOptions](#)

Enumerator

|                              |                                     |
|------------------------------|-------------------------------------|
| OPTIX_BUILD_OPERATION_BUILD  | Perform a full build operation.     |
| OPTIX_BUILD_OPERATION_UPDATE | Perform an update using new bounds. |

#### 5.14.4.5 OptixCompileDebugLevel

enum [OptixCompileDebugLevel](#)

Debug levels.

See also [OptixModuleCompileOptions::debugLevel](#)

Enumerator

|                                    |                                                                                                               |
|------------------------------------|---------------------------------------------------------------------------------------------------------------|
| OPTIX_COMPILE_DEBUG_LEVEL_DEFAULT  | Default currently is minimal.                                                                                 |
| OPTIX_COMPILE_DEBUG_LEVEL_NONE     | No debug information.                                                                                         |
| OPTIX_COMPILE_DEBUG_LEVEL_MINIMAL  | Generate information that does not impact performance. Note this replaces OPTIX_COMPILE_DEBUG_LEVEL_LINEINFO. |
| OPTIX_COMPILE_DEBUG_LEVEL_MODERATE | Generate some debug information with slight performance cost.                                                 |
| OPTIX_COMPILE_DEBUG_LEVEL_FULL     | Generate full debug information.                                                                              |

#### 5.14.4.6 OptixCompileOptimizationLevel

enum [OptixCompileOptimizationLevel](#)

Optimization levels.

See also [OptixModuleCompileOptions::optLevel](#)

Enumerator

|                                    |                                      |
|------------------------------------|--------------------------------------|
| OPTIX_COMPILE_OPTIMIZATION_DEFAULT | Default is to run all optimizations. |
| OPTIX_COMPILE_OPTIMIZATION_LEVEL_0 | No optimizations.                    |
| OPTIX_COMPILE_OPTIMIZATION_LEVEL_1 | Some optimizations.                  |
| OPTIX_COMPILE_OPTIMIZATION_LEVEL_2 | Most optimizations.                  |
| OPTIX_COMPILE_OPTIMIZATION_LEVEL_3 | All optimizations.                   |

#### 5.14.4.7 OptixCurveEndcapFlags

enum [OptixCurveEndcapFlags](#)

Curve end cap types, for non-linear curves.

Enumerator

|                            |                                                                                     |
|----------------------------|-------------------------------------------------------------------------------------|
| OPTIX_CURVE_ENDCAP_DEFAULT | Default end caps. Round end caps for linear, no end caps for quadratic/cubic.       |
| OPTIX_CURVE_ENDCAP_ON      | Flat end caps at both ends of quadratic/cubic curve segments. Not valid for linear. |

#### 5.14.4.8 OptixDenoiserAlphaMode

enum [OptixDenoiserAlphaMode](#)

Alpha denoising mode.

See also [optixDenoiserCreate\(\)](#)

Enumerator

|                                   |                                                         |
|-----------------------------------|---------------------------------------------------------|
| OPTIX_DENOISER_ALPHA_MODE_COPY    | Copy alpha (if present) from input layer, no denoising. |
| OPTIX_DENOISER_ALPHA_MODE_DENOISE | Denoise alpha.                                          |

#### 5.14.4.9 OptixDenoiserAOVType

enum [OptixDenoiserAOVType](#)

AOV type used by the denoiser.

Enumerator

|                                    |                       |
|------------------------------------|-----------------------|
| OPTIX_DENOISER_AOV_TYPE_NONE       | Unspecified AOV type. |
| OPTIX_DENOISER_AOV_TYPE_BEAUTY     |                       |
| OPTIX_DENOISER_AOV_TYPE_SPECULAR   |                       |
| OPTIX_DENOISER_AOV_TYPE_REFLECTION |                       |
| OPTIX_DENOISER_AOV_TYPE_REFRACTION |                       |
| OPTIX_DENOISER_AOV_TYPE_DIFFUSE    |                       |

#### 5.14.4.10 OptixDenoiserModelKind

enum [OptixDenoiserModelKind](#)

Model kind used by the denoiser.

See also [optixDenoiserCreate](#)

Enumerator

|                               |                                                                  |
|-------------------------------|------------------------------------------------------------------|
| OPTIX_DENOISER_MODEL_KIND_LDR | Use the built-in model appropriate for low dynamic range input.  |
| OPTIX_DENOISER_MODEL_KIND_HDR | Use the built-in model appropriate for high dynamic range input. |

## Enumerator

|                                              |                                                                                                                        |
|----------------------------------------------|------------------------------------------------------------------------------------------------------------------------|
| OPTIX_DENOISER_MODEL_KIND_AOV                | Use the built-in model appropriate for high dynamic range input and support for AOVs.                                  |
| OPTIX_DENOISER_MODEL_KIND_TEMPORAL           | Use the built-in model appropriate for high dynamic range input, temporally stable.                                    |
| OPTIX_DENOISER_MODEL_KIND_TEMPORAL_AOV       | Use the built-in model appropriate for high dynamic range input and support for AOVs, temporally stable.               |
| OPTIX_DENOISER_MODEL_KIND_UPSCALE2X          | Use the built-in model appropriate for high dynamic range input and support for AOVs, upscaling 2x.                    |
| OPTIX_DENOISER_MODEL_KIND_TEMPORAL_UPSCALE2X | Use the built-in model appropriate for high dynamic range input and support for AOVs, upscaling 2x, temporally stable. |

## 5.14.4.11 OptixDeviceContextValidationMode

enum [OptixDeviceContextValidationMode](#)

Validation mode settings.

When enabled, certain device code utilities will be enabled to provide as good debug and error checking facilities as possible.

See also [optixDeviceContextCreate\(\)](#)

## Enumerator

|                                          |
|------------------------------------------|
| OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_OFF |
| OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_ALL |

## 5.14.4.12 OptixDeviceProperty

enum [OptixDeviceProperty](#)

Parameters used for [optixDeviceContextGetProperty\(\)](#)

See also [optixDeviceContextGetProperty\(\)](#)

## Enumerator

|                                                         |                                                                                                                                                    |
|---------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRACE_DEPTH             | Maximum value for <a href="#">OptixPipelineLinkOptions::maxTraceDepth</a> . sizeof(unsigned int)                                                   |
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRAVERSABLE_GRAPH_DEPTH | Maximum value to pass into <a href="#">optixPipelineSetStackSize</a> for parameter <a href="#">maxTraversableGraphDepth</a> . sizeof(unsigned int) |
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_PRIMITIVES_PER_GAS      | The maximum number of primitives (over all build inputs) as input to a single Geometry Acceleration Structure (GAS). sizeof(unsigned int)          |

## Enumerator

|                                                               |                                                                                                                                                                                                                                                |
|---------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCES_PER_IAS             | The maximum number of instances (over all build inputs) as input to a single Instance Acceleration Structure (IAS). sizeof(unsigned int)                                                                                                       |
| OPTIX_DEVICE_PROPERTY_RTCORE_VERSION                          | The RT core version supported by the device (0 for no support, 10 for version 1.0). sizeof(unsigned int)                                                                                                                                       |
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCE_ID                   | The maximum value for <a href="#">OptixInstance::instanceId</a> . sizeof(unsigned int)                                                                                                                                                         |
| OPTIX_DEVICE_PROPERTY_LIMIT_NUM_BITS_INSTANCE_VISIBILITY_MASK | The number of bits available for the <a href="#">OptixInstance::visibilityMask</a> . Higher bits must be set to zero. sizeof(unsigned int)                                                                                                     |
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_RECORDS_PER_GAS           | The maximum number of instances that can be added to a single Instance Acceleration Structure (IAS). sizeof(unsigned int)                                                                                                                      |
| OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_OFFSET                    | The maximum summed value of <a href="#">OptixInstance::sbtOffset</a> . Also the maximum summed value of sbt offsets of all ancestor instances of a GAS in a traversable graph. sizeof(unsigned int)                                            |
| OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING             | Returns a flag specifying capabilities of the <a href="#">optixReorder()</a> device function. See <a href="#">OptixDevicePropertyShaderExecutionReorderingFlags</a> for documentation on the values that can be returned. sizeof(unsigned int) |

## 5.14.4.13 OptixDevicePropertyShaderExecutionReorderingFlags

enum [OptixDevicePropertyShaderExecutionReorderingFlags](#)

Flags used to interpret the result of [optixDeviceContextGetProperty\(\)](#) and OPTIX\_DEVICE\_PROPERTY\_SHADER\_EXECUTION\_REORDERING.

See also [optixDeviceContextGetProperty\(\)](#)

## Enumerator

|                                                                 |                                                                                                                                                                               |
|-----------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_NONE     | <a href="#">optixReorder()</a> acts as a no-op, and no thread reordering is performed. Note that it is still legal to call this device function; no errors will be generated. |
| OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_STANDARD |                                                                                                                                                                               |

## 5.14.4.14 OptixDisplacementMicromapArrayIndexingMode

enum [OptixDisplacementMicromapArrayIndexingMode](#)

indexing mode of triangles to displacement micromaps in an array, used in [OptixBuildInputDisplacementMicromap](#).

## Enumerator

|                                                         |                                                                                                                                                                                                                                                                                                                                |
|---------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_NONE    | No displacement micromap is used.                                                                                                                                                                                                                                                                                              |
| OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_LINEAR  | An implicit linear mapping of triangles to displacement micromaps in the displacement micromap array is used. triangle[i] will use displacementMicromapArray[i].                                                                                                                                                               |
| OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_INDEXED | <a href="#">OptixBuildInputDisplacementMicromap::displacementMicromapIndexBuffer</a> provides a per triangle array of indices into <a href="#">OptixBuildInputDisplacementMicromap::displacementMicromapArray</a> . See <a href="#">OptixBuildInputDisplacementMicromap::displacementMicromapIndexBuffer</a> for more details. |

## 5.14.4.15 OptixDisplacementMicromapBiasAndScaleFormat

enum [OptixDisplacementMicromapBiasAndScaleFormat](#)

## Enumerator

|                                                          |
|----------------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_NONE   |
| OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_FLOAT2 |
| OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_HALF2  |

## 5.14.4.16 OptixDisplacementMicromapDirectionFormat

enum [OptixDisplacementMicromapDirectionFormat](#)

## Enumerator

|                                                     |
|-----------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_NONE   |
| OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_FLOAT3 |
| OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_HALF3  |

## 5.14.4.17 OptixDisplacementMicromapFlags

enum [OptixDisplacementMicromapFlags](#)

Flags defining behavior of DMMs in a DMM array.

## Enumerator

|                                                    |                                                                                          |
|----------------------------------------------------|------------------------------------------------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_FLAG_NONE              |                                                                                          |
| OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_TRACE | This flag is mutually exclusive with OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_BUILD. |

Enumerator

|                                                    |                                                                                          |
|----------------------------------------------------|------------------------------------------------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_BUILD | This flag is mutually exclusive with OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_TRACE. |
|----------------------------------------------------|------------------------------------------------------------------------------------------|

#### 5.14.4.18 OptixDisplacementMicromapFormat

enum `OptixDisplacementMicromapFormat`

DMM input data format.

Enumerator

|                                                              |
|--------------------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_FORMAT_NONE                      |
| OPTIX_DISPLACEMENT_MICROMAP_FORMAT_64_MICRO_TRIS_64_BYTES    |
| OPTIX_DISPLACEMENT_MICROMAP_FORMAT_256_MICRO_TRIS_128_BYTES  |
| OPTIX_DISPLACEMENT_MICROMAP_FORMAT_1024_MICRO_TRIS_128_BYTES |

#### 5.14.4.19 OptixDisplacementMicromapTriangleFlags

enum `OptixDisplacementMicromapTriangleFlags`

Enumerator

|                                                            |                                                                                                                                                                                                               |
|------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_NONE             |                                                                                                                                                                                                               |
| OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_01 | The triangle edge v0..v1 is decimated: after subdivision the number of micro triangles on that edge is halved such that a neighboring triangle can have a lower subdivision level without introducing cracks. |
| OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_12 | The triangle edge v1..v2 is decimated.                                                                                                                                                                        |
| OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_20 | The triangle edge v2..v0 is decimated.                                                                                                                                                                        |

#### 5.14.4.20 OptixExceptionCodes

enum `OptixExceptionCodes`

The following values are used to indicate which exception was thrown.

Enumerator

|                                           |                                                                 |
|-------------------------------------------|-----------------------------------------------------------------|
| OPTIX_EXCEPTION_CODE_STACK_OVERFLOW       | Stack overflow of the continuation stack. no exception details. |
| OPTIX_EXCEPTION_CODE_TRACE_DEPTH_EXCEEDED | The trace depth is exceeded. no exception details.              |

#### 5.14.4.21 OptixExceptionFlags

enum [OptixExceptionFlags](#)

Exception flags.

See also [OptixPipelineCompileOptions::exceptionFlags](#), [OptixExceptionCodes](#)

Enumerator

|                                     |                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_EXCEPTION_FLAG_NONE           | No exception are enabled.                                                                                                                                                                                                                                                                                                                                                            |
| OPTIX_EXCEPTION_FLAG_STACK_OVERFLOW | Enables exceptions check related to the continuation stack. This flag should be used when the application handles stack overflows in a user exception program as part of the normal flow of execution. For catching overflows during debugging and development, the device context validation mode should be used instead. See also <a href="#">OptixDeviceContextValidationMode</a> |
| OPTIX_EXCEPTION_FLAG_TRACE_DEPTH    | Enables exceptions check related to trace depth. This flag should be used when the application handles trace depth overflows in a user exception program as part of the normal flow of execution. For catching overflows during debugging and development, the device context validation mode should be used instead. See also <a href="#">OptixDeviceContextValidationMode</a>      |
| OPTIX_EXCEPTION_FLAG_USER           | Enables user exceptions via <a href="#">optixThrowException()</a> . This flag must be specified for all modules in a pipeline if any module calls <a href="#">optixThrowException()</a> .                                                                                                                                                                                            |

#### 5.14.4.22 OptixGeometryFlags

enum [OptixGeometryFlags](#)

Flags used by [OptixBuildInputTriangleArray::flags](#) and [OptixBuildInputCustomPrimitiveArray::flags](#).

Enumerator

|                                                |                                                                                                                                                                         |
|------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_GEOMETRY_FLAG_NONE                       | No flags set.                                                                                                                                                           |
| OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT             | Disables the invocation of the anyhit program. Can be overridden by OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT and OPTIX_RAY_FLAG_ENFORCE_ANYHIT.                               |
| OPTIX_GEOMETRY_FLAG_REQUIRE_SINGLE_ANYHIT_CALL | If set, an intersection with the primitive will trigger one and only one invocation of the anyhit program. Otherwise, the anyhit program may be invoked more than once. |

## Enumerator

|                                                   |                                                                                                                                                                                         |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_GEOMETRY_FLAG_DISABLE_TRIANGLE_FACE_CULLING | Prevent triangles from getting culled due to their orientation. Effectively ignores ray flags OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES and OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES. |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

## 5.14.4.23 OptixHitKind

enum [OptixHitKind](#)

Legacy type: A subset of the hit kinds for built-in primitive intersections. It is preferred to use [optixGetPrimitiveType\(\)](#), together with [optixIsFrontFaceHit\(\)](#) or [optixIsBackFaceHit\(\)](#).

See also [optixGetHitKind\(\)](#)

## Enumerator

|                                    |                                         |
|------------------------------------|-----------------------------------------|
| OPTIX_HIT_KIND_TRIANGLE_FRONT_FACE | Ray hit the triangle on the front face. |
| OPTIX_HIT_KIND_TRIANGLE_BACK_FACE  | Ray hit the triangle on the back face.  |

## 5.14.4.24 OptixIndicesFormat

enum [OptixIndicesFormat](#)

Format of indices used in [OptixBuildInputTriangleArray::indexFormat](#).

## Enumerator

|                                      |                                                                                                                                    |
|--------------------------------------|------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_INDICES_FORMAT_NONE            | No indices, this format must only be used in combination with triangle soups, i.e., <a href="#">numIndexTriplets</a> must be zero. |
| OPTIX_INDICES_FORMAT_UNSIGNED_SHORT3 | Three shorts.                                                                                                                      |
| OPTIX_INDICES_FORMAT_UNSIGNED_INT3   | Three ints.                                                                                                                        |

## 5.14.4.25 OptixInstanceFlags

enum [OptixInstanceFlags](#)

Flags set on the [OptixInstance::flags](#).

These can be or'ed together to combine multiple flags.

## Enumerator

|                                                   |                                                                                                                                                                                         |
|---------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_INSTANCE_FLAG_NONE                          | No special flag set.                                                                                                                                                                    |
| OPTIX_INSTANCE_FLAG_DISABLE_TRIANGLE_FACE_CULLING | Prevent triangles from getting culled due to their orientation. Effectively ignores ray flags OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES and OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES. |



## Enumerator

|                                                    |                                                                                                                                                                                                                                        |
|----------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING           | Flip triangle orientation. This affects front/backface culling as well as the reported face in case of a hit.                                                                                                                          |
| OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT                 | Disable anyhit programs for all geometries of the instance. Can be overridden by OPTIX_RAY_FLAG_ENFORCE_ANYHIT. This flag is mutually exclusive with OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT.                                               |
| OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT                 | Enables anyhit programs for all geometries of the instance. Overrides OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT. Can be overridden by OPTIX_RAY_FLAG_DISABLE_ANYHIT. This flag is mutually exclusive with OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT. |
| OPTIX_INSTANCE_FLAG_FORCE_OPACITY_MICROMAP_2_STATE | Force 4-state opacity micromaps to behave as 2-state opacity micromaps during traversal.                                                                                                                                               |
| OPTIX_INSTANCE_FLAG_DISABLE_OPACITY_MICROMAPS      | Don't perform opacity micromap query for this instance. GAS must be built with ALLOW_DISABLE_OPACITY_MICROMAPS for this to be valid. This flag overrides FORCE_OPACITY_MICROMAP_2_STATE instance and ray flags.                        |

## 5.14.4.26 OptixModuleCompileState

enum [OptixModuleCompileState](#)

Module compilation state.

See also [optixModuleGetCompilationState\(\)](#), [optixModuleCreateWithTasks\(\)](#)

## Enumerator

|                                            |                                                                              |
|--------------------------------------------|------------------------------------------------------------------------------|
| OPTIX_MODULE_COMPILE_STATE_NOT_STARTED     | No OptixTask objects have started.                                           |
| OPTIX_MODULE_COMPILE_STATE_STARTED         | Started, but not all OptixTask objects have completed. No detected failures. |
| OPTIX_MODULE_COMPILE_STATE_PENDING_FAILURE | Not all OptixTask objects have completed, but at least one has failed.       |
| OPTIX_MODULE_COMPILE_STATE_FAILED          | All OptixTask objects have completed, and at least one has failed.           |
| OPTIX_MODULE_COMPILE_STATE_COMPLETED       | All OptixTask objects have completed. The OptixModule is ready to be used.   |

## 5.14.4.27 OptixMotionFlags

enum [OptixMotionFlags](#)

Enum to specify motion flags.

See also [OptixMotionOptions::flags](#).

Enumerator

|                                |
|--------------------------------|
| OPTIX_MOTION_FLAG_NONE         |
| OPTIX_MOTION_FLAG_START_VANISH |
| OPTIX_MOTION_FLAG_END_VANISH   |

#### 5.14.4.28 OptixOpacityMicromapArrayIndexingMode

enum [OptixOpacityMicromapArrayIndexingMode](#)

indexing mode of triangles to opacity micromaps in an array, used in [OptixBuildInputOpacityMicromap](#).

Enumerator

|                                                    |                                                                                                                                                                                                                                                                                              |
|----------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_NONE    | No opacity micromap is used.                                                                                                                                                                                                                                                                 |
| OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_LINEAR  | An implicit linear mapping of triangles to opacity micromaps in the opacity micromap array is used. <code>triangle[i]</code> will use <code>opacityMicromapArray[i]</code> .                                                                                                                 |
| OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_INDEXED | <a href="#">OptixBuildInputOpacityMicromap::indexBuffer</a> provides a per triangle array of predefined indices and/or indices into <a href="#">OptixBuildInputOpacityMicromap::opacityMicromapArray</a> . See <a href="#">OptixBuildInputOpacityMicromap::indexBuffer</a> for more details. |

#### 5.14.4.29 OptixOpacityMicromapFlags

enum [OptixOpacityMicromapFlags](#)

Flags defining behavior of opacity micromaps in a opacity micromap array.

Enumerator

|                                               |                                                                                                   |
|-----------------------------------------------|---------------------------------------------------------------------------------------------------|
| OPTIX_OPACITY_MICROMAP_FLAG_NONE              |                                                                                                   |
| OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_TRACE | This flag is mutually exclusive with <code>OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_BUILD</code> . |
| OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_BUILD | This flag is mutually exclusive with <code>OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_TRACE</code> . |

#### 5.14.4.30 OptixOpacityMicromapFormat

enum [OptixOpacityMicromapFormat](#)

Specifies whether to use a 2- or 4-state opacity micromap format.

## Enumerator

|                                       |                                                                      |
|---------------------------------------|----------------------------------------------------------------------|
| OPTIX_OPACITY_MICROMAP_FORMAT_NONE    | invalid format                                                       |
| OPTIX_OPACITY_MICROMAP_FORMAT_2_STATE | 0: Transparent, 1: Opaque                                            |
| OPTIX_OPACITY_MICROMAP_FORMAT_4_STATE | 0: Transparent, 1: Opaque, 2: Unknown-Transparent, 3: Unknown-Opaque |

## 5.14.4.31 OptixPayloadSemantics

enum `OptixPayloadSemantics`

Semantic flags for a single payload word.

Used to specify the semantics of a payload word per shader type. "read": Shader of this type may read the payload word. "write": Shader of this type may write the payload word.

"trace\_caller\_write": Shaders may consume the value of the payload word passed to `optixTrace` by the caller. "trace\_caller\_read": The caller to `optixTrace` may read the payload word after the call to `optixTrace`.

Semantics can be bitwise combined. Combining "read" and "write" is equivalent to specifying "read\_write". A payload needs to be writable by the caller or at least one shader type. A payload needs to be readable by the caller or at least one shader type after a being writable.

## Enumerator

|                                                 |
|-------------------------------------------------|
| OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_NONE       |
| OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ       |
| OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_WRITE      |
| OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ_WRITE |
| OPTIX_PAYLOAD_SEMANTICS_CH_NONE                 |
| OPTIX_PAYLOAD_SEMANTICS_CH_READ                 |
| OPTIX_PAYLOAD_SEMANTICS_CH_WRITE                |
| OPTIX_PAYLOAD_SEMANTICS_CH_READ_WRITE           |
| OPTIX_PAYLOAD_SEMANTICS_MS_NONE                 |
| OPTIX_PAYLOAD_SEMANTICS_MS_READ                 |
| OPTIX_PAYLOAD_SEMANTICS_MS_WRITE                |
| OPTIX_PAYLOAD_SEMANTICS_MS_READ_WRITE           |
| OPTIX_PAYLOAD_SEMANTICS_AH_NONE                 |
| OPTIX_PAYLOAD_SEMANTICS_AH_READ                 |
| OPTIX_PAYLOAD_SEMANTICS_AH_WRITE                |
| OPTIX_PAYLOAD_SEMANTICS_AH_READ_WRITE           |
| OPTIX_PAYLOAD_SEMANTICS_IS_NONE                 |
| OPTIX_PAYLOAD_SEMANTICS_IS_READ                 |
| OPTIX_PAYLOAD_SEMANTICS_IS_WRITE                |
| OPTIX_PAYLOAD_SEMANTICS_IS_READ_WRITE           |

#### 5.14.4.32 OptixPayloadTypeID

enum [OptixPayloadTypeID](#)

Payload type identifiers.

Enumerator

|                            |  |
|----------------------------|--|
| OPTIX_PAYLOAD_TYPE_DEFAULT |  |
| OPTIX_PAYLOAD_TYPE_ID_0    |  |
| OPTIX_PAYLOAD_TYPE_ID_1    |  |
| OPTIX_PAYLOAD_TYPE_ID_2    |  |
| OPTIX_PAYLOAD_TYPE_ID_3    |  |
| OPTIX_PAYLOAD_TYPE_ID_4    |  |
| OPTIX_PAYLOAD_TYPE_ID_5    |  |
| OPTIX_PAYLOAD_TYPE_ID_6    |  |
| OPTIX_PAYLOAD_TYPE_ID_7    |  |

#### 5.14.4.33 OptixPixelFormat

enum [OptixPixelFormat](#)

Pixel formats used by the denoiser.

See also [OptixImage2D::format](#)

Enumerator

|                                         |                           |
|-----------------------------------------|---------------------------|
| OPTIX_PIXEL_FORMAT_HALF1                | one half                  |
| OPTIX_PIXEL_FORMAT_HALF2                | two halves, XY            |
| OPTIX_PIXEL_FORMAT_HALF3                | three halves, RGB         |
| OPTIX_PIXEL_FORMAT_HALF4                | four halves, RGBA         |
| OPTIX_PIXEL_FORMAT_FLOAT1               | one float                 |
| OPTIX_PIXEL_FORMAT_FLOAT2               | two floats, XY            |
| OPTIX_PIXEL_FORMAT_FLOAT3               | three floats, RGB         |
| OPTIX_PIXEL_FORMAT_FLOAT4               | four floats, RGBA         |
| OPTIX_PIXEL_FORMAT_UCHAR3               | three unsigned chars, RGB |
| OPTIX_PIXEL_FORMAT_UCHAR4               | four unsigned chars, RGBA |
| OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER | internal format           |

#### 5.14.4.34 OptixPrimitiveType

enum [OptixPrimitiveType](#)

Builtin primitive types.

Enumerator

|                             |                   |
|-----------------------------|-------------------|
| OPTIX_PRIMITIVE_TYPE_CUSTOM | Custom primitive. |
|-----------------------------|-------------------|

## Enumerator

|                                                   |                                                               |
|---------------------------------------------------|---------------------------------------------------------------|
| OPTIX_PRIMITIVE_TYPE_ROUND_QUADRATIC_BSPLINE      | B-spline curve of degree 2 with circular cross-section.       |
| OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BSPLINE          | B-spline curve of degree 3 with circular cross-section.       |
| OPTIX_PRIMITIVE_TYPE_ROUND_LINEAR                 | Piecewise linear curve with circular cross-section.           |
| OPTIX_PRIMITIVE_TYPE_ROUND_CATMULLROM             | CatmullRom curve with circular cross-section.                 |
| OPTIX_PRIMITIVE_TYPE_FLAT_QUADRATIC_BSPLINE       | B-spline curve of degree 2 with oriented, flat cross-section. |
| OPTIX_PRIMITIVE_TYPE_SPHERE                       | Sphere.                                                       |
| OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BEZIER           | Bezier curve of degree 3 with circular cross-section.         |
| OPTIX_PRIMITIVE_TYPE_TRIANGLE                     | Triangle.                                                     |
| OPTIX_PRIMITIVE_TYPE_DISPLACED_MICROMESH_TRIANGLE | Triangle with an applied displacement micromap.               |

## 5.14.4.35 OptixPrimitiveTypeFlags

enum `OptixPrimitiveTypeFlags`

Builtin flags may be bitwise combined.

See also `OptixPipelineCompileOptions::usesPrimitiveTypeFlags`

## Enumerator

|                                                         |                                                               |
|---------------------------------------------------------|---------------------------------------------------------------|
| OPTIX_PRIMITIVE_TYPE_FLAGS_CUSTOM                       | Custom primitive.                                             |
| OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_QUADRATIC_BSPLINE      | B-spline curve of degree 2 with circular cross-section.       |
| OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BSPLINE          | B-spline curve of degree 3 with circular cross-section.       |
| OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_LINEAR                 | Piecewise linear curve with circular cross-section.           |
| OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CATMULLROM             | CatmullRom curve with circular cross-section.                 |
| OPTIX_PRIMITIVE_TYPE_FLAGS_FLAT_QUADRATIC_BSPLINE       | B-spline curve of degree 2 with oriented, flat cross-section. |
| OPTIX_PRIMITIVE_TYPE_FLAGS_SPHERE                       | Sphere.                                                       |
| OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BEZIER           | Bezier curve of degree 3 with circular cross-section.         |
| OPTIX_PRIMITIVE_TYPE_FLAGS_TRIANGLE                     | Triangle.                                                     |
| OPTIX_PRIMITIVE_TYPE_FLAGS_DISPLACED_MICROMESH_TRIANGLE | Triangle with an applied displacement micromap.               |

#### 5.14.4.36 OptixProgramGroupFlags

enum [OptixProgramGroupFlags](#)

Flags for program groups.

Enumerator

|                                |                               |
|--------------------------------|-------------------------------|
| OPTIX_PROGRAM_GROUP_FLAGS_NONE | Currently there are no flags. |
|--------------------------------|-------------------------------|

#### 5.14.4.37 OptixProgramGroupKind

enum [OptixProgramGroupKind](#)

Distinguishes different kinds of program groups.

Enumerator

|                                    |                                                                                                                                                                                                        |
|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_PROGRAM_GROUP_KIND_RAYGEN    | Program group containing a raygen (RG) program. See also <a href="#">OptixProgramGroupSingleModule</a> , <a href="#">OptixProgramGroupDesc::raygen</a>                                                 |
| OPTIX_PROGRAM_GROUP_KIND_MISS      | Program group containing a miss (MS) program. See also <a href="#">OptixProgramGroupSingleModule</a> , <a href="#">OptixProgramGroupDesc::miss</a>                                                     |
| OPTIX_PROGRAM_GROUP_KIND_EXCEPTION | Program group containing an exception (EX) program. See also <a href="#">OptixProgramGroupHitgroup</a> , <a href="#">OptixProgramGroupDesc::exception</a>                                              |
| OPTIX_PROGRAM_GROUP_KIND_HITGROUP  | Program group containing an intersection (IS), any hit (AH), and/or closest hit (CH) program. See also <a href="#">OptixProgramGroupSingleModule</a> , <a href="#">OptixProgramGroupDesc::hitgroup</a> |
| OPTIX_PROGRAM_GROUP_KIND_CALLABLES | Program group containing a direct (DC) or continuation (CC) callable program. See also <a href="#">OptixProgramGroupCallables</a> , <a href="#">OptixProgramGroupDesc::callables</a>                   |

#### 5.14.4.38 OptixQueryFunctionTableOptions

enum [OptixQueryFunctionTableOptions](#)

Options that can be passed to [optixQueryFunctionTable\(\)](#)

Enumerator

|                                         |                                        |
|-----------------------------------------|----------------------------------------|
| OPTIX_QUERY_FUNCTION_TABLE_OPTION_DUMMY | Placeholder (there are no options yet) |
|-----------------------------------------|----------------------------------------|

#### 5.14.4.39 OptixRayFlags

enum [OptixRayFlags](#)

Ray flags passed to the device function [optixTrace\(\)](#). These affect the behavior of traversal per

invocation.

See also `optixTrace()`

#### Enumerator

|                                                         |                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>OPTIX_RAY_FLAG_NONE</code>                        | No change from the behavior configured for the individual AS.                                                                                                                                                                                                                                                                                                                                |
| <code>OPTIX_RAY_FLAG_DISABLE_ANYHIT</code>              | Disables anyhit programs for the ray. Overrides <code>OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT</code> . This flag is mutually exclusive with <code>OPTIX_RAY_FLAG_ENFORCE_ANYHIT</code> , <code>OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT</code> , <code>OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT</code> .                                                                                                    |
| <code>OPTIX_RAY_FLAG_ENFORCE_ANYHIT</code>              | Forces anyhit program execution for the ray. Overrides <code>OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT</code> as well as <code>OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT</code> . This flag is mutually exclusive with <code>OPTIX_RAY_FLAG_DISABLE_ANYHIT</code> , <code>OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT</code> , <code>OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT</code> .                                  |
| <code>OPTIX_RAY_FLAG_TERMINATE_ON_FIRST_HIT</code>      | Terminates the ray after the first hit and executes the <code>closesthit</code> program of that hit.                                                                                                                                                                                                                                                                                         |
| <code>OPTIX_RAY_FLAG_DISABLE_CLOSESTHIT</code>          | Disables <code>closesthit</code> programs for the ray, but still executes miss program in case of a miss.                                                                                                                                                                                                                                                                                    |
| <code>OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES</code>  | Do not intersect triangle back faces (respects a possible face change due to instance flag <code>OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING</code> ). This flag is mutually exclusive with <code>OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES</code> .                                                                                                                                           |
| <code>OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES</code> | Do not intersect triangle front faces (respects a possible face change due to instance flag <code>OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING</code> ). This flag is mutually exclusive with <code>OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES</code> .                                                                                                                                           |
| <code>OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT</code>        | Do not intersect geometry which disables anyhit programs (due to setting geometry flag <code>OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT</code> or instance flag <code>OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT</code> ). This flag is mutually exclusive with <code>OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT</code> , <code>OPTIX_RAY_FLAG_ENFORCE_ANYHIT</code> , <code>OPTIX_RAY_FLAG_DISABLE_ANYHIT</code> . |

## Enumerator

|                                               |                                                                                                                                                                                                                                                                                                                                           |
|-----------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT           | Do not intersect geometry which have an enabled anyhit program (due to not setting geometry flag OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT or setting instance flag OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT). This flag is mutually exclusive with OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT, OPTIX_RAY_FLAG_ENFORCE_ANYHIT, OPTIX_RAY_FLAG_DISABLE_ANYHIT. |
| OPTIX_RAY_FLAG_FORCE_OPACITY_MICROMAP_2_STATE | Force 4-state opacity micromaps to behave as 2-state opactiy micromaps during traversal.                                                                                                                                                                                                                                                  |

## 5.14.4.40 OptixResult

enum `OptixResult`

Result codes returned from API functions.

All host side API functions return `OptixResult` with the exception of `optixGetErrorName` and `optixGetErrorString`. When successful `OPTIX_SUCCESS` is returned. All return codes except for `OPTIX_SUCCESS` should be assumed to be errors as opposed to a warning.

See also `optixGetErrorName()`, `optixGetErrorString()`

## Enumerator

|                                         |
|-----------------------------------------|
| OPTIX_SUCCESS                           |
| OPTIX_ERROR_INVALID_VALUE               |
| OPTIX_ERROR_HOST_OUT_OF_MEMORY          |
| OPTIX_ERROR_INVALID_OPERATION           |
| OPTIX_ERROR_FILE_IO_ERROR               |
| OPTIX_ERROR_INVALID_FILE_FORMAT         |
| OPTIX_ERROR_DISK_CACHE_INVALID_PATH     |
| OPTIX_ERROR_DISK_CACHE_PERMISSION_ERROR |
| OPTIX_ERROR_DISK_CACHE_DATABASE_ERROR   |
| OPTIX_ERROR_DISK_CACHE_INVALID_DATA     |
| OPTIX_ERROR_LAUNCH_FAILURE              |
| OPTIX_ERROR_INVALID_DEVICE_CONTEXT      |
| OPTIX_ERROR_CUDA_NOT_INITIALIZED        |
| OPTIX_ERROR_VALIDATION_FAILURE          |
| OPTIX_ERROR_INVALID_INPUT               |
| OPTIX_ERROR_INVALID_LAUNCH_PARAMETER    |
| OPTIX_ERROR_INVALID_PAYLOAD_ACCESS      |
| OPTIX_ERROR_INVALID_ATTRIBUTE_ACCESS    |
| OPTIX_ERROR_INVALID_FUNCTION_USE        |



## Enumerator

|                                             |
|---------------------------------------------|
| OPTIX_ERROR_INVALID_FUNCTION_ARGUMENTS      |
| OPTIX_ERROR_PIPELINE_OUT_OF_CONSTANT_MEMORY |
| OPTIX_ERROR_PIPELINE_LINK_ERROR             |
| OPTIX_ERROR_ILLEGAL_DURING_TASK_EXECUTE     |
| OPTIX_ERROR_INTERNAL_COMPILER_ERROR         |
| OPTIX_ERROR_DENOISER_MODEL_NOT_SET          |
| OPTIX_ERROR_DENOISER_NOT_INITIALIZED        |
| OPTIX_ERROR_NOT_COMPATIBLE                  |
| OPTIX_ERROR_PAYLOAD_TYPE_MISMATCH           |
| OPTIX_ERROR_PAYLOAD_TYPE_RESOLUTION_FAILED  |
| OPTIX_ERROR_PAYLOAD_TYPE_ID_INVALID         |
| OPTIX_ERROR_NOT_SUPPORTED                   |
| OPTIX_ERROR_UNSUPPORTED_ABI_VERSION         |
| OPTIX_ERROR_FUNCTION_TABLE_SIZE_MISMATCH    |
| OPTIX_ERROR_INVALID_ENTRY_FUNCTION_OPTIONS  |
| OPTIX_ERROR_LIBRARY_NOT_FOUND               |
| OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND          |
| OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE          |
| OPTIX_ERROR_DEVICE_OUT_OF_MEMORY            |
| OPTIX_ERROR_CUDA_ERROR                      |
| OPTIX_ERROR_INTERNAL_ERROR                  |
| OPTIX_ERROR_UNKNOWN                         |

## 5.14.4.41 OptixTransformFormat

enum `OptixTransformFormat`Format of transform used in `OptixBuildInputTriangleArray::transformFormat`.

## Enumerator

|                                       |                                               |
|---------------------------------------|-----------------------------------------------|
| OPTIX_TRANSFORM_FORMAT_NONE           | no transform, default for zero initialization |
| OPTIX_TRANSFORM_FORMAT_MATRIX_FLOAT12 | 3x4 row major affine matrix                   |

## 5.14.4.42 OptixTransformType

enum `OptixTransformType`

Transform.

`OptixTransformType` is used by the device function `optixGetTransformTypeFromHandle()` to determine the type of the `OptixTraversableHandle` returned from `optixGetTransformListHandle()`.

## Enumerator

|                                              |                                                     |
|----------------------------------------------|-----------------------------------------------------|
| OPTIX_TRANSFORM_TYPE_NONE                    | Not a transformation.                               |
| OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM        | See also <a href="#">OptixStaticTransform</a>       |
| OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM | See also <a href="#">OptixMatrixMotionTransform</a> |
| OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM    | See also <a href="#">OptixSRTMotionTransform</a>    |
| OPTIX_TRANSFORM_TYPE_INSTANCE                | See also <a href="#">OptixInstance</a>              |

## 5.14.4.43 OptixTraversableGraphFlags

enum [OptixTraversableGraphFlags](#)

Specifies the set of valid traversable graphs that may be passed to invocation of [optixTrace\(\)](#). Flags may be bitwise combined.

## Enumerator

|                                                            |                                                                                                                                                                                                                                                                                                                      |
|------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_ANY                     | Used to signal that any traversable graphs is valid. This flag is mutually exclusive with all other flags.                                                                                                                                                                                                           |
| OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_GAS              | Used to signal that a traversable graph of a single Geometry Acceleration Structure (GAS) without any transforms is valid. This flag may be combined with other flags except for OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_ANY.                                                                                             |
| OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_LEVEL_INSTANCING | Used to signal that a traversable graph of a single Instance Acceleration Structure (IAS) directly connected to Geometry Acceleration Structure (GAS) traversables without transform traversables in between is valid. This flag may be combined with other flags except for OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_ANY. |

## 5.14.4.44 OptixTraversableType

enum [OptixTraversableType](#)

Traversable Handles.

See also [optixConvertPointerToTraversableHandle\(\)](#)

## Enumerator

|                                                |                                                                              |
|------------------------------------------------|------------------------------------------------------------------------------|
| OPTIX_TRAVERSABLE_TYPE_STATIC_TRANSFORM        | Static transforms. See also <a href="#">OptixStaticTransform</a>             |
| OPTIX_TRAVERSABLE_TYPE_MATRIX_MOTION_TRANSFORM | Matrix motion transform. See also <a href="#">OptixMatrixMotionTransform</a> |

Enumerator

|                                             |                                                                        |
|---------------------------------------------|------------------------------------------------------------------------|
| OPTIX_TRAVERSABLE_TYPE_SRT_MOTION_TRANSFORM | SRT motion transform. See also <a href="#">OptixSRTMotionTransform</a> |
|---------------------------------------------|------------------------------------------------------------------------|

#### 5.14.4.45 OptixVertexFormat

enum [OptixVertexFormat](#)

Format of vertices used in [OptixBuildInputTriangleArray::vertexFormat](#).

Enumerator

|                               |                                           |
|-------------------------------|-------------------------------------------|
| OPTIX_VERTEX_FORMAT_NONE      | No vertices.                              |
| OPTIX_VERTEX_FORMAT_FLOAT3    | Vertices are represented by three floats. |
| OPTIX_VERTEX_FORMAT_FLOAT2    | Vertices are represented by two floats.   |
| OPTIX_VERTEX_FORMAT_HALF3     | Vertices are represented by three halves. |
| OPTIX_VERTEX_FORMAT_HALF2     | Vertices are represented by two halves.   |
| OPTIX_VERTEX_FORMAT_SNORM16_3 |                                           |
| OPTIX_VERTEX_FORMAT_SNORM16_2 |                                           |

## 6 Namespace Documentation

### 6.1 optix\_impl Namespace Reference

#### Functions

- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ float4 optixAddFloat4](#) (const float4 &a, const float4 &b)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ float4 optixMulFloat4](#) (const float4 &a, float b)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ uint4 optixLdg](#) (unsigned long long addr)
- template<class T >  
static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ T optixLoadReadOnlyAlign16](#) (const T \*ptr)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ float4 optixMultiplyRowMatrix](#) (const float4 vec, const float4 m0, const float4 m1, const float4 m2)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixGetMatrixFromSrt](#) (float4 &m0, float4 &m1, float4 &m2, const [OptixSRTData](#) &srt)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixInvertMatrix](#) (float4 &m0, float4 &m1, float4 &m2)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixLoadInterpolatedMatrixKey](#) (float4 &m0, float4 &m1, float4 &m2, const float4 \*matrix, const float t1)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixLoadInterpolatedSrtKey](#) (float4 &srt0, float4 &srt1, float4 &srt2, float4 &srt3, const float4 \*srt, const float t1)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixResolveMotionKey](#) (float &localt, int &key, const [OptixMotionOptions](#) &options, const float globalt)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixGetInterpolatedTransformation](#) (float4 &trf0, float4 &trf1, float4 &trf2, const [OptixMatrixMotionTransform](#) \*transformData, const float time)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixGetInterpolatedTransformation](#) (float4 &trf0, float4 &trf1, float4 &trf2, const [OptixSRTMotionTransform](#) \*transformData, const float time)
- static [\\_\\_forceinline\\_\\_ \\_\\_device\\_\\_ void optixGetInterpolatedTransformationFromHandle](#) (float4 &trf0, float4 &trf1, float4 &trf2, const [OptixTraversableHandle](#) handle, const float time, const bool objectToWorld)

- static `__forceinline__ __device__ void optixGetWorldToObjectTransformMatrix` (float4 &m0, float4 &m1, float4 &m2)
- static `__forceinline__ __device__ void optixGetObjectToWorldTransformMatrix` (float4 &m0, float4 &m1, float4 &m2)
- static `__forceinline__ __device__ float3 optixTransformPoint` (const float4 &m0, const float4 &m1, const float4 &m2, const float3 &p)
- static `__forceinline__ __device__ float3 optixTransformVector` (const float4 &m0, const float4 &m1, const float4 &m2, const float3 &v)
- static `__forceinline__ __device__ float3 optixTransformNormal` (const float4 &m0, const float4 &m1, const float4 &m2, const float3 &n)
- `OPTIX_MICROMAP_INLINE_FUNC float __uint_as_float` (unsigned int x)
- `OPTIX_MICROMAP_INLINE_FUNC unsigned int extractEvenBits` (unsigned int x)
- `OPTIX_MICROMAP_INLINE_FUNC unsigned int prefixEor` (unsigned int x)
- `OPTIX_MICROMAP_INLINE_FUNC void index2dbary` (unsigned int index, unsigned int &u, unsigned int &v, unsigned int &w)
- `OPTIX_MICROMAP_INLINE_FUNC void micro2bary` (unsigned int index, unsigned int subdivisionLevel, float2 &bary0, float2 &bary1, float2 &bary2)
- `OPTIX_MICROMAP_INLINE_FUNC float2 base2micro` (const float2 &baseBarycentrics, const float2 microVertexBaseBarycentrics[3])

## 6.1.1 Function Documentation

### 6.1.1.1 optixAddFloat4()

```
static __forceinline__ __device__ float4 optix_impl::optixAddFloat4 (
    const float4 & a,
    const float4 & b ) [static]
```

### 6.1.1.2 optixGetInterpolatedTransformation() [1/2]

```
static __forceinline__ __device__ void optix_impl
::optixGetInterpolatedTransformation (
    float4 & trf0,
    float4 & trf1,
    float4 & trf2,
    const OptixMatrixMotionTransform * transformData,
    const float time ) [static]
```

### 6.1.1.3 optixGetInterpolatedTransformation() [2/2]

```
static __forceinline__ __device__ void optix_impl
::optixGetInterpolatedTransformation (
    float4 & trf0,
    float4 & trf1,
    float4 & trf2,
    const OptixSRTMotionTransform * transformData,
    const float time ) [static]
```

## 6.1.1.4 optixGetInterpolatedTransformationFromHandle()

```
static __forceinline__ __device__ void optix_impl
::optixGetInterpolatedTransformationFromHandle (
    float4 & trf0,
    float4 & trf1,
    float4 & trf2,
    const OptixTraversableHandle handle,
    const float time,
    const bool objectToWorld ) [static]
```

## 6.1.1.5 optixGetMatrixFromSrt()

```
static __forceinline__ __device__ void optix_impl::optixGetMatrixFromSrt (
    float4 & m0,
    float4 & m1,
    float4 & m2,
    const OptixSRTData & srt ) [static]
```

## 6.1.1.6 optixGetObjectToWorldTransformMatrix()

```
static __forceinline__ __device__ void optix_impl
::optixGetObjectToWorldTransformMatrix (
    float4 & m0,
    float4 & m1,
    float4 & m2 ) [static]
```

## 6.1.1.7 optixGetWorldToObjectTransformMatrix()

```
static __forceinline__ __device__ void optix_impl
::optixGetWorldToObjectTransformMatrix (
    float4 & m0,
    float4 & m1,
    float4 & m2 ) [static]
```

## 6.1.1.8 optixInvertMatrix()

```
static __forceinline__ __device__ void optix_impl::optixInvertMatrix (
    float4 & m0,
    float4 & m1,
    float4 & m2 ) [static]
```

## 6.1.1.9 optixLdg()

```
static __forceinline__ __device__ uint4 optix_impl::optixLdg (
    unsigned long long addr ) [static]
```

#### 6.1.1.10 optixLoadInterpolatedMatrixKey()

```
static __forceinline__ __device__ void optix_impl
::optixLoadInterpolatedMatrixKey (
    float4 & m0,
    float4 & m1,
    float4 & m2,
    const float4 * matrix,
    const float t1 ) [static]
```

#### 6.1.1.11 optixLoadInterpolatedSrtKey()

```
static __forceinline__ __device__ void optix_impl
::optixLoadInterpolatedSrtKey (
    float4 & srt0,
    float4 & srt1,
    float4 & srt2,
    float4 & srt3,
    const float4 * srt,
    const float t1 ) [static]
```

#### 6.1.1.12 optixLoadReadOnlyAlign16()

```
template<class T >
static __forceinline__ __device__ T optix_impl::optixLoadReadOnlyAlign16 (
    const T * ptr ) [static]
```

#### 6.1.1.13 optixMulFloat4()

```
static __forceinline__ __device__ float4 optix_impl::optixMulFloat4 (
    const float4 & a,
    float b ) [static]
```

#### 6.1.1.14 optixMultiplyRowMatrix()

```
static __forceinline__ __device__ float4 optix_impl::optixMultiplyRowMatrix
(
    const float4 vec,
    const float4 m0,
    const float4 m1,
    const float4 m2 ) [static]
```

#### 6.1.1.15 optixResolveMotionKey()

```
static __forceinline__ __device__ void optix_impl::optixResolveMotionKey (
    float & localt,
    int & key,
    const OptixMotionOptions & options,
```

```
const float globalt ) [static]
```

#### 6.1.1.16 optixTransformNormal()

```
static __forceinline__ __device__ float3 optix_impl::optixTransformNormal (
    const float4 & m0,
    const float4 & m1,
    const float4 & m2,
    const float3 & n ) [static]
```

#### 6.1.1.17 optixTransformPoint()

```
static __forceinline__ __device__ float3 optix_impl::optixTransformPoint (
    const float4 & m0,
    const float4 & m1,
    const float4 & m2,
    const float3 & p ) [static]
```

#### 6.1.1.18 optixTransformVector()

```
static __forceinline__ __device__ float3 optix_impl::optixTransformVector (
    const float4 & m0,
    const float4 & m1,
    const float4 & m2,
    const float3 & v ) [static]
```

## 6.2 optix\_internal Namespace Reference

### Classes

- struct [TypePack](#)

## 7 Class Documentation

### 7.1 OptixAabb Struct Reference

```
#include <optix_types.h>
```

#### Public Attributes

- float [minX](#)
- float [minY](#)
- float [minZ](#)
- float [maxX](#)
- float [maxY](#)
- float [maxZ](#)

#### 7.1.1 Detailed Description

AABB inputs.

## 7.1.2 Member Data Documentation

### 7.1.2.1 maxX

float OptixAabb::maxX

Upper extent in X direction.

### 7.1.2.2 maxY

float OptixAabb::maxY

Upper extent in Y direction.

### 7.1.2.3 maxZ

float OptixAabb::maxZ

Upper extent in Z direction.

### 7.1.2.4 minX

float OptixAabb::minX

Lower extent in X direction.

### 7.1.2.5 minY

float OptixAabb::minY

Lower extent in Y direction.

### 7.1.2.6 minZ

float OptixAabb::minZ

Lower extent in Z direction.

## 7.2 OptixAccelBufferSizes Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- [size\\_t outputSizeInBytes](#)
- [size\\_t tempSizeInBytes](#)
- [size\\_t tempUpdateSizeInBytes](#)

### 7.2.1 Detailed Description

Struct for querying builder allocation requirements.

Once queried the sizes should be used to allocate device memory of at least these sizes.

See also [optixAccelComputeMemoryUsage\(\)](#)

## 7.2.2 Member Data Documentation

### 7.2.2.1 outputSizeInBytes

size\_t OptixAccelBufferSizes::outputSizeInBytes



The size in bytes required for the `outputBuffer` parameter to `optixAccelBuild` when doing a build (`OPTIX_BUILD_OPERATION_BUILD`).

#### 7.2.2.2 tempSizeInBytes

`size_t OptixAccelBufferSizes::tempSizeInBytes`

The size in bytes required for the `tempBuffer` paramter to `optixAccelBuild` when doing a build (`OPTIX_BUILD_OPERATION_BUILD`).

#### 7.2.2.3 tempUpdateSizeInBytes

`size_t OptixAccelBufferSizes::tempUpdateSizeInBytes`

The size in bytes required for the `tempBuffer` parameter to `optixAccelBuild` when doing an update (`OPTIX_BUILD_OPERATION_UPDATE`). This value can be different than `tempSizeInBytes` used for a full build. Only non-zero if `OPTIX_BUILD_FLAG_ALLOW_UPDATE` flag is set in [OptixAccelBuildOptions](#).

### 7.3 OptixAccelBuildOptions Struct Reference

```
#include <optix_types.h>
```

#### Public Attributes

- unsigned int [buildFlags](#)
- [OptixBuildOperation](#) operation
- [OptixMotionOptions](#) motionOptions

#### 7.3.1 Detailed Description

Build options for acceleration structures.

See also [optixAccelComputeMemoryUsage\(\)](#), [optixAccelBuild\(\)](#)

#### 7.3.2 Member Data Documentation

##### 7.3.2.1 buildFlags

`unsigned int OptixAccelBuildOptions::buildFlags`

Combinations of [OptixBuildFlags](#).

##### 7.3.2.2 motionOptions

[OptixMotionOptions](#) `OptixAccelBuildOptions::motionOptions`

Options for motion.

##### 7.3.2.3 operation

[OptixBuildOperation](#) `OptixAccelBuildOptions::operation`

If `OPTIX_BUILD_OPERATION_UPDATE` the output buffer is assumed to contain the result of a full build with `OPTIX_BUILD_FLAG_ALLOW_UPDATE` set and using the same number of primitives. It is updated incrementally to reflect the current position of the primitives. If a BLAS has been built with `OPTIX_BUILD_FLAG_ALLOW_OPACITY_MICROMAP_UPDATE`, new opacity micromap arrays and opacity micromap indices may be provided to the refit.

## 7.4 OptixAccelEmitDesc Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- [CUdeviceptr](#) result
- [OptixAccelPropertyType](#) type

#### 7.4.1 Detailed Description

Specifies a type and output destination for emitted post-build properties.

See also [optixAccelBuild\(\)](#)

#### 7.4.2 Member Data Documentation

##### 7.4.2.1 result

[CUdeviceptr](#) [OptixAccelEmitDesc::result](#)

Output buffer for the properties.

##### 7.4.2.2 type

[OptixAccelPropertyType](#) [OptixAccelEmitDesc::type](#)

Requested property.

## 7.5 OptixBuildInput Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- [OptixBuildInputType](#) type
  - union {
    - [OptixBuildInputTriangleArray](#) triangleArray
    - [OptixBuildInputCurveArray](#) curveArray
    - [OptixBuildInputSphereArray](#) sphereArray
    - [OptixBuildInputCustomPrimitiveArray](#) customPrimitiveArray
    - [OptixBuildInputInstanceArray](#) instanceArray
    - char pad [1024]
- };

#### 7.5.1 Detailed Description

Build inputs.

All of them support motion and the size of the data arrays needs to match the number of motion steps

See also [optixAccelComputeMemoryUsage\(\)](#), [optixAccelBuild\(\)](#)

#### 7.5.2 Member Data Documentation

##### 7.5.2.1

union { ... } [OptixBuildInput::@1](#)

### 7.5.2.2 curveArray

`OptixBuildInputCurveArray` `OptixBuildInput::curveArray`

Curve inputs.

### 7.5.2.3 customPrimitiveArray

`OptixBuildInputCustomPrimitiveArray` `OptixBuildInput::customPrimitiveArray`

Custom primitive inputs.

### 7.5.2.4 instanceArray

`OptixBuildInputInstanceArray` `OptixBuildInput::instanceArray`

Instance and instance pointer inputs.

### 7.5.2.5 pad

`char` `OptixBuildInput::pad[1024]`

### 7.5.2.6 sphereArray

`OptixBuildInputSphereArray` `OptixBuildInput::sphereArray`

Sphere inputs.

### 7.5.2.7 triangleArray

`OptixBuildInputTriangleArray` `OptixBuildInput::triangleArray`

Triangle inputs.

### 7.5.2.8 type

`OptixBuildInputType` `OptixBuildInput::type`

The type of the build input.

## 7.6 OptixBuildInputCurveArray Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `OptixPrimitiveType` `curveType`
- unsigned int `numPrimitives`
- const `CUdeviceptr` \* `vertexBuffers`
- unsigned int `numVertices`
- unsigned int `vertexStrideInBytes`
- const `CUdeviceptr` \* `widthBuffers`
- unsigned int `widthStrideInBytes`
- const `CUdeviceptr` \* `normalBuffers`
- unsigned int `normalStrideInBytes`
- `CUdeviceptr` `indexBuffer`
- unsigned int `indexStrideInBytes`
- unsigned int `flag`
- unsigned int `primitiveIndexOffset`

- unsigned int `endcapFlags`

## 7.6.1 Detailed Description

Curve inputs.

A curve is a swept surface defined by a 3D spline curve and a varying width (radius). A curve (or "strand") of degree  $d$  (3=cubic, 2=quadratic, 1=linear) is represented by  $N > d$  vertices and  $N$  width values, and comprises  $N - d$  segments. Each segment is defined by  $d+1$  consecutive vertices. Each curve may have a different number of vertices.

OptiX describes the curve array as a list of curve segments. The primitive id is the segment number. It is the user's responsibility to maintain a mapping between curves and curve segments. Each index buffer entry  $i = \text{indexBuffer}[\text{primid}]$  specifies the start of a curve segment, represented by  $d+1$  consecutive vertices in the vertex buffer, and  $d+1$  consecutive widths in the width buffer. Width is interpolated the same way vertices are interpolated, that is, using the curve basis.

Each curves build input has only one SBT record. To create curves with different materials in the same BVH, use multiple build inputs.

See also [OptixBuildInput::curveArray](#)

## 7.6.2 Member Data Documentation

### 7.6.2.1 curveType

`OptixPrimitiveType` `OptixBuildInputCurveArray::curveType`

Curve degree and basis.

See also [OptixPrimitiveType](#)

### 7.6.2.2 endcapFlags

`unsigned int` `OptixBuildInputCurveArray::endcapFlags`

End cap flags, see [OptixCurveEndcapFlags](#).

### 7.6.2.3 flag

`unsigned int` `OptixBuildInputCurveArray::flag`

Combination of [OptixGeometryFlags](#) describing the primitive behavior.

### 7.6.2.4 indexBuffer

`CUdeviceptr` `OptixBuildInputCurveArray::indexBuffer`

Device pointer to array of unsigned ints, one per curve segment. This buffer is required (unlike for [OptixBuildInputTriangleArray](#)). Each index is the start of degree+1 consecutive vertices in `vertexBuffers`, and corresponding widths in `widthBuffers` and normals in `normalBuffers`. These define a single segment. Size of array is `numPrimitives`.

### 7.6.2.5 indexStrideInBytes

`unsigned int` `OptixBuildInputCurveArray::indexStrideInBytes`

Stride between indices. If set to zero, indices are assumed to be tightly packed and stride is `sizeof(unsigned int)`.

#### 7.6.2.6 normalBuffers

```
const CUdeviceptr* OptixBuildInputCurveArray::normalBuffers
```

Reserved for future use.

#### 7.6.2.7 normalStrideInBytes

```
unsigned int OptixBuildInputCurveArray::normalStrideInBytes
```

Reserved for future use.

#### 7.6.2.8 numPrimitives

```
unsigned int OptixBuildInputCurveArray::numPrimitives
```

Number of primitives. Each primitive is a polynomial curve segment.

#### 7.6.2.9 numVertices

```
unsigned int OptixBuildInputCurveArray::numVertices
```

Number of vertices in each buffer in `vertexBuffers`.

#### 7.6.2.10 primitiveIndexOffset

```
unsigned int OptixBuildInputCurveArray::primitiveIndexOffset
```

Primitive index bias, applied in `optixGetPrimitiveIndex()`. Sum of `primitiveIndexOffset` and number of primitives must not overflow 32bits.

#### 7.6.2.11 vertexBuffers

```
const CUdeviceptr* OptixBuildInputCurveArray::vertexBuffers
```

Pointer to host array of device pointers, one per motion step. Host array size must match number of motion keys as set in `OptixMotionOptions` (or an array of size 1 if `OptixMotionOptions::numKeys` is set to 1). Each per-motion-key device pointer must point to an array of floats (the vertices of the curves).

#### 7.6.2.12 vertexStrideInBytes

```
unsigned int OptixBuildInputCurveArray::vertexStrideInBytes
```

Stride between vertices. If set to zero, vertices are assumed to be tightly packed and stride is `sizeof(float3)`.

#### 7.6.2.13 widthBuffers

```
const CUdeviceptr* OptixBuildInputCurveArray::widthBuffers
```

Parallel to `vertexBuffers`: a device pointer per motion step, each with `numVertices` float values, specifying the curve width (radius) corresponding to each vertex.

#### 7.6.2.14 widthStrideInBytes

```
unsigned int OptixBuildInputCurveArray::widthStrideInBytes
```

Stride between widths. If set to zero, widths are assumed to be tightly packed and stride is `sizeof(float)`.

## 7.7 OptixBuildInputCustomPrimitiveArray Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `const CUdeviceptr * aabbBuffers`
- `unsigned int numPrimitives`
- `unsigned int strideInBytes`
- `const unsigned int * flags`
- `unsigned int numSbtRecords`
- `CUdeviceptr sbtIndexOffsetBuffer`
- `unsigned int sbtIndexOffsetSizeInBytes`
- `unsigned int sbtIndexOffsetStrideInBytes`
- `unsigned int primitiveIndexOffset`

### 7.7.1 Detailed Description

Custom primitive inputs.

See also `OptixBuildInput::customPrimitiveArray`

### 7.7.2 Member Data Documentation

#### 7.7.2.1 aabbBuffers

```
const CUdeviceptr* OptixBuildInputCustomPrimitiveArray::aabbBuffers
```

Points to host array of device pointers to AABBs (type `OptixAabb`), one per motion step. Host array size must match number of motion keys as set in `OptixMotionOptions` (or an array of size 1 if `OptixMotionOptions::numKeys` is set to 1). Each device pointer must be a multiple of `OPTIX_AABB_BUFFER_BYTE_ALIGNMENT`.

#### 7.7.2.2 flags

```
const unsigned int* OptixBuildInputCustomPrimitiveArray::flags
```

Array of flags, to specify flags per sbt record, combinations of `OptixGeometryFlags` describing the primitive behavior, size must match `numSbtRecords`.

#### 7.7.2.3 numPrimitives

```
unsigned int OptixBuildInputCustomPrimitiveArray::numPrimitives
```

Number of primitives in each buffer (i.e., per motion step) in `OptixBuildInputCustomPrimitiveArray::aabbBuffers`.

#### 7.7.2.4 numSbtRecords

```
unsigned int OptixBuildInputCustomPrimitiveArray::numSbtRecords
```

Number of sbt records available to the sbt index offset override.

#### 7.7.2.5 primitiveIndexOffset

```
unsigned int OptixBuildInputCustomPrimitiveArray::primitiveIndexOffset
```

Primitive index bias, applied in `optixGetPrimitiveIndex()`. Sum of `primitiveIndexOffset` and number of primitive must not overflow 32bits.

### 7.7.2.6 sbtIndexOffsetBuffer

`CUdeviceptr` `OptixBuildInputCustomPrimitiveArray::sbtIndexOffsetBuffer`

Device pointer to per-primitive local sbt index offset buffer. May be NULL. Every entry must be in range [0,numSbtRecords-1]. Size needs to be the number of primitives.

### 7.7.2.7 sbtIndexOffsetSizeInBytes

`unsigned int` `OptixBuildInputCustomPrimitiveArray::sbtIndexOffsetSizeInBytes`

Size of type of the sbt index offset. Needs to be 0, 1, 2 or 4 (8, 16 or 32 bit).

### 7.7.2.8 sbtIndexOffsetStrideInBytes

`unsigned int` `OptixBuildInputCustomPrimitiveArray::sbtIndexOffsetStrideInBytes`

Stride between the index offsets. If set to zero, the offsets are assumed to be tightly packed and the stride matches the size of the type (`sbtIndexOffsetSizeInBytes`).

### 7.7.2.9 strideInBytes

`unsigned int` `OptixBuildInputCustomPrimitiveArray::strideInBytes`

Stride between AABBs (per motion key). If set to zero, the aabbs are assumed to be tightly packed and the stride is assumed to be `sizeof(OptixAabb)`. If non-zero, the value must be a multiple of `OPTIX_AABB_BUFFER_BYTE_ALIGNMENT`.

## 7.8 OptixBuildInputDisplacementMicromap Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `OptixDisplacementMicromapArrayIndexingMode` `indexingMode`
- `CUdeviceptr` `displacementMicromapArray`
- `CUdeviceptr` `displacementMicromapIndexBuffer`
- `CUdeviceptr` `vertexDirectionsBuffer`
- `CUdeviceptr` `vertexBiasAndScaleBuffer`
- `CUdeviceptr` `triangleFlagsBuffer`
- `unsigned int` `displacementMicromapIndexOffset`
- `unsigned int` `displacementMicromapIndexStrideInBytes`
- `unsigned int` `displacementMicromapIndexSizeInBytes`
- `OptixDisplacementMicromapDirectionFormat` `vertexDirectionFormat`
- `unsigned int` `vertexDirectionStrideInBytes`
- `OptixDisplacementMicromapBiasAndScaleFormat` `vertexBiasAndScaleFormat`
- `unsigned int` `vertexBiasAndScaleStrideInBytes`
- `unsigned int` `triangleFlagsStrideInBytes`
- `unsigned int` `numDisplacementMicromapUsageCounts`
- `const` `OptixDisplacementMicromapUsageCount * displacementMicromapUsageCounts`

### 7.8.1 Detailed Description

Optional displacement part of a triangle array input.

## 7.8.2 Member Data Documentation

### 7.8.2.1 displacementMicromapArray

`CUdeviceptr` `OptixBuildInputDisplacementMicromap::displacementMicromapArray`

Address to a displacement micromap array used by this build input array. Set to NULL to disable DMs for this input.

### 7.8.2.2 displacementMicromapIndexBuffer

`CUdeviceptr` `OptixBuildInputDisplacementMicromap::displacementMicromapIndexBuffer`

int16 or int32 buffer specifying which displacement micromap index to use for each triangle. Only valid if displacementMicromapArray != NULL.

### 7.8.2.3 displacementMicromapIndexOffset

unsigned int `OptixBuildInputDisplacementMicromap::displacementMicromapIndexOffset`

Constant offset to displacement micromap indices as specified by the displacement micromap index buffer.

### 7.8.2.4 displacementMicromapIndexSizeInBytes

unsigned int `OptixBuildInputDisplacementMicromap::displacementMicromapIndexSizeInBytes`

2 or 4 (16 or 32 bit)

### 7.8.2.5 displacementMicromapIndexStrideInBytes

unsigned int `OptixBuildInputDisplacementMicromap::displacementMicromapIndexStrideInBytes`

Displacement micromap index buffer stride. If set to zero, indices are assumed to be tightly packed and stride is inferred from `OptixBuildInputDisplacementMicromap::displacementMicromapIndexSizeInBytes`.

### 7.8.2.6 displacementMicromapUsageCounts

const `OptixDisplacementMicromapUsageCount*`  
`OptixBuildInputDisplacementMicromap::displacementMicromapUsageCounts`

List of number of usages of displacement micromaps of format and subdivision combinations. Counts with equal format and subdivision combination (duplicates) are added together.

### 7.8.2.7 indexingMode

`OptixDisplacementMicromapArrayIndexingMode`  
`OptixBuildInputDisplacementMicromap::indexingMode`

Indexing mode of triangle to displacement micromap array mapping.

### 7.8.2.8 numDisplacementMicromapUsageCounts

unsigned int `OptixBuildInputDisplacementMicromap`



`::numDisplacementMicromapUsageCounts`

Number of `OptixDisplacementMicromapUsageCount` entries.

#### 7.8.2.9 triangleFlagsBuffer

`CUdeviceptr` `OptixBuildInputDisplacementMicromap::triangleFlagsBuffer`

Optional per-triangle flags, `uint8_t` per triangle, possible values defined in enum `OptixDisplacementMicromapTriangleFlags`.

#### 7.8.2.10 triangleFlagsStrideInBytes

`unsigned int` `OptixBuildInputDisplacementMicromap::triangleFlagsStrideInBytes`

Stride in bytes for `triangleFlags`.

#### 7.8.2.11 vertexBiasAndScaleBuffer

`CUdeviceptr` `OptixBuildInputDisplacementMicromap::vertexBiasAndScaleBuffer`

Optional per-vertex bias (offset) along displacement direction and displacement direction scale.

#### 7.8.2.12 vertexBiasAndScaleFormat

`OptixDisplacementMicromapBiasAndScaleFormat`

`OptixBuildInputDisplacementMicromap::vertexBiasAndScaleFormat`

Format of vertex bias and direction scale.

#### 7.8.2.13 vertexBiasAndScaleStrideInBytes

`unsigned int` `OptixBuildInputDisplacementMicromap::vertexBiasAndScaleStrideInBytes`

Stride in bytes for vertex bias and direction scale entries.

#### 7.8.2.14 vertexDirectionFormat

`OptixDisplacementMicromapDirectionFormat`

`OptixBuildInputDisplacementMicromap::vertexDirectionFormat`

Format of displacement vectors.

#### 7.8.2.15 vertexDirectionsBuffer

`CUdeviceptr` `OptixBuildInputDisplacementMicromap::vertexDirectionsBuffer`

Per triangle-vertex displacement directions.

#### 7.8.2.16 vertexDirectionStrideInBytes

`unsigned int` `OptixBuildInputDisplacementMicromap::vertexDirectionStrideInBytes`

Stride between displacement vectors.

### 7.9 OptixBuildInputInstanceArray Struct Reference

```
#include <optix_types.h>
```

## Public Attributes

- [CUdeviceptr](#) instances
- unsigned int numInstances
- unsigned int instanceStride

### 7.9.1 Detailed Description

Instance and instance pointer inputs.

See also [OptixBuildInput::instanceArray](#)

### 7.9.2 Member Data Documentation

#### 7.9.2.1 instances

[CUdeviceptr](#) OptixBuildInputInstanceArray::instances

If [OptixBuildInput::type](#) is OPTIX\_BUILD\_INPUT\_TYPE\_INSTANCE\_POINTERS instances and aabbs should be interpreted as arrays of pointers instead of arrays of structs.

This pointer must be a multiple of OPTIX\_INSTANCE\_BYTE\_ALIGNMENT if [OptixBuildInput::type](#) is OPTIX\_BUILD\_INPUT\_TYPE\_INSTANCES. The array elements must be a multiple of OPTIX\_INSTANCE\_BYTE\_ALIGNMENT if [OptixBuildInput::type](#) is OPTIX\_BUILD\_INPUT\_TYPE\_INSTANCE\_POINTERS.

#### 7.9.2.2 instanceStride

unsigned int OptixBuildInputInstanceArray::instanceStride

Only valid for OPTIX\_BUILD\_INPUT\_TYPE\_INSTANCE Defines the stride between instances. A stride of 0 indicates a tight packing, i.e., stride = sizeof(OptixInstance)

#### 7.9.2.3 numInstances

unsigned int OptixBuildInputInstanceArray::numInstances

Number of elements in [OptixBuildInputInstanceArray::instances](#).

## 7.10 OptixBuildInputOpacityMicromap Struct Reference

```
#include <optix_types.h>
```

## Public Attributes

- [OptixOpacityMicromapArrayIndexingMode](#) indexingMode
- [CUdeviceptr](#) opacityMicromapArray
- [CUdeviceptr](#) indexBuffer
- unsigned int indexSizeInBytes
- unsigned int indexStrideInBytes
- unsigned int indexOffset
- unsigned int numMicromapUsageCounts
- const [OptixOpacityMicromapUsageCount](#) \* micromapUsageCounts

### 7.10.1 Member Data Documentation

#### 7.10.1.1 indexBuffer

[CUdeviceptr](#) OptixBuildInputOpacityMicromap::indexBuffer

int16 or int32 buffer specifying which opacity micromap index to use for each triangle. Instead of an actual index, one of the predefined indices `OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_TRANSPARENT` | `OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_OPAQUE` | `OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_TRANSPARENT` | `OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_OPAQUE` can be used to indicate that there is no opacity micromap for this particular triangle but the triangle is in a uniform state and the selected behavior is applied to the entire triangle. This buffer is required when `OptixBuildInputOpacityMicromap::indexingMode` is `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_INDEXED`. Must be zero if

`OptixBuildInputOpacityMicromap::indexingMode` is `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_LINEAR` or `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_NONE`.

### 7.10.1.2 indexingMode

`OptixOpacityMicromapArrayIndexingMode` `OptixBuildInputOpacityMicromap::indexingMode`

Indexing mode of triangle to opacity micromap array mapping.

### 7.10.1.3 indexOffset

`unsigned int` `OptixBuildInputOpacityMicromap::indexOffset`

Constant offset to non-negative opacity micromap indices.

### 7.10.1.4 indexSizeInBytes

`unsigned int` `OptixBuildInputOpacityMicromap::indexSizeInBytes`

0, 2 or 4 (unused, 16 or 32 bit) Must be non-zero when `OptixBuildInputOpacityMicromap::indexingMode` is `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_INDEXED`.

### 7.10.1.5 indexStrideInBytes

`unsigned int` `OptixBuildInputOpacityMicromap::indexStrideInBytes`

Opacity micromap index buffer stride. If set to zero, indices are assumed to be tightly packed and stride is inferred from `OptixBuildInputOpacityMicromap::indexSizeInBytes`.

### 7.10.1.6 micromapUsageCounts

`const OptixOpacityMicromapUsageCount*` `OptixBuildInputOpacityMicromap::micromapUsageCounts`

List of number of usages of opacity micromaps of format and subdivision combinations. Counts with equal format and subdivision combination (duplicates) are added together.

### 7.10.1.7 numMicromapUsageCounts

`unsigned int` `OptixBuildInputOpacityMicromap::numMicromapUsageCounts`

Number of `OptixOpacityMicromapUsageCount`.

### 7.10.1.8 opacityMicromapArray

`CUdeviceptr` `OptixBuildInputOpacityMicromap::opacityMicromapArray`

Device pointer to a opacity micromap array used by this build input array. This buffer is required when `OptixBuildInputOpacityMicromap::indexingMode` is `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_LINEAR` or `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_NONE`.

INDEXED. Must be zero if [OptixBuildInputOpacityMicromap::indexingMode](#) is `OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_NONE`.

## 7.11 OptixBuildInputSphereArray Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `const CUdeviceptr * vertexBuffers`
- `unsigned int vertexStrideInBytes`
- `unsigned int numVertices`
- `const CUdeviceptr * radiusBuffers`
- `unsigned int radiusStrideInBytes`
- `int singleRadius`
- `const unsigned int * flags`
- `unsigned int numSbtRecords`
- `CUdeviceptr sbtIndexOffsetBuffer`
- `unsigned int sbtIndexOffsetSizeInBytes`
- `unsigned int sbtIndexOffsetStrideInBytes`
- `unsigned int primitiveIndexOffset`

### 7.11.1 Detailed Description

Sphere inputs.

A sphere is defined by a center point and a radius. Each center point is represented by a vertex in the vertex buffer. There is either a single radius for all spheres, or the radii are represented by entries in the radius buffer.

The vertex buffers and radius buffers point to a host array of device pointers, one per motion step. Host array size must match the number of motion keys as set in [OptixMotionOptions](#) (or an array of size 1 if [OptixMotionOptions::numKeys](#) is set to 0 or 1). Each per motion key device pointer must point to an array of vertices corresponding to the center points of the spheres, or an array of 1 or N radii. Format `OPTIX_VERTEX_FORMAT_FLOAT3` is used for vertices, `OPTIX_VERTEX_FORMAT_FLOAT` for radii.

See also [OptixBuildInput::sphereArray](#)

### 7.11.2 Member Data Documentation

#### 7.11.2.1 flags

```
const unsigned int* OptixBuildInputSphereArray::flags
```

Array of flags, to specify flags per sbt record, combinations of [OptixGeometryFlags](#) describing the primitive behavior, size must match `numSbtRecords`.

#### 7.11.2.2 numSbtRecords

```
unsigned int OptixBuildInputSphereArray::numSbtRecords
```

Number of sbt records available to the sbt index offset override.

#### 7.11.2.3 numVertices

```
unsigned int OptixBuildInputSphereArray::numVertices
```

Number of vertices in each buffer in `vertexBuffers`.

#### 7.11.2.4 primitiveIndexOffset

`unsigned int OptixBuildInputSphereArray::primitiveIndexOffset`

Primitive index bias, applied in `optixGetPrimitiveIndex()`. Sum of `primitiveIndexOffset` and number of primitives must not overflow 32bits.

#### 7.11.2.5 radiusBuffers

`const CUdeviceptr* OptixBuildInputSphereArray::radiusBuffers`

Parallel to `vertexBuffers`: a device pointer per motion step, each with `numRadii` float values, specifying the sphere radius corresponding to each vertex.

#### 7.11.2.6 radiusStrideInBytes

`unsigned int OptixBuildInputSphereArray::radiusStrideInBytes`

Stride between radii. If set to zero, widths are assumed to be tightly packed and stride is `sizeof(float)`.

#### 7.11.2.7 sbtIndexOffsetBuffer

`CUdeviceptr OptixBuildInputSphereArray::sbtIndexOffsetBuffer`

Device pointer to per-primitive local sbt index offset buffer. May be NULL. Every entry must be in range `[0,numSbtRecords-1]`. Size needs to be the number of primitives.

#### 7.11.2.8 sbtIndexOffsetSizeInBytes

`unsigned int OptixBuildInputSphereArray::sbtIndexOffsetSizeInBytes`

Size of type of the sbt index offset. Needs to be 0, 1, 2 or 4 (8, 16 or 32 bit).

#### 7.11.2.9 sbtIndexOffsetStrideInBytes

`unsigned int OptixBuildInputSphereArray::sbtIndexOffsetStrideInBytes`

Stride between the sbt index offsets. If set to zero, the offsets are assumed to be tightly packed and the stride matches the size of the type (`sbtIndexOffsetSizeInBytes`).

#### 7.11.2.10 singleRadius

`int OptixBuildInputSphereArray::singleRadius`

Boolean value indicating whether a single radius per radius buffer is used, or the number of radii in `radiusBuffers` equals `numVertices`.

#### 7.11.2.11 vertexBuffers

`const CUdeviceptr* OptixBuildInputSphereArray::vertexBuffers`

Pointer to host array of device pointers, one per motion step. Host array size must match number of motion keys as set in `OptixMotionOptions` (or an array of size 1 if `OptixMotionOptions::numKeys` is set to 1). Each per-motion-key device pointer must point to an array of floats (the center points of the spheres).

#### 7.11.2.12 vertexStrideInBytes

`unsigned int OptixBuildInputSphereArray::vertexStrideInBytes`

Stride between vertices. If set to zero, vertices are assumed to be tightly packed and stride is

sizeof(float3).

## 7.12 OptixBuildInputTriangleArray Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `const CUdeviceptr * vertexBuffers`
- `unsigned int numVertices`
- `OptixVertexFormat vertexFormat`
- `unsigned int vertexStrideInBytes`
- `CUdeviceptr indexBuffer`
- `unsigned int numIndexTriplets`
- `OptixIndicesFormat indexFormat`
- `unsigned int indexStrideInBytes`
- `CUdeviceptr preTransform`
- `const unsigned int * flags`
- `unsigned int numSbtRecords`
- `CUdeviceptr sbtIndexOffsetBuffer`
- `unsigned int sbtIndexOffsetSizeInBytes`
- `unsigned int sbtIndexOffsetStrideInBytes`
- `unsigned int primitiveIndexOffset`
- `OptixTransformFormat transformFormat`
- `OptixBuildInputOpacityMicromap opacityMicromap`
- `OptixBuildInputDisplacementMicromap displacementMicromap`

### 7.12.1 Detailed Description

Triangle inputs.

See also `OptixBuildInput::triangleArray`

### 7.12.2 Member Data Documentation

#### 7.12.2.1 displacementMicromap

`OptixBuildInputDisplacementMicromap OptixBuildInputTriangleArray::displacementMicromap`

Optional displacement micromap inputs.

#### 7.12.2.2 flags

`const unsigned int* OptixBuildInputTriangleArray::flags`

Array of flags, to specify flags per sbt record, combinations of `OptixGeometryFlags` describing the primitive behavior, size must match `numSbtRecords`.

#### 7.12.2.3 indexBuffer

`CUdeviceptr OptixBuildInputTriangleArray::indexBuffer`

Optional pointer to array of 16 or 32-bit int triplets, one triplet per triangle. The minimum alignment must match the natural alignment of the type as specified in the `indexFormat`, i.e., for `OPTIX_INDICES_FORMAT_UNSIGNED_INT3` 4-byte and for `OPTIX_INDICES_FORMAT_UNSIGNED_SHORT3` a 2-byte alignment.

#### 7.12.2.4 indexFormat

[OptixIndicesFormat](#) `OptixBuildInputTriangleArray::indexFormat`

See also [OptixIndicesFormat](#)

#### 7.12.2.5 indexStrideInBytes

`unsigned int OptixBuildInputTriangleArray::indexStrideInBytes`

Stride between triplets of indices. If set to zero, indices are assumed to be tightly packed and stride is inferred from `indexFormat`.

#### 7.12.2.6 numIndexTriplets

`unsigned int OptixBuildInputTriangleArray::numIndexTriplets`

Size of array in [OptixBuildInputTriangleArray::indexBuffer](#). For build, needs to be zero if `indexBuffer` is `nullptr`.

#### 7.12.2.7 numSbtRecords

`unsigned int OptixBuildInputTriangleArray::numSbtRecords`

Number of sbt records available to the sbt index offset override.

#### 7.12.2.8 numVertices

`unsigned int OptixBuildInputTriangleArray::numVertices`

Number of vertices in each of buffer in [OptixBuildInputTriangleArray::vertexBuffers](#).

#### 7.12.2.9 opacityMicromap

[OptixBuildInputOpacityMicromap](#) `OptixBuildInputTriangleArray::opacityMicromap`

Optional opacity micromap inputs.

#### 7.12.2.10 preTransform

[CUdeviceptr](#) `OptixBuildInputTriangleArray::preTransform`

Optional pointer to array of floats representing a 3x4 row major affine transformation matrix. This pointer must be a multiple of `OPTIX_GEOMETRY_TRANSFORM_BYTE_ALIGNMENT`.

#### 7.12.2.11 primitiveIndexOffset

`unsigned int OptixBuildInputTriangleArray::primitiveIndexOffset`

Primitive index bias, applied in [optixGetPrimitiveIndex\(\)](#). Sum of `primitiveIndexOffset` and number of triangles must not overflow 32bits.

#### 7.12.2.12 sbtIndexOffsetBuffer

[CUdeviceptr](#) `OptixBuildInputTriangleArray::sbtIndexOffsetBuffer`

Device pointer to per-primitive local sbt index offset buffer. May be `NULL`. Every entry must be in range `[0,numSbtRecords-1]`. Size needs to be the number of primitives.

### 7.12.2.13 sbtIndexOffsetSizeInBytes

`unsigned int OptixBuildInputTriangleArray::sbtIndexOffsetSizeInBytes`

Size of type of the sbt index offset. Needs to be 0, 1, 2 or 4 (8, 16 or 32 bit).

### 7.12.2.14 sbtIndexOffsetStrideInBytes

`unsigned int OptixBuildInputTriangleArray::sbtIndexOffsetStrideInBytes`

Stride between the index offsets. If set to zero, the offsets are assumed to be tightly packed and the stride matches the size of the type (`sbtIndexOffsetSizeInBytes`).

### 7.12.2.15 transformFormat

`OptixTransformFormat OptixBuildInputTriangleArray::transformFormat`

See also [OptixTransformFormat](#)

### 7.12.2.16 vertexBuffers

`const CUdeviceptr* OptixBuildInputTriangleArray::vertexBuffers`

Points to host array of device pointers, one per motion step. Host array size must match the number of motion keys as set in [OptixMotionOptions](#) (or an array of size 1 if [OptixMotionOptions::numKeys](#) is set to 0 or 1). Each per motion key device pointer must point to an array of vertices of the triangles in the format as described by `vertexFormat`. The minimum alignment must match the natural alignment of the type as specified in the `vertexFormat`, i.e., for `OPTIX_VERTEX_FORMAT_FLOATX` 4-byte, for all others a 2-byte alignment. However, an 16-byte stride (and buffer alignment) is recommended for vertices of format `OPTIX_VERTEX_FORMAT_FLOAT3` for GAS build performance.

### 7.12.2.17 vertexFormat

`OptixVertexFormat OptixBuildInputTriangleArray::vertexFormat`

See also [OptixVertexFormat](#)

### 7.12.2.18 vertexStrideInBytes

`unsigned int OptixBuildInputTriangleArray::vertexStrideInBytes`

Stride between vertices. If set to zero, vertices are assumed to be tightly packed and stride is inferred from `vertexFormat`.

## 7.13 OptixBuiltinISOOptions Struct Reference

`#include <optix_types.h>`

### Public Attributes

- [OptixPrimitiveType](#) `builtinISModuleType`
- `int` `usesMotionBlur`
- `unsigned int` `buildFlags`
- `unsigned int` `curveEndcapFlags`

### 7.13.1 Detailed Description

Specifies the options for retrieving an intersection program for a built-in primitive type. The primitive type must not be `OPTIX_PRIMITIVE_TYPE_CUSTOM`.



See also [optixBuiltinISModuleGet\(\)](#)

## 7.13.2 Member Data Documentation

### 7.13.2.1 buildFlags

`unsigned int OptixBuiltinISOptions::buildFlags`

Build flags, see [OptixBuildFlags](#).

### 7.13.2.2 builtinISModuleType

[OptixPrimitiveType](#) `OptixBuiltinISOptions::builtinISModuleType`

### 7.13.2.3 curveEndcapFlags

`unsigned int OptixBuiltinISOptions::curveEndcapFlags`

End cap properties of curves, see [OptixCurveEndcapFlags](#), 0 for non-curve types.

### 7.13.2.4 usesMotionBlur

`int OptixBuiltinISOptions::usesMotionBlur`

Boolean value indicating whether vertex motion blur is used (but not motion transform blur).

## 7.14 OptixDenoiserGuideLayer Struct Reference

`#include <optix_types.h>`

### Public Attributes

- [OptixImage2D](#) `albedo`
- [OptixImage2D](#) `normal`
- [OptixImage2D](#) `flow`
- [OptixImage2D](#) `previousOutputInternalGuideLayer`
- [OptixImage2D](#) `outputInternalGuideLayer`
- [OptixImage2D](#) `flowTrustworthiness`

### 7.14.1 Detailed Description

Guide layer for the denoiser.

See also [optixDenoiserInvoke\(\)](#)

## 7.14.2 Member Data Documentation

### 7.14.2.1 albedo

[OptixImage2D](#) `OptixDenoiserGuideLayer::albedo`

### 7.14.2.2 flow

[OptixImage2D](#) `OptixDenoiserGuideLayer::flow`

### 7.14.2.3 flowTrustworthiness

[OptixImage2D](#) `OptixDenoiserGuideLayer::flowTrustworthiness`

#### 7.14.2.4 normal

[OptixImage2D](#) [OptixDenoiserGuideLayer::normal](#)

#### 7.14.2.5 outputInternalGuideLayer

[OptixImage2D](#) [OptixDenoiserGuideLayer::outputInternalGuideLayer](#)

#### 7.14.2.6 previousOutputInternalGuideLayer

[OptixImage2D](#) [OptixDenoiserGuideLayer::previousOutputInternalGuideLayer](#)

### 7.15 OptixDenoiserLayer Struct Reference

```
#include <optix_types.h>
```

#### Public Attributes

- [OptixImage2D](#) [input](#)
- [OptixImage2D](#) [previousOutput](#)
- [OptixImage2D](#) [output](#)
- [OptixDenoiserAOVType](#) [type](#)

#### 7.15.1 Detailed Description

Input/Output layers for the denoiser.

See also [optixDenoiserInvoke\(\)](#)

#### 7.15.2 Member Data Documentation

##### 7.15.2.1 input

[OptixImage2D](#) [OptixDenoiserLayer::input](#)

##### 7.15.2.2 output

[OptixImage2D](#) [OptixDenoiserLayer::output](#)

##### 7.15.2.3 previousOutput

[OptixImage2D](#) [OptixDenoiserLayer::previousOutput](#)

##### 7.15.2.4 type

[OptixDenoiserAOVType](#) [OptixDenoiserLayer::type](#)

### 7.16 OptixDenoiserOptions Struct Reference

```
#include <optix_types.h>
```

#### Public Attributes

- unsigned int [guideAlbedo](#)
- unsigned int [guideNormal](#)
- [OptixDenoiserAlphaMode](#) [denoiseAlpha](#)

### 7.16.1 Detailed Description

Options used by the denoiser.

See also [optixDenoiserCreate\(\)](#)

### 7.16.2 Member Data Documentation

#### 7.16.2.1 denoiseAlpha

[OptixDenoiserAlphaMode](#) [OptixDenoiserOptions::denoiseAlpha](#)

alpha denoise mode

#### 7.16.2.2 guideAlbedo

`unsigned int OptixDenoiserOptions::guideAlbedo`

#### 7.16.2.3 guideNormal

`unsigned int OptixDenoiserOptions::guideNormal`

## 7.17 OptixDenoiserParams Struct Reference

`#include <optix_types.h>`

### Public Attributes

- [CUdeviceptr](#) `hdrIntensity`
- `float` `blendFactor`
- [CUdeviceptr](#) `hdrAverageColor`
- `unsigned int` `temporalModeUsePreviousLayers`

### 7.17.1 Detailed Description

Various parameters used by the denoiser.

See also [optixDenoiserInvoke\(\)](#)

[optixDenoiserComputeIntensity\(\)](#)

[optixDenoiserComputeAverageColor\(\)](#)

### 7.17.2 Member Data Documentation

#### 7.17.2.1 blendFactor

`float OptixDenoiserParams::blendFactor`

blend factor. If set to 0 the output is 100% of the denoised input. If set to 1, the output is 100% of the unmodified input. Values between 0 and 1 will linearly interpolate between the denoised and unmodified input.

#### 7.17.2.2 hdrAverageColor

[CUdeviceptr](#) [OptixDenoiserParams::hdrAverageColor](#)

this parameter is used when the `OPTIX_DENOISER_MODEL_KIND_AOV` model kind is set. average log color of input image, separate for RGB channels (default null pointer). points to three floats. if set to null, average log color will be calculated automatically. See `hdrIntensity` for tiling, this also applies

here.

### 7.17.2.3 hdrIntensity

`CUdeviceptr` `OptixDenoiserParams::hdrIntensity`

average log intensity of input image (default null pointer). points to a single float. if set to null, autoexposure will be calculated automatically for the input image. Should be set to average log intensity of the entire image at least if tiling is used to get consistent autoexposure for all tiles.

### 7.17.2.4 temporalModeUsePreviousLayers

`unsigned int` `OptixDenoiserParams::temporalModeUsePreviousLayers`

In temporal modes this parameter must be set to 1 if previous layers (e.g. `previousOutputInternalGuideLayer`) contain valid data. This is the case in the second and subsequent frames of a sequence (for example after a change of camera angle). In the first frame of such a sequence this parameter must be set to 0.

## 7.18 OptixDenoiserSizes Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `size_t` `stateSizeInBytes`
- `size_t` `withOverlapScratchSizeInBytes`
- `size_t` `withoutOverlapScratchSizeInBytes`
- `unsigned int` `overlapWindowSizeInPixels`
- `size_t` `computeAverageColorSizeInBytes`
- `size_t` `computeIntensitySizeInBytes`
- `size_t` `internalGuideLayerPixelSizeInBytes`

### 7.18.1 Detailed Description

Various sizes related to the denoiser.

See also `optixDenoiserComputeMemoryResources()`

### 7.18.2 Member Data Documentation

#### 7.18.2.1 computeAverageColorSizeInBytes

`size_t` `OptixDenoiserSizes::computeAverageColorSizeInBytes`

Size of scratch memory passed to `optixDenoiserComputeAverageColor`. The size is independent of the tile/image resolution.

#### 7.18.2.2 computeIntensitySizeInBytes

`size_t` `OptixDenoiserSizes::computeIntensitySizeInBytes`

Size of scratch memory passed to `optixDenoiserComputeIntensity`. The size is independent of the tile/image resolution.

#### 7.18.2.3 internalGuideLayerPixelSizeInBytes

`size_t` `OptixDenoiserSizes::internalGuideLayerPixelSizeInBytes`

Number of bytes for each pixel in internal guide layers.

#### 7.18.2.4 overlapWindowSizeInPixels

`unsigned int OptixDenoiserSizes::overlapWindowSizeInPixels`

Overlap on all four tile sides.

#### 7.18.2.5 stateSizeInBytes

`size_t OptixDenoiserSizes::stateSizeInBytes`

Size of state memory passed to [optixDenoiserSetup](#), [optixDenoiserInvoke](#).

#### 7.18.2.6 withoutOverlapScratchSizeInBytes

`size_t OptixDenoiserSizes::withoutOverlapScratchSizeInBytes`

Size of scratch memory passed to [optixDenoiserSetup](#), [optixDenoiserInvoke](#). No overlap added.

#### 7.18.2.7 withOverlapScratchSizeInBytes

`size_t OptixDenoiserSizes::withOverlapScratchSizeInBytes`

Size of scratch memory passed to [optixDenoiserSetup](#), [optixDenoiserInvoke](#). Overlap added to dimensions passed to [optixDenoiserComputeMemoryResources](#).

### 7.19 OptixDeviceContextOptions Struct Reference

`#include <optix_types.h>`

#### Public Attributes

- [OptixLogCallback](#) `logCallbackFunction`
- `void *` `logCallbackData`
- `int` `logCallbackLevel`
- [OptixDeviceContextValidationMode](#) `validationMode`

#### 7.19.1 Detailed Description

Parameters used for [optixDeviceContextCreate\(\)](#)

See also [optixDeviceContextCreate\(\)](#)

#### 7.19.2 Member Data Documentation

##### 7.19.2.1 logCallbackData

`void* OptixDeviceContextOptions::logCallbackData`

Pointer stored and passed to [logCallbackFunction](#) when a message is generated.

##### 7.19.2.2 logCallbackFunction

[OptixLogCallback](#) `OptixDeviceContextOptions::logCallbackFunction`

Function pointer used when OptiX wishes to generate messages.

### 7.19.2.3 logCallbackLevel

`int OptixDeviceContextOptions::logCallbackLevel`

Maximum callback level to generate message for (see [OptixLogCallback](#))

### 7.19.2.4 validationMode

`OptixDeviceContextValidationMode OptixDeviceContextOptions::validationMode`

Validation mode of context.

## 7.20 OptixDisplacementMicromapArrayBuildInput Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `OptixDisplacementMicromapFlags` flags
- `CUdeviceptr` displacementValuesBuffer
- `CUdeviceptr` perDisplacementMicromapDescBuffer
- `unsigned int` perDisplacementMicromapDescStrideInBytes
- `unsigned int` numDisplacementMicromapHistogramEntries
- `const OptixDisplacementMicromapHistogramEntry *` displacementMicromapHistogramEntries

### 7.20.1 Detailed Description

Inputs to displacement micromaps array construction.

### 7.20.2 Member Data Documentation

#### 7.20.2.1 displacementMicromapHistogramEntries

```
const OptixDisplacementMicromapHistogramEntry*
OptixDisplacementMicromapArrayBuildInput
::displacementMicromapHistogramEntries
```

Histogram over DMMs for input format and subdivision combinations. Counts of histogram bins with equal format and subdivision combinations are added together.

#### 7.20.2.2 displacementValuesBuffer

```
CUdeviceptr OptixDisplacementMicromapArrayBuildInput
::displacementValuesBuffer
```

128 byte aligned pointer for displacement micromap raw input data.

#### 7.20.2.3 flags

```
OptixDisplacementMicromapFlags OptixDisplacementMicromapArrayBuildInput
::flags
```

Flags that apply to all displacement micromaps in array.

#### 7.20.2.4 numDisplacementMicromapHistogramEntries

```
unsigned int OptixDisplacementMicromapArrayBuildInput
::numDisplacementMicromapHistogramEntries
```

Number of `OptixDisplacementMicromapHistogramEntry` entries.

### 7.20.2.5 perDisplacementMicromapDescBuffer

```
CUdeviceptr OptixDisplacementMicromapArrayBuildInput
::perDisplacementMicromapDescBuffer
```

Descriptors for interpreting raw input data, one [OptixDisplacementMicromapDesc](#) entry required per displacement micromap. This device pointer must be a multiple of `OPTIX_DISPLACEMENT_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT`.

### 7.20.2.6 perDisplacementMicromapDescStrideInBytes

```
unsigned int OptixDisplacementMicromapArrayBuildInput
::perDisplacementMicromapDescStrideInBytes
```

Stride between [OptixDisplacementMicromapDesc](#) in `perDisplacementMicromapDescBuffer`. If set to zero, the displacement micromap descriptors are assumed to be tightly packed and the stride is assumed to be `sizeof(OptixDisplacementMicromapDesc)`. This stride must be a multiple of `OPTIX_DISPLACEMENT_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT`.

## 7.21 OptixDisplacementMicromapDesc Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int [byteOffset](#)
- unsigned short [subdivisionLevel](#)
- unsigned short [format](#)

### 7.21.1 Member Data Documentation

#### 7.21.1.1 byteOffset

```
unsigned int OptixDisplacementMicromapDesc::byteOffset
```

Block is located at `displacementValuesBuffer + byteOffset`.

#### 7.21.1.2 format

```
unsigned short OptixDisplacementMicromapDesc::format
```

Format ([OptixDisplacementMicromapFormat](#))

#### 7.21.1.3 subdivisionLevel

```
unsigned short OptixDisplacementMicromapDesc::subdivisionLevel
```

Number of micro-triangles is  $4^{\text{level}}$ . Valid levels are `[0, 5]`.

## 7.22 OptixDisplacementMicromapHistogramEntry Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int [count](#)
- unsigned int [subdivisionLevel](#)
- [OptixDisplacementMicromapFormat](#) [format](#)

### 7.22.1 Detailed Description

Displacement micromap histogram entry. Specifies how many displacement micromaps of a specific type are input to the displacement micromap array build. Note that while this is similar to [OptixDisplacementMicromapUsageCount](#), the histogram entry specifies how many displacement micromaps of a specific type are combined into a displacement micromap array.

### 7.22.2 Member Data Documentation

#### 7.22.2.1 count

`unsigned int OptixDisplacementMicromapHistogramEntry::count`

Number of displacement micromaps with the format and subdivision level that are input to the displacement micromap array build.

#### 7.22.2.2 format

`OptixDisplacementMicromapFormat OptixDisplacementMicromapHistogramEntry::format`

Displacement micromap format.

#### 7.22.2.3 subdivisionLevel

`unsigned int OptixDisplacementMicromapHistogramEntry::subdivisionLevel`

Number of micro-triangles is  $4^{\text{level}}$ . Valid levels are [0, 5].

## 7.23 OptixDisplacementMicromapUsageCount Struct Reference

`#include <optix_types.h>`

### Public Attributes

- unsigned int `count`
- unsigned int `subdivisionLevel`
- `OptixDisplacementMicromapFormat` `format`

### 7.23.1 Detailed Description

Displacement micromap usage count for acceleration structure builds. Specifies how many displacement micromaps of a specific type are referenced by triangles when building the AS. Note that while this is similar to [OptixDisplacementMicromapHistogramEntry](#), the usage count specifies how many displacement micromaps of a specific type are referenced by triangles in the AS.

### 7.23.2 Member Data Documentation

#### 7.23.2.1 count

`unsigned int OptixDisplacementMicromapUsageCount::count`

Number of displacement micromaps with this format and subdivision level referenced by triangles in the corresponding triangle build input at AS build time.

#### 7.23.2.2 format

`OptixDisplacementMicromapFormat OptixDisplacementMicromapUsageCount::format`



Displacement micromaps format.

### 7.23.2.3 subdivisionLevel

unsigned int OptixDisplacementMicromapUsageCount::subdivisionLevel

Number of micro-triangles is  $4^{\text{level}}$ . Valid levels are [0, 5].

## 7.24 OptixFunctionTable Struct Reference

```
#include <optix_function_table.h>
```

### Public Attributes

#### Error handling

- const char \*(\* optixGetErrorName)(OptixResult result)
- const char \*(\* optixGetErrorString)(OptixResult result)

#### Device context

- OptixResult(\* optixDeviceContextCreate)(CUcontext fromContext, const OptixDeviceContextOptions \*options, OptixDeviceContext \*context)
- OptixResult(\* optixDeviceContextDestroy)(OptixDeviceContext context)
- OptixResult(\* optixDeviceContextGetProperty)(OptixDeviceContext context, OptixDeviceProperty property, void \*value, size\_t sizeInBytes)
- OptixResult(\* optixDeviceContextSetLogCallback)(OptixDeviceContext context, OptixLogCallback callbackFunction, void \*callbackData, unsigned int callbackLevel)
- OptixResult(\* optixDeviceContextSetCacheEnabled)(OptixDeviceContext context, int enabled)
- OptixResult(\* optixDeviceContextSetCacheLocation)(OptixDeviceContext context, const char \*location)
- OptixResult(\* optixDeviceContextSetCacheDatabaseSizes)(OptixDeviceContext context, size\_t lowWaterMark, size\_t highWaterMark)
- OptixResult(\* optixDeviceContextGetCacheEnabled)(OptixDeviceContext context, int \*enabled)
- OptixResult(\* optixDeviceContextGetCacheLocation)(OptixDeviceContext context, char \*location, size\_t locationSize)
- OptixResult(\* optixDeviceContextGetCacheDatabaseSizes)(OptixDeviceContext context, size\_t \*lowWaterMark, size\_t \*highWaterMark)

#### Modules

- OptixResult(\* optixModuleCreate)(OptixDeviceContext context, const OptixModuleCompileOptions \*moduleCompileOptions, const OptixPipelineCompileOptions \*pipelineCompileOptions, const char \*input, size\_t inputSize, char \*logString, size\_t \*logStringSize, OptixModule \*module)
- OptixResult(\* optixModuleCreateWithTasks)(OptixDeviceContext context, const OptixModuleCompileOptions \*moduleCompileOptions, const OptixPipelineCompileOptions \*pipelineCompileOptions, const char \*input, size\_t inputSize, char \*logString, size\_t \*logStringSize, OptixModule \*module, OptixTask \*firstTask)
- OptixResult(\* optixModuleGetCompilationState)(OptixModule module, OptixModuleCompileState \*state)
- OptixResult(\* optixModuleDestroy)(OptixModule module)
- OptixResult(\* optixBuiltinISModuleGet)(OptixDeviceContext context, const OptixModuleCompileOptions \*moduleCompileOptions, const OptixPipelineCompileOptions \*pipelineCompileOptions, const OptixBuiltinISOOptions \*builtinISOOptions, OptixModule \*builtinModule)

#### Tasks

- `OptixResult(* optixTaskExecute)(OptixTask task, OptixTask *additionalTasks, unsigned int maxNumAdditionalTasks, unsigned int *numAdditionalTasksCreated)`

#### Program groups

- `OptixResult(* optixProgramGroupCreate)(OptixDeviceContext context, const OptixProgramGroupDesc *programDescriptions, unsigned int numProgramGroups, const OptixProgramGroupOptions *options, char *logString, size_t *logStringSize, OptixProgramGroup *programGroups)`
- `OptixResult(* optixProgramGroupDestroy)(OptixProgramGroup programGroup)`
- `OptixResult(* optixProgramGroupGetStackSize)(OptixProgramGroup programGroup, OptixStackSizes *stackSizes, OptixPipeline pipeline)`

#### Pipeline

- `OptixResult(* optixPipelineCreate)(OptixDeviceContext context, const OptixPipelineCompileOptions *pipelineCompileOptions, const OptixPipelineLinkOptions *pipelineLinkOptions, const OptixProgramGroup *programGroups, unsigned int numProgramGroups, char *logString, size_t *logStringSize, OptixPipeline *pipeline)`
- `OptixResult(* optixPipelineDestroy)(OptixPipeline pipeline)`
- `OptixResult(* optixPipelineSetStackSize)(OptixPipeline pipeline, unsigned int directCallableStackSizeFromTraversal, unsigned int directCallableStackSizeFromState, unsigned int continuationStackSize, unsigned int maxTraversableGraphDepth)`

#### Acceleration structures

- `OptixResult(* optixAccelComputeMemoryUsage)(OptixDeviceContext context, const OptixAccelBuildOptions *accelOptions, const OptixBuildInput *buildInputs, unsigned int numBuildInputs, OptixAccelBufferSizes *bufferSizes)`
- `OptixResult(* optixAccelBuild)(OptixDeviceContext context, CUstream stream, const OptixAccelBuildOptions *accelOptions, const OptixBuildInput *buildInputs, unsigned int numBuildInputs, CUdeviceptr tempBuffer, size_t tempBufferSizeInBytes, CUdeviceptr outputBuffer, size_t outputBufferSizeInBytes, OptixTraversableHandle *outputHandle, const OptixAccelEmitDesc *emittedProperties, unsigned int numEmittedProperties)`
- `OptixResult(* optixAccelGetRelocationInfo)(OptixDeviceContext context, OptixTraversableHandle handle, OptixRelocationInfo *info)`
- `OptixResult(* optixCheckRelocationCompatibility)(OptixDeviceContext context, const OptixRelocationInfo *info, int *compatible)`
- `OptixResult(* optixAccelRelocate)(OptixDeviceContext context, CUstream stream, const OptixRelocationInfo *info, const OptixRelocateInput *relocateInputs, size_t numRelocateInputs, CUdeviceptr targetAccel, size_t targetAccelSizeInBytes, OptixTraversableHandle *targetHandle)`
- `OptixResult(* optixAccelCompact)(OptixDeviceContext context, CUstream stream, OptixTraversableHandle inputHandle, CUdeviceptr outputBuffer, size_t outputBufferSizeInBytes, OptixTraversableHandle *outputHandle)`
- `OptixResult(* optixAccelEmitProperty)(OptixDeviceContext context, CUstream stream, OptixTraversableHandle handle, const OptixAccelEmitDesc *emittedProperty)`
- `OptixResult(* optixConvertPointerToTraversableHandle)(OptixDeviceContext onDevice, CUdeviceptr pointer, OptixTraversableType traversableType, OptixTraversableHandle *traversableHandle)`
- `OptixResult(* optixOpacityMicromapArrayComputeMemoryUsage)(OptixDeviceContext context, const OptixOpacityMicromapArrayBuildInput *buildInput, OptixMicromapBufferSizes *bufferSizes)`
- `OptixResult(* optixOpacityMicromapArrayBuild)(OptixDeviceContext context, CUstream stream, const OptixOpacityMicromapArrayBuildInput *buildInput, const OptixMicromapBuffers *buffers)`

- `OptixResult(* optixOpacityMicromapArrayGetRelocationInfo)(OptixDeviceContext context, CUdeviceptr opacityMicromapArray, OptixRelocationInfo *info)`
- `OptixResult(* optixOpacityMicromapArrayRelocate)(OptixDeviceContext context, CUstream stream, const OptixRelocationInfo *info, CUdeviceptr targetOpacityMicromapArray, size_t targetOpacityMicromapArraySizeInBytes)`
- `OptixResult(* optixDisplacementMicromapArrayComputeMemoryUsage)(OptixDeviceContext context, const OptixDisplacementMicromapArrayBuildInput *buildInput, OptixMicromapBufferSizes *bufferSizes)`
- `OptixResult(* optixDisplacementMicromapArrayBuild)(OptixDeviceContext context, CUstream stream, const OptixDisplacementMicromapArrayBuildInput *buildInput, const OptixMicromapBuffers *buffers)`

#### Launch

- `OptixResult(* optixSbtRecordPackHeader)(OptixProgramGroup programGroup, void *sbtRecordHeaderHostPointer)`
- `OptixResult(* optixLaunch)(OptixPipeline pipeline, CUstream stream, CUdeviceptr pipelineParams, size_t pipelineParamsSize, const OptixShaderBindingTable *sbt, unsigned int width, unsigned int height, unsigned int depth)`

#### Denoiser

- `OptixResult(* optixDenoiserCreate)(OptixDeviceContext context, OptixDenoiserModelKind modelKind, const OptixDenoiserOptions *options, OptixDenoiser *returnHandle)`
- `OptixResult(* optixDenoiserDestroy)(OptixDenoiser handle)`
- `OptixResult(* optixDenoiserComputeMemoryResources)(const OptixDenoiser handle, unsigned int maximumInputWidth, unsigned int maximumInputHeight, OptixDenoiserSizes *returnSizes)`
- `OptixResult(* optixDenoiserSetup)(OptixDenoiser denoiser, CUstream stream, unsigned int inputWidth, unsigned int inputHeight, CUdeviceptr state, size_t stateSizeInBytes, CUdeviceptr scratch, size_t scratchSizeInBytes)`
- `OptixResult(* optixDenoiserInvoke)(OptixDenoiser denoiser, CUstream stream, const OptixDenoiserParams *params, CUdeviceptr denoiserState, size_t denoiserStateSizeInBytes, const OptixDenoiserGuideLayer *guideLayer, const OptixDenoiserLayer *layers, unsigned int numLayers, unsigned int inputOffsetX, unsigned int inputOffsetY, CUdeviceptr scratch, size_t scratchSizeInBytes)`
- `OptixResult(* optixDenoiserComputeIntensity)(OptixDenoiser handle, CUstream stream, const OptixImage2D *inputImage, CUdeviceptr outputIntensity, CUdeviceptr scratch, size_t scratchSizeInBytes)`
- `OptixResult(* optixDenoiserComputeAverageColor)(OptixDenoiser handle, CUstream stream, const OptixImage2D *inputImage, CUdeviceptr outputAverageColor, CUdeviceptr scratch, size_t scratchSizeInBytes)`
- `OptixResult(* optixDenoiserCreateWithUserModel)(OptixDeviceContext context, const void *data, size_t dataSizeInBytes, OptixDenoiser *returnHandle)`

### 7.24.1 Detailed Description

The function table containing all API functions.

See `optixInit()` and `optixInitWithHandle()`.

### 7.24.2 Member Data Documentation

#### 7.24.2.1 optixAccelBuild

`OptixResult(* OptixFunctionTable::optixAccelBuild) (OptixDeviceContext context, CUstream stream, const OptixAccelBuildOptions *accelOptions, const`

`OptixBuildInput *buildInputs`, unsigned int `numBuildInputs`, `CUdeviceptr` `tempBuffer`, `size_t` `tempBufferSizeInBytes`, `CUdeviceptr` `outputBuffer`, `size_t` `outputBufferSizeInBytes`, `OptixTraversableHandle` `*outputHandle`, const `OptixAccelEmitDesc` `*emittedProperties`, unsigned int `numEmittedProperties`)

See `optixAccelBuild()`.

#### 7.24.2.2 optixAccelCompact

`OptixResult`(\* `OptixFunctionTable::optixAccelCompact`) (`OptixDeviceContext` `context`, `CUstream` `stream`, `OptixTraversableHandle` `inputHandle`, `CUdeviceptr` `outputBuffer`, `size_t` `outputBufferSizeInBytes`, `OptixTraversableHandle` `*outputHandle`)

See `optixAccelCompact()`.

#### 7.24.2.3 optixAccelComputeMemoryUsage

`OptixResult`(\* `OptixFunctionTable::optixAccelComputeMemoryUsage`) (`OptixDeviceContext` `context`, const `OptixAccelBuildOptions` `*accelOptions`, const `OptixBuildInput` `*buildInputs`, unsigned int `numBuildInputs`, `OptixAccelBufferSizes` `*bufferSizes`)

See `optixAccelComputeMemoryUsage()`.

#### 7.24.2.4 optixAccelEmitProperty

`OptixResult`(\* `OptixFunctionTable::optixAccelEmitProperty`) (`OptixDeviceContext` `context`, `CUstream` `stream`, `OptixTraversableHandle` `handle`, const `OptixAccelEmitDesc` `*emittedProperty`)

See `optixAccelComputeMemoryUsage()`.

#### 7.24.2.5 optixAccelGetRelocationInfo

`OptixResult`(\* `OptixFunctionTable::optixAccelGetRelocationInfo`) (`OptixDeviceContext` `context`, `OptixTraversableHandle` `handle`, `OptixRelocationInfo` `*info`)

See `optixAccelGetRelocationInfo()`.

#### 7.24.2.6 optixAccelRelocate

`OptixResult`(\* `OptixFunctionTable::optixAccelRelocate`) (`OptixDeviceContext` `context`, `CUstream` `stream`, const `OptixRelocationInfo` `*info`, const `OptixRelocateInput` `*relocateInputs`, `size_t` `numRelocateInputs`, `CUdeviceptr` `targetAccel`, `size_t` `targetAccelSizeInBytes`, `OptixTraversableHandle` `*targetHandle`)

See `optixAccelRelocate()`.

#### 7.24.2.7 optixBuiltinISModuleGet

`OptixResult`(\* `OptixFunctionTable::optixBuiltinISModuleGet`) (`OptixDeviceContext` `context`, const `OptixModuleCompileOptions` `*moduleCompileOptions`, const `OptixPipelineCompileOptions` `*pipelineCompileOptions`, const `OptixBuiltinISOptions` `*builtinISOptions`, `OptixModule` `*builtinModule`)

See `optixBuiltinISModuleGet()`.

#### 7.24.2.8 `optixCheckRelocationCompatibility`

```
OptixResult(* OptixFunctionTable::optixCheckRelocationCompatibility)
(OptixDeviceContext context, const OptixRelocationInfo *info, int
*compatible)
```

See `optixCheckRelocationCompatibility()`.

#### 7.24.2.9 `optixConvertPointerToTraversableHandle`

```
OptixResult(* OptixFunctionTable::optixConvertPointerToTraversableHandle)
(OptixDeviceContext onDevice, CUdeviceptr pointer, OptixTraversableType
traversableType, OptixTraversableHandle *traversableHandle)
```

See `optixConvertPointerToTraversableHandle()`.

#### 7.24.2.10 `optixDenoiserComputeAverageColor`

```
OptixResult(* OptixFunctionTable::optixDenoiserComputeAverageColor)
(OptixDenoiser handle, CUstream stream, const OptixImage2D *inputImage,
CUdeviceptr outputAverageColor, CUdeviceptr scratch, size_t
scratchSizeInBytes)
```

See `optixDenoiserComputeAverageColor()`.

#### 7.24.2.11 `optixDenoiserComputeIntensity`

```
OptixResult(* OptixFunctionTable::optixDenoiserComputeIntensity)
(OptixDenoiser handle, CUstream stream, const OptixImage2D *inputImage,
CUdeviceptr outputIntensity, CUdeviceptr scratch, size_t scratchSizeInBytes)
```

See `optixDenoiserComputeIntensity()`.

#### 7.24.2.12 `optixDenoiserComputeMemoryResources`

```
OptixResult(* OptixFunctionTable::optixDenoiserComputeMemoryResources)
(const OptixDenoiser handle, unsigned int maximumInputWidth, unsigned int
maximumInputHeight, OptixDenoiserSizes *returnSizes)
```

See `optixDenoiserComputeMemoryResources()`.

#### 7.24.2.13 `optixDenoiserCreate`

```
OptixResult(* OptixFunctionTable::optixDenoiserCreate) (OptixDeviceContext
context, OptixDenoiserModelKind modelKind, const OptixDenoiserOptions
*options, OptixDenoiser *returnHandle)
```

See `optixDenoiserCreate()`.

#### 7.24.2.14 `optixDenoiserCreateWithUserModel`

```
OptixResult(* OptixFunctionTable::optixDenoiserCreateWithUserModel)
(OptixDeviceContext context, const void *data, size_t dataSizeInBytes,
OptixDenoiser *returnHandle)
```

See `optixDenoiserCreateWithUserModel()`.

### 7.24.2.15 optixDenoiserDestroy

`OptixResult(* OptixFunctionTable::optixDenoiserDestroy) (OptixDenoiser handle)`

See `optixDenoiserDestroy()`.

### 7.24.2.16 optixDenoiserInvoke

`OptixResult(* OptixFunctionTable::optixDenoiserInvoke) (OptixDenoiser denoiser, CUstream stream, const OptixDenoiserParams *params, CUdeviceptr denoiserState, size_t denoiserStateSizeInBytes, const OptixDenoiserGuideLayer *guideLayer, const OptixDenoiserLayer *layers, unsigned int numLayers, unsigned int inputOffsetX, unsigned int inputOffsetY, CUdeviceptr scratch, size_t scratchSizeInBytes)`

See `optixDenoiserInvoke()`.

### 7.24.2.17 optixDenoiserSetup

`OptixResult(* OptixFunctionTable::optixDenoiserSetup) (OptixDenoiser denoiser, CUstream stream, unsigned int inputWidth, unsigned int inputHeight, CUdeviceptr state, size_t stateSizeInBytes, CUdeviceptr scratch, size_t scratchSizeInBytes)`

See `optixDenoiserSetup()`.

### 7.24.2.18 optixDeviceContextCreate

`OptixResult(* OptixFunctionTable::optixDeviceContextCreate) (CUcontext fromContext, const OptixDeviceContextOptions *options, OptixDeviceContext *context)`

See `optixDeviceContextCreate()`.

### 7.24.2.19 optixDeviceContextDestroy

`OptixResult(* OptixFunctionTable::optixDeviceContextDestroy) (OptixDeviceContext context)`

See `optixDeviceContextDestroy()`.

### 7.24.2.20 optixDeviceContextGetCacheDatabaseSizes

`OptixResult(* OptixFunctionTable::optixDeviceContextGetCacheDatabaseSizes) (OptixDeviceContext context, size_t *lowWaterMark, size_t *highWaterMark)`

See `optixDeviceContextGetCacheDatabaseSizes()`.

### 7.24.2.21 optixDeviceContextGetCacheEnabled

`OptixResult(* OptixFunctionTable::optixDeviceContextGetCacheEnabled) (OptixDeviceContext context, int *enabled)`

See `optixDeviceContextGetCacheEnabled()`.

### 7.24.2.22 optixDeviceContextGetCacheLocation

`OptixResult(* OptixFunctionTable::optixDeviceContextGetCacheLocation)`



(`OptixDeviceContext` context, `char *location`, `size_t locationSize`)

See `optixDeviceContextGetCacheLocation()`.

#### 7.24.2.23 `optixDeviceContextGetProperty`

`OptixResult`(\* `OptixFunctionTable::optixDeviceContextGetProperty`)  
(`OptixDeviceContext` context, `OptixDeviceProperty` property, `void *value`, `size_t sizeInBytes`)

See `optixDeviceContextGetProperty()`.

#### 7.24.2.24 `optixDeviceContextSetCacheDatabaseSizes`

`OptixResult`(\* `OptixFunctionTable::optixDeviceContextSetCacheDatabaseSizes`)  
(`OptixDeviceContext` context, `size_t lowWaterMark`, `size_t highWaterMark`)

See `optixDeviceContextSetCacheDatabaseSizes()`.

#### 7.24.2.25 `optixDeviceContextSetCacheEnabled`

`OptixResult`(\* `OptixFunctionTable::optixDeviceContextSetCacheEnabled`)  
(`OptixDeviceContext` context, `int enabled`)

See `optixDeviceContextSetCacheEnabled()`.

#### 7.24.2.26 `optixDeviceContextSetCacheLocation`

`OptixResult`(\* `OptixFunctionTable::optixDeviceContextSetCacheLocation`)  
(`OptixDeviceContext` context, `const char *location`)

See `optixDeviceContextSetCacheLocation()`.

#### 7.24.2.27 `optixDeviceContextSetLogCallback`

`OptixResult`(\* `OptixFunctionTable::optixDeviceContextSetLogCallback`)  
(`OptixDeviceContext` context, `OptixLogCallback` callbackFunction, `void *callbackData`, `unsigned int callbackLevel`)

See `optixDeviceContextSetLogCallback()`.

#### 7.24.2.28 `optixDisplacementMicromapArrayBuild`

`OptixResult`(\* `OptixFunctionTable::optixDisplacementMicromapArrayBuild`)  
(`OptixDeviceContext` context, `CUstream` stream, `const OptixDisplacementMicromapArrayBuildInput *buildInput`, `const OptixMicromapBuffers *buffers`)

See `optixDisplacementMicromapArrayBuild()`.

#### 7.24.2.29 `optixDisplacementMicromapArrayComputeMemoryUsage`

`OptixResult`(\* `OptixFunctionTable::optixDisplacementMicromapArrayComputeMemoryUsage`) (`OptixDeviceContext` context, `const OptixDisplacementMicromapArrayBuildInput *buildInput`, `OptixMicromapBufferSizes *bufferSizes`)

See `optixDisplacementMicromapArrayComputeMemoryUsage()`.

### 7.24.2.30 optixGetErrorName

`const char *(* OptixFunctionTable::optixGetErrorName) (OptixResult result)`

See `optixGetErrorName()`.

### 7.24.2.31 optixGetErrorString

`const char *(* OptixFunctionTable::optixGetErrorString) (OptixResult result)`

See `optixGetErrorString()`.

### 7.24.2.32 optixLaunch

`OptixResult(* OptixFunctionTable::optixLaunch) (OptixPipeline pipeline, CUstream stream, CUdeviceptr pipelineParams, size_t pipelineParamsSize, const OptixShaderBindingTable *sbt, unsigned int width, unsigned int height, unsigned int depth)`

See `optixConvertPointerToTraversableHandle()`.

### 7.24.2.33 optixModuleCreate

`OptixResult(* OptixFunctionTable::optixModuleCreate) (OptixDeviceContext context, const OptixModuleCompileOptions *moduleCompileOptions, const OptixPipelineCompileOptions *pipelineCompileOptions, const char *input, size_t inputSize, char *logString, size_t *logStringSize, OptixModule *module)`

See `optixModuleCreate()`.

### 7.24.2.34 optixModuleCreateWithTasks

`OptixResult(* OptixFunctionTable::optixModuleCreateWithTasks) (OptixDeviceContext context, const OptixModuleCompileOptions *moduleCompileOptions, const OptixPipelineCompileOptions *pipelineCompileOptions, const char *input, size_t inputSize, char *logString, size_t *logStringSize, OptixModule *module, OptixTask *firstTask)`

See `optixModuleCreateWithTasks()`.

### 7.24.2.35 optixModuleDestroy

`OptixResult(* OptixFunctionTable::optixModuleDestroy) (OptixModule module)`

See `optixModuleDestroy()`.

### 7.24.2.36 optixModuleGetCompilationState

`OptixResult(* OptixFunctionTable::optixModuleGetCompilationState) (OptixModule module, OptixModuleCompileState *state)`

See `optixModuleGetCompilationState()`.

### 7.24.2.37 optixOpacityMicromapArrayBuild

`OptixResult(* OptixFunctionTable::optixOpacityMicromapArrayBuild) (OptixDeviceContext context, CUstream stream, const OptixOpacityMicromapArrayBuildInput *buildInput, const OptixMicromapBuffers`



\*buffers)

See `optixOpacityMicromapArrayBuild()`.

#### 7.24.2.38 `optixOpacityMicromapArrayComputeMemoryUsage`

```
OptixResult(* OptixFunctionTable
::optixOpacityMicromapArrayComputeMemoryUsage) (OptixDeviceContext context,
const OptixOpacityMicromapArrayBuildInput *buildInput,
OptixMicromapBufferSizes *bufferSizes)
```

See `optixOpacityMicromapArrayComputeMemoryUsage()`.

#### 7.24.2.39 `optixOpacityMicromapArrayGetRelocationInfo`

```
OptixResult(* OptixFunctionTable
::optixOpacityMicromapArrayGetRelocationInfo) (OptixDeviceContext context,
CUdeviceptr opacityMicromapArray, OptixRelocationInfo *info)
```

See `optixOpacityMicromapArrayGetRelocationInfo()`.

#### 7.24.2.40 `optixOpacityMicromapArrayRelocate`

```
OptixResult(* OptixFunctionTable::optixOpacityMicromapArrayRelocate)
(OptixDeviceContext context, CUstream stream, const OptixRelocationInfo
*info, CUdeviceptr targetOpacityMicromapArray, size_t
targetOpacityMicromapArraySizeInBytes)
```

See `optixOpacityMicromapArrayRelocate()`.

#### 7.24.2.41 `optixPipelineCreate`

```
OptixResult(* OptixFunctionTable::optixPipelineCreate) (OptixDeviceContext
context, const OptixPipelineCompileOptions *pipelineCompileOptions, const
OptixPipelineLinkOptions *pipelineLinkOptions, const OptixProgramGroup
*programGroups, unsigned int numProgramGroups, char *logString, size_t
*logStringSize, OptixPipeline *pipeline)
```

See `optixPipelineCreate()`.

#### 7.24.2.42 `optixPipelineDestroy`

```
OptixResult(* OptixFunctionTable::optixPipelineDestroy) (OptixPipeline
pipeline)
```

See `optixPipelineDestroy()`.

#### 7.24.2.43 `optixPipelineSetStackSize`

```
OptixResult(* OptixFunctionTable::optixPipelineSetStackSize) (OptixPipeline
pipeline, unsigned int directCallableStackSizeFromTraversal, unsigned int
directCallableStackSizeFromState, unsigned int continuationStackSize,
unsigned int maxTraversableGraphDepth)
```

See `optixPipelineSetStackSize()`.

#### 7.24.2.44 `optixProgramGroupCreate`

```
OptixResult(* OptixFunctionTable::optixProgramGroupCreate)
```

```
(OptixDeviceContext context, const OptixProgramGroupDesc
*programDescriptions, unsigned int numProgramGroups, const
OptixProgramGroupOptions *options, char *logString, size_t *logStringSize,
OptixProgramGroup *programGroups)
```

See [optixProgramGroupCreate\(\)](#).

#### 7.24.2.45 optixProgramGroupDestroy

```
OptixResult(* OptixFunctionTable::optixProgramGroupDestroy)
(OptixProgramGroup programGroup)
```

See [optixProgramGroupDestroy\(\)](#).

#### 7.24.2.46 optixProgramGroupGetStackSize

```
OptixResult(* OptixFunctionTable::optixProgramGroupGetStackSize)
(OptixProgramGroup programGroup, OptixStackSizes *stackSizes, OptixPipeline
pipeline)
```

See [optixProgramGroupGetStackSize\(\)](#).

#### 7.24.2.47 optixSbtRecordPackHeader

```
OptixResult(* OptixFunctionTable::optixSbtRecordPackHeader)
(OptixProgramGroup programGroup, void *sbtRecordHeaderHostPointer)
```

See [optixConvertPointerToTraversableHandle\(\)](#).

#### 7.24.2.48 optixTaskExecute

```
OptixResult(* OptixFunctionTable::optixTaskExecute) (OptixTask task,
OptixTask *additionalTasks, unsigned int maxNumAdditionalTasks, unsigned int
*numAdditionalTasksCreated)
```

See [optixTaskExecute\(\)](#).

### 7.25 OptixImage2D Struct Reference

```
#include <optix_types.h>
```

#### Public Attributes

- [CUdeviceptr](#) data
- unsigned int width
- unsigned int height
- unsigned int rowStrideInBytes
- unsigned int pixelStrideInBytes
- [OptixPixelFormat](#) format

#### 7.25.1 Detailed Description

Image descriptor used by the denoiser.

See also [optixDenoiserInvoke\(\)](#), [optixDenoiserComputeIntensity\(\)](#)

## 7.25.2 Member Data Documentation

### 7.25.2.1 data

`CUdeviceptr` `OptixImage2D::data`

Pointer to the actual pixel data.

### 7.25.2.2 format

`OptixPixelFormat` `OptixImage2D::format`

Pixel format.

### 7.25.2.3 height

`unsigned int` `OptixImage2D::height`

Height of the image (in pixels)

### 7.25.2.4 pixelStrideInBytes

`unsigned int` `OptixImage2D::pixelStrideInBytes`

Stride between subsequent pixels of the image (in bytes). If set to 0, dense packing (no gaps) is assumed. For pixel format `OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER` it must be set to `OptixDenoiserSizes::internalGuideLayerPixelSizeInBytes`.

### 7.25.2.5 rowStrideInBytes

`unsigned int` `OptixImage2D::rowStrideInBytes`

Stride between subsequent rows of the image (in bytes).

### 7.25.2.6 width

`unsigned int` `OptixImage2D::width`

Width of the image (in pixels)

## 7.26 OptixInstance Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `float` `transform` [12]
- `unsigned int` `instanceId`
- `unsigned int` `sbtOffset`
- `unsigned int` `visibilityMask`
- `unsigned int` `flags`
- `OptixTraversableHandle` `traversableHandle`
- `unsigned int` `pad` [2]

### 7.26.1 Detailed Description

Instances.

See also `OptixBuildInputInstanceArray::instances`

## 7.26.2 Member Data Documentation

### 7.26.2.1 flags

`unsigned int OptixInstance::flags`

Any combination of `OptixInstanceFlags` is allowed.

### 7.26.2.2 instanceId

`unsigned int OptixInstance::instanceId`

Application supplied ID. The maximal ID can be queried using `OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCE_ID`.

### 7.26.2.3 pad

`unsigned int OptixInstance::pad[2]`

round up to 80-byte, to ensure 16-byte alignment

### 7.26.2.4 sbtOffset

`unsigned int OptixInstance::sbtOffset`

SBT record offset. In a traversable graph with multiple levels of instance acceleration structure (IAS) objects, offsets are summed together. The maximal SBT offset can be queried using `OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_OFFSET`.

### 7.26.2.5 transform

`float OptixInstance::transform[12]`

affine object-to-world transformation as 3x4 matrix in row-major layout

### 7.26.2.6 traversableHandle

`OptixTraversableHandle OptixInstance::traversableHandle`

Set with an `OptixTraversableHandle`.

### 7.26.2.7 visibilityMask

`unsigned int OptixInstance::visibilityMask`

Visibility mask. If `rayMask & instanceMask == 0` the instance is culled. The number of available bits can be queried using `OPTIX_DEVICE_PROPERTY_LIMIT_NUM_BITS_INSTANCE_VISIBILITY_MASK`.

## 7.27 OptixMatrixMotionTransform Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `OptixTraversableHandle child`
- `OptixMotionOptions motionOptions`
- `unsigned int pad [3]`
- `float transform [2][12]`

### 7.27.1 Detailed Description

Represents a matrix motion transformation.

The device address of instances of this type must be a multiple of `OPTIX_TRANSFORM_BYTE_ALIGNMENT`.

This struct, as defined here, handles only N=2 motion keys due to the fixed array length of its transform member. The following example shows how to create instances for an arbitrary number N of motion keys:

```
float matrixData[N][12];
... // setup matrixData
size_t transformSizeInBytes = sizeof(OptixMatrixMotionTransform) + (N-2) * 12 * sizeof(float);
OptixMatrixMotionTransform* matrixMoptionTransform = (OptixMatrixMotionTransform*)
malloc(transformSizeInBytes);
memset(matrixMoptionTransform, 0, transformSizeInBytes);
... // setup other members of matrixMoptionTransform
matrixMoptionTransform->motionOptions.numKeys
memcpy(matrixMoptionTransform->transform, matrixData, N * 12 * sizeof(float));
... // copy matrixMoptionTransform to device memory
free(matrixMoptionTransform)
```

See also `optixConvertPointerToTraversableHandle()`

### 7.27.2 Member Data Documentation

#### 7.27.2.1 child

`OptixTraversableHandle` `OptixMatrixMotionTransform::child`

The traversable that is transformed by this transformation.

#### 7.27.2.2 motionOptions

`OptixMotionOptions` `OptixMatrixMotionTransform::motionOptions`

The motion options for this transformation. Must have at least two motion keys.

#### 7.27.2.3 pad

`unsigned int` `OptixMatrixMotionTransform::pad[3]`

Padding to make the transformation 16 byte aligned.

#### 7.27.2.4 transform

`float` `OptixMatrixMotionTransform::transform[2][12]`

Affine object-to-world transformation as 3x4 matrix in row-major layout.

## 7.28 OptixMicromapBuffers Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `CUdeviceptr` output
- `size_t` outputSizeInBytes
- `CUdeviceptr` temp
- `size_t` tempSizeInBytes

### 7.28.1 Detailed Description

Buffer inputs for opacity/displacement micromap array builds.

### 7.28.2 Member Data Documentation

#### 7.28.2.1 output

`CUdeviceptr` `OptixMicromapBuffers::output`

Output buffer.

#### 7.28.2.2 outputSizeInBytes

`size_t` `OptixMicromapBuffers::outputSizeInBytes`

Output buffer size.

#### 7.28.2.3 temp

`CUdeviceptr` `OptixMicromapBuffers::temp`

Temp buffer.

#### 7.28.2.4 tempSizeInBytes

`size_t` `OptixMicromapBuffers::tempSizeInBytes`

Temp buffer size.

## 7.29 OptixMicromapBufferSizes Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `size_t` `outputSizeInBytes`
- `size_t` `tempSizeInBytes`

### 7.29.1 Detailed Description

Conservative memory requirements for building a opacity/displacement micromap array.

### 7.29.2 Member Data Documentation

#### 7.29.2.1 outputSizeInBytes

`size_t` `OptixMicromapBufferSizes::outputSizeInBytes`

#### 7.29.2.2 tempSizeInBytes

`size_t` `OptixMicromapBufferSizes::tempSizeInBytes`

## 7.30 OptixModuleCompileBoundValueEntry Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `size_t` `pipelineParamOffsetInBytes`

- `size_t` `sizeInBytes`
- `const void *` `boundValuePtr`
- `const char *` `annotation`

### 7.30.1 Detailed Description

Struct for specifying specializations for pipelineParams as specified in [OptixPipelineCompileOptions::pipelineLaunchParamsVariableName](#).

The bound values are supposed to represent a constant value in the pipelineParams. OptiX will attempt to locate all loads from the pipelineParams and correlate them to the appropriate bound value, but there are cases where OptiX cannot safely or reliably do this. For example if the pointer to the pipelineParams is passed as an argument to a non-inline function or the offset of the load to the pipelineParams cannot be statically determined (e.g. accessed in a loop). No module should rely on the value being specialized in order to work correctly. The values in the pipelineParams specified on `optixLaunch` should match the bound value. If validation mode is enabled on the context, OptiX will verify that the bound values specified matches the values in pipelineParams specified to `optixLaunch`.

These values are compiled in to the module as constants. Once the constants are inserted into the code, an optimization pass will be run that will attempt to propagate the constants and remove unreachable code.

If caching is enabled, changes in these values will result in newly compiled modules.

The `pipelineParamOffset` and `sizeInBytes` must be within the bounds of the pipelineParams variable. `OPTIX_ERROR_INVALID_VALUE` will be returned from `optixModuleCreate` otherwise.

If more than one bound value overlaps or the size of a bound value is equal to 0, an `OPTIX_ERROR_INVALID_VALUE` will be returned from `optixModuleCreate`.

The same set of bound values do not need to be used for all modules in a pipeline, but overlapping values between modules must have the same value. `OPTIX_ERROR_INVALID_VALUE` will be returned from `optixPipelineCreate` otherwise.

See also [OptixModuleCompileOptions](#)

### 7.30.2 Member Data Documentation

#### 7.30.2.1 annotation

```
const char* OptixModuleCompileBoundValueEntry::annotation
```

#### 7.30.2.2 boundValuePtr

```
const void* OptixModuleCompileBoundValueEntry::boundValuePtr
```

#### 7.30.2.3 pipelineParamOffsetInBytes

```
size_t OptixModuleCompileBoundValueEntry::pipelineParamOffsetInBytes
```

#### 7.30.2.4 sizeInBytes

```
size_t OptixModuleCompileBoundValueEntry::sizeInBytes
```

## 7.31 OptixModuleCompileOptions Struct Reference

```
#include <optix_types.h>
```

## Public Attributes

- `int maxRegisterCount`
- `OptixCompileOptimizationLevel optLevel`
- `OptixCompileDebugLevel debugLevel`
- `const OptixModuleCompileBoundValueEntry * boundValues`
- `unsigned int numBoundValues`
- `unsigned int numPayloadTypes`
- `const OptixPayloadType * payloadTypes`

### 7.31.1 Detailed Description

Compilation options for module.

See also `optixModuleCreate()`

### 7.31.2 Member Data Documentation

#### 7.31.2.1 boundValues

`const OptixModuleCompileBoundValueEntry* OptixModuleCompileOptions::boundValues`

Ingored if numBoundValues is set to 0.

#### 7.31.2.2 debugLevel

`OptixCompileDebugLevel OptixModuleCompileOptions::debugLevel`

Generate debug information.

#### 7.31.2.3 maxRegisterCount

`int OptixModuleCompileOptions::maxRegisterCount`

Maximum number of registers allowed when compiling to SASS. Set to 0 for no explicit limit. May vary within a pipeline.

#### 7.31.2.4 numBoundValues

`unsigned int OptixModuleCompileOptions::numBoundValues`

set to 0 if unused

#### 7.31.2.5 numPayloadTypes

`unsigned int OptixModuleCompileOptions::numPayloadTypes`

The number of different payload types available for compilation. Must be zero if `OptixPipelineCompileOptions::numPayloadValues` is not zero.

#### 7.31.2.6 optLevel

`OptixCompileOptimizationLevel OptixModuleCompileOptions::optLevel`

Optimization level. May vary within a pipeline.

#### 7.31.2.7 payloadTypes

`const OptixPayloadType* OptixModuleCompileOptions::payloadTypes`



Points to host array of payload type definitions, size must match numPayloadTypes.

## 7.32 OptixMotionOptions Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned short [numKeys](#)
- unsigned short [flags](#)
- float [timeBegin](#)
- float [timeEnd](#)

### 7.32.1 Detailed Description

Motion options.

See also [OptixAccelBuildOptions::motionOptions](#), [OptixMatrixMotionTransform::motionOptions](#), [OptixSRTMotionTransform::motionOptions](#)

### 7.32.2 Member Data Documentation

#### 7.32.2.1 flags

unsigned short [OptixMotionOptions::flags](#)

Combinations of [OptixMotionFlags](#).

#### 7.32.2.2 numKeys

unsigned short [OptixMotionOptions::numKeys](#)

If numKeys > 1, motion is enabled. timeBegin, timeEnd and flags are all ignored when motion is disabled.

#### 7.32.2.3 timeBegin

float [OptixMotionOptions::timeBegin](#)

Point in time where motion starts. Must be lesser than timeEnd.

#### 7.32.2.4 timeEnd

float [OptixMotionOptions::timeEnd](#)

Point in time where motion ends. Must be greater than timeBegin.

## 7.33 OptixOpacityMicromapArrayBuildInput Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int [flags](#)
- CUdeviceptr [inputBuffer](#)
- CUdeviceptr [perMicromapDescBuffer](#)
- unsigned int [perMicromapDescStrideInBytes](#)
- unsigned int [numMicromapHistogramEntries](#)
- const [OptixOpacityMicromapHistogramEntry](#) \* [micromapHistogramEntries](#)

### 7.33.1 Detailed Description

Inputs to opacity micromap array construction.

### 7.33.2 Member Data Documentation

#### 7.33.2.1 flags

`unsigned int OptixOpacityMicromapArrayBuildInput::flags`

Applies to all opacity micromaps in array.

#### 7.33.2.2 inputBuffer

`CUdeviceptr OptixOpacityMicromapArrayBuildInput::inputBuffer`

128B aligned base pointer for raw opacity micromap input data.

#### 7.33.2.3 micromapHistogramEntries

`const OptixOpacityMicromapHistogramEntry*  
OptixOpacityMicromapArrayBuildInput::micromapHistogramEntries`

Histogram over opacity micromaps of input format and subdivision combinations. Counts of entries with equal format and subdivision combination (duplicates) are added together.

#### 7.33.2.4 numMicromapHistogramEntries

`unsigned int OptixOpacityMicromapArrayBuildInput  
::numMicromapHistogramEntries`

Number of `OptixOpacityMicromapHistogramEntry`.

#### 7.33.2.5 perMicromapDescBuffer

`CUdeviceptr OptixOpacityMicromapArrayBuildInput::perMicromapDescBuffer`

One `OptixOpacityMicromapDesc` entry per opacity micromap. This device pointer must be a multiple of `OPTIX_OPACITY_MICROMAP_DESC_BYTE_ALIGNMENT`.

#### 7.33.2.6 perMicromapDescStrideInBytes

`unsigned int OptixOpacityMicromapArrayBuildInput  
::perMicromapDescStrideInBytes`

Stride between `OptixOpacityMicromapDescs` in `perOmDescBuffer`. If set to zero, the opacity micromap descriptors are assumed to be tightly packed and the stride is assumed to be `sizeof(OptixOpacityMicromapDesc)`. This stride must be a multiple of `OPTIX_OPACITY_MICROMAP_DESC_BYTE_ALIGNMENT`.

## 7.34 OptixOpacityMicromapDesc Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `unsigned int byteOffset`
- `unsigned short subdivisionLevel`
- `unsigned short format`

### 7.34.1 Detailed Description

Opacity micromap descriptor.

### 7.34.2 Member Data Documentation

#### 7.34.2.1 byteOffset

`unsigned int OptixOpacityMicromapDesc::byteOffset`

Byte offset to opacity micromap in data input buffer of opacity micromap array build.

#### 7.34.2.2 format

`unsigned short OptixOpacityMicromapDesc::format`

`OptixOpacityMicromapFormat`.

#### 7.34.2.3 subdivisionLevel

`unsigned short OptixOpacityMicromapDesc::subdivisionLevel`

Number of micro-triangles is  $4^{\text{level}}$ . Valid levels are [0, 12].

## 7.35 OptixOpacityMicromapHistogramEntry Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `unsigned int count`
- `unsigned int subdivisionLevel`
- `OptixOpacityMicromapFormat format`

### 7.35.1 Detailed Description

Opacity micromap histogram entry. Specifies how many opacity micromaps of a specific type are input to the opacity micromap array build. Note that while this is similar to [OptixOpacityMicromapUsageCount](#), the histogram entry specifies how many opacity micromaps of a specific type are combined into a opacity micromap array.

### 7.35.2 Member Data Documentation

#### 7.35.2.1 count

`unsigned int OptixOpacityMicromapHistogramEntry::count`

Number of opacity micromaps with the format and subdivision level that are input to the opacity micromap array build.

#### 7.35.2.2 format

`OptixOpacityMicromapFormat OptixOpacityMicromapHistogramEntry::format`

Opacity micromap format.

#### 7.35.2.3 subdivisionLevel

`unsigned int OptixOpacityMicromapHistogramEntry::subdivisionLevel`

Number of micro-triangles is  $4^{\text{level}}$ . Valid levels are [0, 12].

## 7.36 OptixOpacityMicromapUsageCount Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int `count`
- unsigned int `subdivisionLevel`
- `OptixOpacityMicromapFormat` `format`

### 7.36.1 Detailed Description

Opacity micromap usage count for acceleration structure builds. Specifies how many opacity micromaps of a specific type are referenced by triangles when building the AS. Note that while this is similar to `OptixOpacityMicromapHistogramEntry`, the usage count specifies how many opacity micromaps of a specific type are referenced by triangles in the AS.

### 7.36.2 Member Data Documentation

#### 7.36.2.1 `count`

```
unsigned int OptixOpacityMicromapUsageCount::count
```

Number of opacity micromaps with this format and subdivision level referenced by triangles in the corresponding triangle build input at AS build time.

#### 7.36.2.2 `format`

```
OptixOpacityMicromapFormat OptixOpacityMicromapUsageCount::format
```

opacity micromap format.

#### 7.36.2.3 `subdivisionLevel`

```
unsigned int OptixOpacityMicromapUsageCount::subdivisionLevel
```

Number of micro-triangles is  $4^{\text{level}}$ . Valid levels are [0, 12].

## 7.37 OptixPayloadType Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int `numPayloadValues`
- const unsigned int \* `payloadSemantics`

### 7.37.1 Detailed Description

Specifies a single payload type.

### 7.37.2 Member Data Documentation

#### 7.37.2.1 `numPayloadValues`

```
unsigned int OptixPayloadType::numPayloadValues
```

The number of 32b words the payload of this type holds.

### 7.37.2.2 payloadSemantics

`const unsigned int* OptixPayloadType::payloadSemantics`

Points to host array of payload word semantics, size must match numPayloadValues.

## 7.38 OptixPipelineCompileOptions Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `int usesMotionBlur`
- `unsigned int traversableGraphFlags`
- `int numPayloadValues`
- `int numAttributeValues`
- `unsigned int exceptionFlags`
- `const char * pipelineLaunchParamsVariableName`
- `unsigned int usesPrimitiveTypeFlags`
- `int allowOpacityMicromaps`

### 7.38.1 Detailed Description

Compilation options for all modules of a pipeline.

Similar to `OptixModuleCompileOptions`, but these options here need to be equal for all modules of a pipeline.

See also `optixModuleCreate()`, `optixPipelineCreate()`

### 7.38.2 Member Data Documentation

#### 7.38.2.1 allowOpacityMicromaps

`int OptixPipelineCompileOptions::allowOpacityMicromaps`

Boolean value indicating whether opacity micromaps could be used.

#### 7.38.2.2 exceptionFlags

`unsigned int OptixPipelineCompileOptions::exceptionFlags`

A bitmask of `OptixExceptionFlags` indicating which exceptions are enabled.

#### 7.38.2.3 numAttributeValues

`int OptixPipelineCompileOptions::numAttributeValues`

How much storage, in 32b words, to make available for the attributes. The minimum number is 2. Values below that will automatically be changed to 2. [2..8].

#### 7.38.2.4 numPayloadValues

`int OptixPipelineCompileOptions::numPayloadValues`

How much storage, in 32b words, to make available for the payload, [0..32] Must be zero if numPayloadTypes is not zero.

### 7.38.2.5 pipelineLaunchParamsVariableName

`const char* OptixPipelineCompileOptions::pipelineLaunchParamsVariableName`

The name of the pipeline parameter variable. If 0, no pipeline parameter will be available. This will be ignored if the launch param variable was optimized out or was not found in the modules linked to the pipeline.

### 7.38.2.6 traversableGraphFlags

`unsigned int OptixPipelineCompileOptions::traversableGraphFlags`

Traversable graph bitfield. See `OptixTraversableGraphFlags`.

### 7.38.2.7 usesMotionBlur

`int OptixPipelineCompileOptions::usesMotionBlur`

Boolean value indicating whether motion blur could be used.

### 7.38.2.8 usesPrimitiveTypeFlags

`unsigned int OptixPipelineCompileOptions::usesPrimitiveTypeFlags`

Bit field enabling primitive types. See `OptixPrimitiveTypeFlags`. Setting to zero corresponds to enabling `OPTIX_PRIMITIVE_TYPE_FLAGS_CUSTOM` and `OPTIX_PRIMITIVE_TYPE_FLAGS_TRIANGLE`.

## 7.39 OptixPipelineLinkOptions Struct Reference

`#include <optix_types.h>`

### Public Attributes

- unsigned int [maxTraceDepth](#)

### 7.39.1 Detailed Description

Link options for a pipeline.

See also [optixPipelineCreate\(\)](#)

### 7.39.2 Member Data Documentation

#### 7.39.2.1 maxTraceDepth

`unsigned int OptixPipelineLinkOptions::maxTraceDepth`

Maximum trace recursion depth. 0 means a ray generation program can be launched, but can't trace any rays. The maximum allowed value is 31.

## 7.40 OptixProgramGroupCallables Struct Reference

`#include <optix_types.h>`

### Public Attributes

- [OptixModule moduleDC](#)
- `const char * entryFunctionNameDC`
- [OptixModule moduleCC](#)

- `const char * entryFunctionNameCC`

### 7.40.1 Detailed Description

Program group representing callables.

Module and entry function name need to be valid for at least one of the two callables.

See also `#OptixProgramGroupDesc::callables`

### 7.40.2 Member Data Documentation

#### 7.40.2.1 entryFunctionNameCC

`const char* OptixProgramGroupCallables::entryFunctionNameCC`

Entry function name of the continuation callable (CC) program.

#### 7.40.2.2 entryFunctionNameDC

`const char* OptixProgramGroupCallables::entryFunctionNameDC`

Entry function name of the direct callable (DC) program.

#### 7.40.2.3 moduleCC

`OptixModule OptixProgramGroupCallables::moduleCC`

Module holding the continuation callable (CC) program.

#### 7.40.2.4 moduleDC

`OptixModule OptixProgramGroupCallables::moduleDC`

Module holding the direct callable (DC) program.

## 7.41 OptixProgramGroupDesc Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `OptixProgramGroupKind kind`
- `unsigned int flags`
- `union {`
  - `OptixProgramGroupSingleModule raygen`
  - `OptixProgramGroupSingleModule miss`
  - `OptixProgramGroupSingleModule exception`
  - `OptixProgramGroupCallables callables`
  - `OptixProgramGroupHitgroup hitgroup`
- `};`

### 7.41.1 Detailed Description

Descriptor for program groups.

## 7.41.2 Member Data Documentation

### 7.41.2.1

`union { ... } OptixProgramGroupDesc::@5`

### 7.41.2.2 callables

`OptixProgramGroupCallables OptixProgramGroupDesc::callables`

See also `OPTIX_PROGRAM_GROUP_KIND_CALLABLES`

### 7.41.2.3 exception

`OptixProgramGroupSingleModule OptixProgramGroupDesc::exception`

See also `OPTIX_PROGRAM_GROUP_KIND_EXCEPTION`

### 7.41.2.4 flags

`unsigned int OptixProgramGroupDesc::flags`

See `OptixProgramGroupFlags`.

### 7.41.2.5 hitgroup

`OptixProgramGroupHitgroup OptixProgramGroupDesc::hitgroup`

See also `OPTIX_PROGRAM_GROUP_KIND_HITGROUP`

### 7.41.2.6 kind

`OptixProgramGroupKind OptixProgramGroupDesc::kind`

The kind of program group.

### 7.41.2.7 miss

`OptixProgramGroupSingleModule OptixProgramGroupDesc::miss`

See also `OPTIX_PROGRAM_GROUP_KIND_MISS`

### 7.41.2.8 raygen

`OptixProgramGroupSingleModule OptixProgramGroupDesc::raygen`

See also `OPTIX_PROGRAM_GROUP_KIND_RAYGEN`

## 7.42 OptixProgramGroupHitgroup Struct Reference

`#include <optix_types.h>`

### Public Attributes

- `OptixModule moduleCH`
- `const char * entryFunctionNameCH`
- `OptixModule moduleAH`
- `const char * entryFunctionNameAH`
- `OptixModule moduleIS`
- `const char * entryFunctionNameIS`



### 7.42.1 Detailed Description

Program group representing the hitgroup.

For each of the three program types, module and entry function name might both be `nullptr`.

See also [OptixProgramGroupDesc::hitgroup](#)

### 7.42.2 Member Data Documentation

#### 7.42.2.1 entryFunctionNameAH

```
const char* OptixProgramGroupHitgroup::entryFunctionNameAH
```

Entry function name of the any hit (AH) program.

#### 7.42.2.2 entryFunctionNameCH

```
const char* OptixProgramGroupHitgroup::entryFunctionNameCH
```

Entry function name of the closest hit (CH) program.

#### 7.42.2.3 entryFunctionNameIS

```
const char* OptixProgramGroupHitgroup::entryFunctionNameIS
```

Entry function name of the intersection (IS) program.

#### 7.42.2.4 moduleAH

```
OptixModule OptixProgramGroupHitgroup::moduleAH
```

Module holding the any hit (AH) program.

#### 7.42.2.5 moduleCH

```
OptixModule OptixProgramGroupHitgroup::moduleCH
```

Module holding the closest hit (CH) program.

#### 7.42.2.6 moduleIS

```
OptixModule OptixProgramGroupHitgroup::moduleIS
```

Module holding the intersection (IS) program.

## 7.43 OptixProgramGroupOptions Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `const OptixPayloadType * payloadType`

### 7.43.1 Detailed Description

Program group options.

See also [optixProgramGroupCreate\(\)](#)

## 7.43.2 Member Data Documentation

### 7.43.2.1 payloadType

const [OptixPayloadType](#)\* [OptixProgramGroupOptions::payloadType](#)

Specifies the payload type of this program group. All programs in the group must support the payload type (Program support for a type is specified by calling.

See also [optixSetPayloadTypes](#) or otherwise all types specified in

[OptixModuleCompileOptions](#) are supported). If a program is not available for the requested payload type, [optixProgramGroupCreate](#) returns [OPTIX\\_ERROR\\_PAYLOAD\\_TYPE\\_MISMATCH](#). If the [payloadType](#) is left zero, a unique type is deduced. The payload type can be uniquely deduced if there is exactly one payload type for which all programs in the group are available. If the payload type could not be deduced uniquely [optixProgramGroupCreate](#) returns [OPTIX\\_ERROR\\_PAYLOAD\\_TYPE\\_RESOLUTION\\_FAILED](#).

## 7.44 OptixProgramGroupSingleModule Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- [OptixModule](#) module
- const char \* [entryFunctionName](#)

### 7.44.1 Detailed Description

Program group representing a single module.

Used for raygen, miss, and exception programs. In case of raygen and exception programs, module and entry function name need to be valid. For miss programs, module and entry function name might both be nullptr.

See also [OptixProgramGroupDesc::raygen](#), [OptixProgramGroupDesc::miss](#), [OptixProgramGroupDesc::exception](#)

## 7.44.2 Member Data Documentation

### 7.44.2.1 entryFunctionName

const char\* [OptixProgramGroupSingleModule::entryFunctionName](#)

Entry function name of the single program.

### 7.44.2.2 module

[OptixModule](#) [OptixProgramGroupSingleModule::module](#)

Module holding single program.

## 7.45 OptixRelocateInput Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- [OptixBuildInputType](#) type
- union {

```

    OptixRelocateInputInstanceArray instanceArray
    OptixRelocateInputTriangleArray triangleArray
};

```

### 7.45.1 Detailed Description

Relocation inputs.

See also [optixAccelRelocate\(\)](#)

### 7.45.2 Member Data Documentation

#### 7.45.2.1

```
union { ... } OptixRelocateInput::@3
```

#### 7.45.2.2 instanceArray

[OptixRelocateInputInstanceArray](#) [OptixRelocateInput::instanceArray](#)

Instance and instance pointer inputs.

#### 7.45.2.3 triangleArray

[OptixRelocateInputTriangleArray](#) [OptixRelocateInput::triangleArray](#)

Triangle inputs.

#### 7.45.2.4 type

[OptixBuildInputType](#) [OptixRelocateInput::type](#)

The type of the build input to relocate.

## 7.46 OptixRelocateInputInstanceArray Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int [numInstances](#)
- [CUdeviceptr](#) [traversableHandles](#)

### 7.46.1 Detailed Description

Instance and instance pointer inputs.

See also [OptixRelocateInput::instanceArray](#)

### 7.46.2 Member Data Documentation

#### 7.46.2.1 numInstances

unsigned int [OptixRelocateInputInstanceArray::numInstances](#)

Number of elements in [OptixRelocateInputInstanceArray::traversableHandles](#). Must match [OptixBuildInputInstanceArray::numInstances](#) of the source build input.

### 7.46.2.2 traversableHandles

`CUdeviceptr` `OptixRelocateInputInstanceArray::traversableHandles`

These are the traversable handles of the instances (See `OptixInstance::traversableHandle`) These can be used when also relocating the instances. No updates to the bounds are performed. Use `optixAccelBuild` to update the bounds. 'traversableHandles' may be zero when the traversables are not relocated (i.e. relocation of an IAS on the source device).

## 7.47 OptixRelocateInputOpacityMicromap Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `CUdeviceptr` `opacityMicromapArray`

### 7.47.1 Member Data Documentation

#### 7.47.1.1 opacityMicromapArray

`CUdeviceptr` `OptixRelocateInputOpacityMicromap::opacityMicromapArray`

Device pointer to a relocated opacity micromap array used by the source build input array. May be zero when no micromaps were used in the source accel, or the referenced opacity micromaps don't require relocation (for example relocation of a GAS on the source device).

## 7.48 OptixRelocateInputTriangleArray Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned int `numSbtRecords`
- `OptixRelocateInputOpacityMicromap` `opacityMicromap`

### 7.48.1 Detailed Description

Triangle inputs.

See also `OptixRelocateInput::triangleArray`

### 7.48.2 Member Data Documentation

#### 7.48.2.1 numSbtRecords

unsigned int `OptixRelocateInputTriangleArray::numSbtRecords`

Number of sbt records available to the sbt index offset override. Must match `OptixBuildInputTriangleArray::numSbtRecords` of the source build input.

#### 7.48.2.2 opacityMicromap

`OptixRelocateInputOpacityMicromap` `OptixRelocateInputTriangleArray::opacityMicromap`

Opacity micromap inputs.

## 7.49 OptixRelocationInfo Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- unsigned long long [info](#) [4]

### 7.49.1 Detailed Description

Used to store information related to relocation of optix data structures.

See also [optixOpacityMicromapArrayGetRelocationInfo\(\)](#), [optixOpacityMicromapArrayRelocate\(\)](#), [optixAccelGetRelocationInfo\(\)](#), [optixAccelRelocate\(\)](#), [optixCheckRelocationCompatibility\(\)](#)

### 7.49.2 Member Data Documentation

#### 7.49.2.1 info

```
unsigned long long OptixRelocationInfo::info[4]
```

Opaque data, used internally, should not be modified.

## 7.50 OptixShaderBindingTable Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- [CUdeviceptr](#) [raygenRecord](#)
- [CUdeviceptr](#) [exceptionRecord](#)
- [CUdeviceptr](#) [missRecordBase](#)
- unsigned int [missRecordStrideInBytes](#)
- unsigned int [missRecordCount](#)
- [CUdeviceptr](#) [hitgroupRecordBase](#)
- unsigned int [hitgroupRecordStrideInBytes](#)
- unsigned int [hitgroupRecordCount](#)
- [CUdeviceptr](#) [callablesRecordBase](#)
- unsigned int [callablesRecordStrideInBytes](#)
- unsigned int [callablesRecordCount](#)

### 7.50.1 Detailed Description

Describes the shader binding table (SBT)

See also [optixLaunch\(\)](#)

### 7.50.2 Member Data Documentation

#### 7.50.2.1 callablesRecordBase

```
CUdeviceptr OptixShaderBindingTable::callablesRecordBase
```

Arrays of SBT records for callable programs. If the base address is not null, the stride and count must not be zero. If the base address is null, then the count needs to zero. The base address and the stride must be a multiple of OPTIX\_SBT\_RECORD\_ALIGNMENT.

### 7.50.2.2 callablesRecordCount

`unsigned int OptixShaderBindingTable::callablesRecordCount`

Arrays of SBT records for callable programs. If the base address is not null, the stride and count must not be zero. If the base address is null, then the count needs to zero. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.3 callablesRecordStrideInBytes

`unsigned int OptixShaderBindingTable::callablesRecordStrideInBytes`

Arrays of SBT records for callable programs. If the base address is not null, the stride and count must not be zero. If the base address is null, then the count needs to zero. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.4 exceptionRecord

`CUdeviceptr OptixShaderBindingTable::exceptionRecord`

Device address of the SBT record of the exception program. The address must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.5 hitgroupRecordBase

`CUdeviceptr OptixShaderBindingTable::hitgroupRecordBase`

Arrays of SBT records for hit groups. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.6 hitgroupRecordCount

`unsigned int OptixShaderBindingTable::hitgroupRecordCount`

Arrays of SBT records for hit groups. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.7 hitgroupRecordStrideInBytes

`unsigned int OptixShaderBindingTable::hitgroupRecordStrideInBytes`

Arrays of SBT records for hit groups. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.8 missRecordBase

`CUdeviceptr OptixShaderBindingTable::missRecordBase`

Arrays of SBT records for miss programs. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.9 missRecordCount

`unsigned int OptixShaderBindingTable::missRecordCount`

Arrays of SBT records for miss programs. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.10 missRecordStrideInBytes

`unsigned int OptixShaderBindingTable::missRecordStrideInBytes`

Arrays of SBT records for miss programs. The base address and the stride must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

### 7.50.2.11 raygenRecord

`CUdeviceptr OptixShaderBindingTable::raygenRecord`

Device address of the SBT record of the ray gen program to start launch at. The address must be a multiple of `OPTIX_SBT_RECORD_ALIGNMENT`.

## 7.51 OptixSRTData Struct Reference

`#include <optix_types.h>`

### Public Attributes

Parameters describing the SRT transformation

- `float sx`
- `float a`
- `float b`
- `float pvx`
- `float sy`
- `float c`
- `float pvy`
- `float sz`
- `float pvz`
- `float qx`
- `float qy`
- `float qz`
- `float qw`
- `float tx`
- `float ty`
- `float tz`

### 7.51.1 Detailed Description

Represents an SRT transformation.

An SRT transformation can represent a smooth rotation with fewer motion keys than a matrix transformation. Each motion key is constructed from elements taken from a matrix *S*, a quaternion *R*, and a translation *T*.

The scaling matrix  $S = \begin{bmatrix} sx & a & b & pvx \\ 0 & sy & c & pvy \\ 0 & 0 & sz & pvz \end{bmatrix}$  defines an affine transformation that can include scale,

shear, and a translation. The translation allows to define the pivot point for the subsequent rotation.

The quaternion  $R = [qx, qy, qz, qw]$  describes a rotation with angular component  $qw = \cos(\theta/2)$  and other components  $[qx, qy, qz] = \sin(\theta/2) * [ax, ay, az]$  where the axis  $[ax, ay, az]$  is normalized.

The translation matrix  $T = \begin{bmatrix} 1 & 0 & 0 & tx \\ 0 & 1 & 0 & ty \\ 0 & 0 & 1 & tz \end{bmatrix}$  defines another translation that is applied after the rotation.

Typically, this translation includes the inverse translation from the matrix  $S$  to reverse the translation for the pivot point for  $R$ .

To obtain the effective transformation at time  $t$ , the elements of the components of  $S$ ,  $R$ , and  $T$  will be interpolated linearly. The components are then multiplied to obtain the combined transformation  $C = T * R * S$ . The transformation  $C$  is the effective object-to-world transformations at time  $t$ , and  $C^{-1}$  is the effective world-to-object transformation at time  $t$ .

See also [OptixSRTMotionTransform::srtData](#), [optixConvertPointerToTraversableHandle\(\)](#)

## 7.51.2 Member Data Documentation

### 7.51.2.1 `a`

`float OptixSRTData::a`

### 7.51.2.2 `b`

`float OptixSRTData::b`

### 7.51.2.3 `c`

`float OptixSRTData::c`

### 7.51.2.4 `pvx`

`float OptixSRTData::pvx`

### 7.51.2.5 `pvy`

`float OptixSRTData::pvy`

### 7.51.2.6 `pvz`

`float OptixSRTData::pvz`

### 7.51.2.7 `qw`

`float OptixSRTData::qw`

### 7.51.2.8 `qx`

`float OptixSRTData::qx`

### 7.51.2.9 `qy`

`float OptixSRTData::qy`

### 7.51.2.10 `qz`

`float OptixSRTData::qz`

### 7.51.2.11 `sx`

`float OptixSRTData::sx`



## 7.51.2.12 sy

float OptixSRTData::sy

## 7.51.2.13 sz

float OptixSRTData::sz

## 7.51.2.14 tx

float OptixSRTData::tx

## 7.51.2.15 ty

float OptixSRTData::ty

## 7.51.2.16 tz

float OptixSRTData::tz

## 7.52 OptixSRTMotionTransform Struct Reference

```
#include <optix_types.h>
```

## Public Attributes

- [OptixTraversableHandle](#) child
- [OptixMotionOptions](#) motionOptions
- unsigned int pad [3]
- [OptixSRTData](#) srtData [2]

## 7.52.1 Detailed Description

Represents an SRT motion transformation.

The device address of instances of this type must be a multiple of OPTIX\_TRANSFORM\_BYTE\_ALIGNMENT.

This struct, as defined here, handles only N=2 motion keys due to the fixed array length of its srtData member. The following example shows how to create instances for an arbitrary number N of motion keys:

```
OptixSRTData srtData[N];
... // setup srtData
size_t transformSizeInBytes = sizeof(OptixSRTMotionTransform) + (N-2) * sizeof(OptixSRTData);
OptixSRTMotionTransform* srtMotionTransform = (OptixSRTMotionTransform*) malloc(transformSizeInBytes);
memset(srtMotionTransform, 0, transformSizeInBytes);
... // setup other members of srtMotionTransform
srtMotionTransform->motionOptions.numKeys = N;
memcpy(srtMotionTransform->srtData, srtData, N * sizeof(OptixSRTData));
... // copy srtMotionTransform to device memory
free(srtMotionTransform)
```

See also [optixConvertPointerToTraversableHandle\(\)](#)

## 7.52.2 Member Data Documentation

## 7.52.2.1 child

[OptixTraversableHandle](#) OptixSRTMotionTransform::child

The traversable transformed by this transformation.

### 7.52.2.2 motionOptions

[OptixMotionOptions](#) [OptixSRTMotionTransform::motionOptions](#)

The motion options for this transformation Must have at least two motion keys.

### 7.52.2.3 pad

`unsigned int OptixSRTMotionTransform::pad[3]`

Padding to make the SRT data 16 byte aligned.

### 7.52.2.4 srtData

[OptixSRTData](#) [OptixSRTMotionTransform::srtData\[2\]](#)

The actual SRT data describing the transformation.

## 7.53 OptixStackSizes Struct Reference

```
#include <optix_types.h>
```

### Public Attributes

- `unsigned int` [cssRG](#)
- `unsigned int` [cssMS](#)
- `unsigned int` [cssCH](#)
- `unsigned int` [cssAH](#)
- `unsigned int` [cssIS](#)
- `unsigned int` [cssCC](#)
- `unsigned int` [dssDC](#)

### 7.53.1 Detailed Description

Describes the stack size requirements of a program group.

See also [optixProgramGroupGetStackSize\(\)](#)

### 7.53.2 Member Data Documentation

#### 7.53.2.1 cssAH

`unsigned int OptixStackSizes::cssAH`

Continuation stack size of AH programs in bytes.

#### 7.53.2.2 cssCC

`unsigned int OptixStackSizes::cssCC`

Continuation stack size of CC programs in bytes.

#### 7.53.2.3 cssCH

`unsigned int OptixStackSizes::cssCH`

Continuation stack size of CH programs in bytes.

#### 7.53.2.4 cssIS

`unsigned int OptixStackSizes::cssIS`

Continuation stack size of IS programs in bytes.

#### 7.53.2.5 cssMS

`unsigned int OptixStackSizes::cssMS`

Continuation stack size of MS programs in bytes.

#### 7.53.2.6 cssRG

`unsigned int OptixStackSizes::cssRG`

Continuation stack size of RG programs in bytes.

#### 7.53.2.7 dssDC

`unsigned int OptixStackSizes::dssDC`

Direct stack size of DC programs in bytes.

### 7.54 OptixStaticTransform Struct Reference

`#include <optix_types.h>`

#### Public Attributes

- [OptixTraversableHandle](#) `child`
- `unsigned int` `pad` [2]
- `float` `transform` [12]
- `float` `invTransform` [12]

#### 7.54.1 Detailed Description

Static transform.

The device address of instances of this type must be a multiple of `OPTIX_TRANSFORM_BYTE_ALIGNMENT`.

See also [optixConvertPointerToTraversableHandle\(\)](#)

#### 7.54.2 Member Data Documentation

##### 7.54.2.1 child

[OptixTraversableHandle](#) `OptixStaticTransform::child`

The traversable transformed by this transformation.

##### 7.54.2.2 invTransform

`float` `OptixStaticTransform::invTransform`[12]

Affine world-to-object transformation as 3x4 matrix in row-major layout Must be the inverse of the transform matrix.

### 7.54.2.3 pad

`unsigned int OptixStaticTransform::pad[2]`

Padding to make the transformations 16 byte aligned.

### 7.54.2.4 transform

`float OptixStaticTransform::transform[12]`

Affine object-to-world transformation as 3x4 matrix in row-major layout.

## 7.55 OptixUtilDenoiserImageTile Struct Reference

`#include <optix_denoiser_tiling.h>`

### Public Attributes

- [OptixImage2D](#) `input`
- [OptixImage2D](#) `output`
- `unsigned int` `inputOffsetX`
- `unsigned int` `inputOffsetY`

### 7.55.1 Detailed Description

Tile definition.

see [optixUtilDenoiserSplitImage](#)

### 7.55.2 Member Data Documentation

#### 7.55.2.1 input

[OptixImage2D](#) `OptixUtilDenoiserImageTile::input`

#### 7.55.2.2 inputOffsetX

`unsigned int` `OptixUtilDenoiserImageTile::inputOffsetX`

#### 7.55.2.3 inputOffsetY

`unsigned int` `OptixUtilDenoiserImageTile::inputOffsetY`

#### 7.55.2.4 output

[OptixImage2D](#) `OptixUtilDenoiserImageTile::output`

## 7.56 optix\_internal::TypePack<... > Struct Template Reference

`#include <optix_device_impl.h>`

# 8 File Documentation

## 8.1 optix\_device\_impl.h File Reference

### Classes

- `struct` [optix\\_internal::TypePack<... >](#)

## Namespaces

- namespace [optix\\_internal](#)

## Macros

- `#define OPTIX_DEFINE_optixGetAttribute_BODY(which)`
- `#define OPTIX_DEFINE_optixGetExceptionDetail_BODY(which)`

## Functions

- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTrace (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTStride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTraverse (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTStride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTrace (OptixPayloadTypeID type, OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTStride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTraverse (OptixPayloadTypeID type, OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTStride, unsigned int missSBTIndex, Payload &... payload)`
- `static __forceinline__ __device__ void optixReorder (unsigned int coherenceHint, unsigned int numCoherenceHintBits)`
- `static __forceinline__ __device__ void optixReorder ()`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixInvoke (OptixPayloadTypeID type, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixInvoke (Payload &... payload)`
- `template<typename... RegAttributes>`  
`static __forceinline__ __device__ void optixMakeHitObject (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int sbtOffset, unsigned int sbtStride, unsigned int instIdx, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind, RegAttributes... regAttributes)`
- `template<typename... RegAttributes>`  
`static __forceinline__ __device__ void optixMakeHitObject (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int sbtOffset, unsigned int sbtStride, unsigned int instIdx, const OptixTraversableHandle *transforms, unsigned int numTransforms, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind, RegAttributes... regAttributes)`
- `template<typename... RegAttributes>`  
`static __forceinline__ __device__ void optixMakeHitObjectWithRecord (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int sbtRecordIndex, unsigned int instIdx, const OptixTraversableHandle *transforms, unsigned int`

numTransforms, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind, RegAttributes... regAttributes)

- static \_\_forceinline\_\_ \_\_device\_\_ void [optixMakeMissHitObject](#) (unsigned int missSBTIndex, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixMakeNopHitObject](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool [optixHitObjectIsHit](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool [optixHitObjectIsMiss](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool [optixHitObjectIsNop](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetInstanceId](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetInstanceIndex](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetPrimitiveIndex](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetTransformListSize](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ [OptixTraversableHandle](#) [optixHitObjectGetTransformListHandle](#) (unsigned int index)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetSbtGASIndex](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetHitKind](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 [optixHitObjectGetWorldRayOrigin](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 [optixHitObjectGetWorldRayDirection](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ float [optixHitObjectGetRayTmin](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ float [optixHitObjectGetRayTmax](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ float [optixHitObjectGetRayTime](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_0](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_1](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_2](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_3](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_4](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_5](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_6](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetAttribute\\_7](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int [optixHitObjectGetSbtRecordIndex](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ [CUdeviceptr](#) [optixHitObjectGetSbtDataPointer](#) ()
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_0](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_1](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_2](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_3](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_4](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_5](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_6](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_7](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_8](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_9](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_10](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_11](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_12](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_13](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_14](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_15](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_16](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_17](#) (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void [optixSetPayload\\_18](#) (unsigned int p)

- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_19 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_20 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_21 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_22 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_23 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_24 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_25 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_26 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_27 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_28 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_29 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_30 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayload\_31 (unsigned int p)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_0 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_1 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_2 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_3 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_4 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_5 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_6 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_7 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_8 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_9 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_10 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_11 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_12 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_13 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_14 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_15 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_16 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_17 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_18 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_19 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_20 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_21 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_22 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_23 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_24 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_25 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_26 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_27 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_28 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_29 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_30 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_31 ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayloadTypes (unsigned int types)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixUndefinedValue ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetWorldRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetWorldRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetObjectRayOrigin ()



- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetObjectRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTmin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTmax ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTime ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetRayFlags ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetRayVisibilityMask ()
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetInstanceTraversableFromIAS (OptixTraversableHandle ias, unsigned int instIdx)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetTriangleVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float3 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetMicroTriangleVertexData (float3 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetMicroTriangleBarycentricsData (float2 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetLinearCurveVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[2])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetQuadraticBSplineVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCubicBSplineVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCatmullRomVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCubicBezierVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetRibbonVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetRibbonNormal (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float2 ribbonParameters)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetSphereData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[1])
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetGASTraversableHandle ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetGASMotionTimeBegin (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetGASMotionTimeEnd (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetGASMotionStepCount (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetWorldToObjectTransformMatrix (float m[12])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetObjectToWorldTransformMatrix (float m[12])
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformPointFromWorldToObjectSpace (float3 point)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformVectorFromWorldToObjectSpace (float3 vec)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformNormalFromWorldToObjectSpace (float3 normal)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformPointFromObjectToWorldSpace (float3 point)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformVectorFromObjectToWorldSpace (float3 vec)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformNormalFromObjectToWorldSpace (float3 normal)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetTransformListSize ()



- static `__forceinline__ __device__ OptixTraversableHandle optixGetTransformListHandle` (unsigned int index)
- static `__forceinline__ __device__ OptixTransformType optixGetTransformTypeFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const OptixStaticTransform *`  
`optixGetStaticTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const OptixSRTMotionTransform *`  
`optixGetSRTMotionTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const OptixMatrixMotionTransform *`  
`optixGetMatrixMotionTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ unsigned int optixGetInstanceIdFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ OptixTraversableHandle optixGetInstanceChildFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const float4 * optixGetInstanceTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ const float4 * optixGetInstanceInverseTransformFromHandle` (OptixTraversableHandle handle)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5, unsigned int a6)
- static `__forceinline__ __device__ bool optixReportIntersection` (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5, unsigned int a6, unsigned int a7)
- static `__forceinline__ __device__ unsigned int optixGetAttribute_0` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_1` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_2` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_3` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_4` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_5` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_6` ()
- static `__forceinline__ __device__ unsigned int optixGetAttribute_7` ()
- static `__forceinline__ __device__ void optixTerminateRay` ()
- static `__forceinline__ __device__ void optixIgnoreIntersection` ()
- static `__forceinline__ __device__ unsigned int optixGetPrimitiveIndex` ()
- static `__forceinline__ __device__ unsigned int optixGetSbtGASIndex` ()
- static `__forceinline__ __device__ unsigned int optixGetInstanceId` ()

- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetInstanceIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetHitKind ()
- static \_\_forceinline\_\_ \_\_device\_\_ OptixPrimitiveType optixGetPrimitiveType (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsBackFaceHit (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsFrontFaceHit (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ OptixPrimitiveType optixGetPrimitiveType ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsBackFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsFrontFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsTriangleHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsTriangleFrontFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsTriangleBackFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsDisplacedMicromeshTriangleHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsDisplacedMicromeshTriangleFrontFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixIsDisplacedMicromeshTriangleBackFaceHit ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetCurveParameter ()
- static \_\_forceinline\_\_ \_\_device\_\_ float2 optixGetRibbonParameters ()
- static \_\_forceinline\_\_ \_\_device\_\_ float2 optixGetTriangleBarycentrics ()
- static \_\_forceinline\_\_ \_\_device\_\_ uint3 optixGetLaunchIndex ()
- static \_\_forceinline\_\_ \_\_device\_\_ uint3 optixGetLaunchDimensions ()
- static \_\_forceinline\_\_ \_\_device\_\_ CUdeviceptr optixGetSbtDataPointer ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int exceptionDetail6)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int exceptionDetail6, unsigned int exceptionDetail7)
- static \_\_forceinline\_\_ \_\_device\_\_ int optixGetExceptionCode ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_0 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_1 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_2 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_3 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_4 ()

- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int `optixGetExceptionDetail_5()`
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int `optixGetExceptionDetail_6()`
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int `optixGetExceptionDetail_7()`
- static \_\_forceinline\_\_ \_\_device\_\_ char \* `optixGetExceptionLineInfo()`
- template<typename ReturnT, typename... ArgTypes>  
static \_\_forceinline\_\_ \_\_device\_\_ ReturnT `optixDirectCall` (unsigned int sbtIndex, ArgTypes... args)
- template<typename ReturnT, typename... ArgTypes>  
static \_\_forceinline\_\_ \_\_device\_\_ ReturnT `optixContinuationCall` (unsigned int sbtIndex, ArgTypes... args)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 `optixTexFootprint2D` (unsigned long long tex, unsigned int texInfo, float x, float y, unsigned int \*singleMipLevel)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 `optixTexFootprint2DGrad` (unsigned long long tex, unsigned int texInfo, float x, float y, float dPdx\_x, float dPdx\_y, float dPdy\_x, float dPdy\_y, bool coarse, unsigned int \*singleMipLevel)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 `optixTexFootprint2DLod` (unsigned long long tex, unsigned int texInfo, float x, float y, float level, bool coarse, unsigned int \*singleMipLevel)

## 8.1.1 Detailed Description

OptiX public API.

Author

NVIDIA Corporation

OptiX public API Reference - Device side implementation

## 8.1.2 Macro Definition Documentation

### 8.1.2.1 OPTIX\_DEFINE\_optixGetAttribute\_BODY

```
#define OPTIX_DEFINE_optixGetAttribute_BODY(  
    which )
```

Value:

```
    unsigned int ret;  
    \  
    asm("call (%0), _optix_get_attribute_" #which ", ();" : "=r"(ret) :);  
    \  
    return ret;
```

### 8.1.2.2 OPTIX\_DEFINE\_optixGetExceptionDetail\_BODY

```
#define OPTIX_DEFINE_optixGetExceptionDetail_BODY(  
    which )
```

Value:

```
    unsigned int ret;  
    \  
    asm("call (%0), _optix_get_exception_detail_" #which ", ();" : "=r"(ret) :);  
    \  
    return ret;
```

### 8.1.3 Function Documentation

#### 8.1.3.1 optixContinuationCall()

```
template<typename ReturnT , typename... ArgTypes>
static __forceinline__ __device__ ReturnT optixContinuationCall (
    unsigned int sbtIndex,
    ArgTypes... args ) [static]
```

#### 8.1.3.2 optixDirectCall()

```
template<typename ReturnT , typename... ArgTypes>
static __forceinline__ __device__ ReturnT optixDirectCall (
    unsigned int sbtIndex,
    ArgTypes... args ) [static]
```

#### 8.1.3.3 optixGetAttribute\_0()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_0 ( ) [static]
```

#### 8.1.3.4 optixGetAttribute\_1()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_1 ( ) [static]
```

#### 8.1.3.5 optixGetAttribute\_2()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_2 ( ) [static]
```

#### 8.1.3.6 optixGetAttribute\_3()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_3 ( ) [static]
```

#### 8.1.3.7 optixGetAttribute\_4()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_4 ( ) [static]
```

#### 8.1.3.8 optixGetAttribute\_5()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_5 ( ) [static]
```

#### 8.1.3.9 optixGetAttribute\_6()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_6 ( ) [static]
```

#### 8.1.3.10 optixGetAttribute\_7()

```
static __forceinline__ __device__ unsigned int optixGetAttribute_7 ( ) [static]
```

#### 8.1.3.11 optixGetCatmullRomVertexData()

```
static __forceinline__ __device__ void optixGetCatmullRomVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
```

```
    unsigned int sbtGASIndex,  
    float time,  
    float4 data[4] ) [static]
```

#### 8.1.3.12 optixGetCubicBezierVertexData()

```
static __forceinline__ __device__ void optixGetCubicBezierVertexData (  
    OptixTraversableHandle gas,  
    unsigned int primIdx,  
    unsigned int sbtGASIndex,  
    float time,  
    float4 data[4] ) [static]
```

#### 8.1.3.13 optixGetCubicBSplineVertexData()

```
static __forceinline__ __device__ void optixGetCubicBSplineVertexData (  
    OptixTraversableHandle gas,  
    unsigned int primIdx,  
    unsigned int sbtGASIndex,  
    float time,  
    float4 data[4] ) [static]
```

#### 8.1.3.14 optixGetCurveParameter()

```
static __forceinline__ __device__ float optixGetCurveParameter ( ) [static]
```

#### 8.1.3.15 optixGetExceptionCode()

```
static __forceinline__ __device__ int optixGetExceptionCode ( ) [static]
```

#### 8.1.3.16 optixGetExceptionDetail\_0()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_0 ( )  
[static]
```

#### 8.1.3.17 optixGetExceptionDetail\_1()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_1 ( )  
[static]
```

#### 8.1.3.18 optixGetExceptionDetail\_2()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_2 ( )  
[static]
```

#### 8.1.3.19 optixGetExceptionDetail\_3()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_3 ( )  
[static]
```

#### 8.1.3.20 optixGetExceptionDetail\_4()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_4 ( )  
[static]
```

#### 8.1.3.21 optixGetExceptionDetail\_5()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_5 ( )  
[static]
```

#### 8.1.3.22 optixGetExceptionDetail\_6()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_6 ( )  
[static]
```

#### 8.1.3.23 optixGetExceptionDetail\_7()

```
static __forceinline__ __device__ unsigned int optixGetExceptionDetail_7 ( )  
[static]
```

#### 8.1.3.24 optixGetExceptionLineInfo()

```
static __forceinline__ __device__ char * optixGetExceptionLineInfo ( ) [static]
```

#### 8.1.3.25 optixGetGASMotionStepCount()

```
static __forceinline__ __device__ unsigned int optixGetGASMotionStepCount (   
    OptixTraversableHandle handle ) [static]
```

#### 8.1.3.26 optixGetGASMotionTimeBegin()

```
static __forceinline__ __device__ float optixGetGASMotionTimeBegin (   
    OptixTraversableHandle handle ) [static]
```

#### 8.1.3.27 optixGetGASMotionTimeEnd()

```
static __forceinline__ __device__ float optixGetGASMotionTimeEnd (   
    OptixTraversableHandle handle ) [static]
```

#### 8.1.3.28 optixGetGASTraversableHandle()

```
static __forceinline__ __device__ OptixTraversableHandle  
optixGetGASTraversableHandle ( ) [static]
```

#### 8.1.3.29 optixGetHitKind()

```
static __forceinline__ __device__ unsigned int optixGetHitKind ( ) [static]
```

#### 8.1.3.30 optixGetInstanceChildFromHandle()

```
static __forceinline__ __device__ OptixTraversableHandle  
optixGetInstanceChildFromHandle (   
    OptixTraversableHandle handle ) [static]
```

### 8.1.3.31 optixGetInstanceId()

```
static __forceinline__ __device__ unsigned int optixGetInstanceId ( ) [static]
```

### 8.1.3.32 optixGetInstanceIdFromHandle()

```
static __forceinline__ __device__ unsigned int optixGetInstanceIdFromHandle  
(  
    OptixTraversableHandle handle ) [static]
```

### 8.1.3.33 optixGetInstanceIndex()

```
static __forceinline__ __device__ unsigned int optixGetInstanceIndex ( )  
[static]
```

### 8.1.3.34 optixGetInstanceInverseTransformFromHandle()

```
static __forceinline__ __device__ const float4 *  
optixGetInstanceInverseTransformFromHandle (   
    OptixTraversableHandle handle ) [static]
```

### 8.1.3.35 optixGetInstanceTransformFromHandle()

```
static __forceinline__ __device__ const float4 *  
optixGetInstanceTransformFromHandle (   
    OptixTraversableHandle handle ) [static]
```

### 8.1.3.36 optixGetInstanceTraversableFromIAS()

```
static __forceinline__ __device__ OptixTraversableHandle  
optixGetInstanceTraversableFromIAS (   
    OptixTraversableHandle ias,  
    unsigned int instIdx ) [static]
```

### 8.1.3.37 optixGetLaunchDimensions()

```
static __forceinline__ __device__ uint3 optixGetLaunchDimensions ( ) [static]
```

### 8.1.3.38 optixGetLaunchIndex()

```
static __forceinline__ __device__ uint3 optixGetLaunchIndex ( ) [static]
```

### 8.1.3.39 optixGetLinearCurveVertexData()

```
static __forceinline__ __device__ void optixGetLinearCurveVertexData (   
    OptixTraversableHandle gas,  
    unsigned int primIdx,  
    unsigned int sbtGASIndex,  
    float time,  
    float4 data[2] ) [static]
```

## 8.1.3.40 optixGetMatrixMotionTransformFromHandle()

```
static __forceinline__ __device__ const OptixMatrixMotionTransform *
optixGetMatrixMotionTransformFromHandle (
    OptixTraversableHandle handle ) [static]
```

## 8.1.3.41 optixGetMicroTriangleBarycentricsData()

```
static __forceinline__ __device__ void optixGetMicroTriangleBarycentricsData
(
    float2 data[3] ) [static]
```

## 8.1.3.42 optixGetMicroTriangleVertexData()

```
static __forceinline__ __device__ void optixGetMicroTriangleVertexData (
    float3 data[3] ) [static]
```

## 8.1.3.43 optixGetObjectRayDirection()

```
static __forceinline__ __device__ float3 optixGetObjectRayDirection ( )
[static]
```

## 8.1.3.44 optixGetObjectRayOrigin()

```
static __forceinline__ __device__ float3 optixGetObjectRayOrigin ( ) [static]
```

## 8.1.3.45 optixGetObjectToWorldTransformMatrix()

```
static __forceinline__ __device__ void optixGetObjectToWorldTransformMatrix
(
    float m[12] ) [static]
```

## 8.1.3.46 optixGetPayload\_0()

```
static __forceinline__ __device__ unsigned int optixGetPayload_0 ( ) [static]
```

## 8.1.3.47 optixGetPayload\_1()

```
static __forceinline__ __device__ unsigned int optixGetPayload_1 ( ) [static]
```

## 8.1.3.48 optixGetPayload\_10()

```
static __forceinline__ __device__ unsigned int optixGetPayload_10 ( ) [static]
```

## 8.1.3.49 optixGetPayload\_11()

```
static __forceinline__ __device__ unsigned int optixGetPayload_11 ( ) [static]
```

## 8.1.3.50 optixGetPayload\_12()

```
static __forceinline__ __device__ unsigned int optixGetPayload_12 ( ) [static]
```

## 8.1.3.51 optixGetPayload\_13()

```
static __forceinline__ __device__ unsigned int optixGetPayload_13 ( ) [static]
```



### 8.1.3.52 optixGetPayload\_14()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_14 ( ) *[static]*

### 8.1.3.53 optixGetPayload\_15()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_15 ( ) *[static]*

### 8.1.3.54 optixGetPayload\_16()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_16 ( ) *[static]*

### 8.1.3.55 optixGetPayload\_17()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_17 ( ) *[static]*

### 8.1.3.56 optixGetPayload\_18()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_18 ( ) *[static]*

### 8.1.3.57 optixGetPayload\_19()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_19 ( ) *[static]*

### 8.1.3.58 optixGetPayload\_2()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_2 ( ) *[static]*

### 8.1.3.59 optixGetPayload\_20()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_20 ( ) *[static]*

### 8.1.3.60 optixGetPayload\_21()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_21 ( ) *[static]*

### 8.1.3.61 optixGetPayload\_22()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_22 ( ) *[static]*

### 8.1.3.62 optixGetPayload\_23()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_23 ( ) *[static]*

### 8.1.3.63 optixGetPayload\_24()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_24 ( ) *[static]*

### 8.1.3.64 optixGetPayload\_25()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_25 ( ) *[static]*

### 8.1.3.65 optixGetPayload\_26()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_26 ( ) *[static]*

### 8.1.3.66 optixGetPayload\_27()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_27 ( ) *[static]*

### 8.1.3.67 optixGetPayload\_28()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_28 ( ) *[static]*

### 8.1.3.68 optixGetPayload\_29()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_29 ( ) *[static]*

### 8.1.3.69 optixGetPayload\_3()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_3 ( ) *[static]*

### 8.1.3.70 optixGetPayload\_30()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_30 ( ) *[static]*

### 8.1.3.71 optixGetPayload\_31()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_31 ( ) *[static]*

### 8.1.3.72 optixGetPayload\_4()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_4 ( ) *[static]*

### 8.1.3.73 optixGetPayload\_5()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_5 ( ) *[static]*

### 8.1.3.74 optixGetPayload\_6()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_6 ( ) *[static]*

### 8.1.3.75 optixGetPayload\_7()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_7 ( ) *[static]*

### 8.1.3.76 optixGetPayload\_8()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_8 ( ) *[static]*

### 8.1.3.77 optixGetPayload\_9()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_9 ( ) *[static]*

### 8.1.3.78 optixGetPrimitiveIndex()

static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPrimitiveIndex ( )  
*[static]*

### 8.1.3.79 optixGetPrimitiveType() [1/2]

static \_\_forceinline\_\_ \_\_device\_\_ [OptixPrimitiveType](#) optixGetPrimitiveType ( )  
*[static]*

### 8.1.3.80 optixGetPrimitiveType() [2/2]

```
static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType (
    unsigned int hitKind ) [static]
```

### 8.1.3.81 optixGetQuadraticBSplineVertexData()

```
static __forceinline__ __device__ void optixGetQuadraticBSplineVertexData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[3] ) [static]
```

### 8.1.3.82 optixGetRayFlags()

```
static __forceinline__ __device__ unsigned int optixGetRayFlags ( ) [static]
```

### 8.1.3.83 optixGetRayTime()

```
static __forceinline__ __device__ float optixGetRayTime ( ) [static]
```

### 8.1.3.84 optixGetRayTmax()

```
static __forceinline__ __device__ float optixGetRayTmax ( ) [static]
```

### 8.1.3.85 optixGetRayTmin()

```
static __forceinline__ __device__ float optixGetRayTmin ( ) [static]
```

### 8.1.3.86 optixGetRayVisibilityMask()

```
static __forceinline__ __device__ unsigned int optixGetRayVisibilityMask ( )
[static]
```

### 8.1.3.87 optixGetRibbonNormal()

```
static __forceinline__ __device__ float3 optixGetRibbonNormal (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float2 ribbonParameters ) [static]
```

### 8.1.3.88 optixGetRibbonParameters()

```
static __forceinline__ __device__ float2 optixGetRibbonParameters ( ) [static]
```

### 8.1.3.89 optixGetRibbonVertexData()

```
static __forceinline__ __device__ void optixGetRibbonVertexData (
    OptixTraversableHandle gas,
```

```

    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[3] ) [static]

```

#### 8.1.3.90 optixGetSbtDataPointer()

```

static __forceinline__ __device__ CUdeviceptr optixGetSbtDataPointer ( )
[static]

```

#### 8.1.3.91 optixGetSbtGASIndex()

```

static __forceinline__ __device__ unsigned int optixGetSbtGASIndex ( ) [static]

```

#### 8.1.3.92 optixGetSphereData()

```

static __forceinline__ __device__ void optixGetSphereData (
    OptixTraversableHandle gas,
    unsigned int primIdx,
    unsigned int sbtGASIndex,
    float time,
    float4 data[1] ) [static]

```

#### 8.1.3.93 optixGetSRTMotionTransformFromHandle()

```

static __forceinline__ __device__ const OptixSRTMotionTransform *
optixGetSRTMotionTransformFromHandle (
    OptixTraversableHandle handle ) [static]

```

#### 8.1.3.94 optixGetStaticTransformFromHandle()

```

static __forceinline__ __device__ const OptixStaticTransform *
optixGetStaticTransformFromHandle (
    OptixTraversableHandle handle ) [static]

```

#### 8.1.3.95 optixGetTransformListHandle()

```

static __forceinline__ __device__ OptixTraversableHandle
optixGetTransformListHandle (
    unsigned int index ) [static]

```

#### 8.1.3.96 optixGetTransformListSize()

```

static __forceinline__ __device__ unsigned int optixGetTransformListSize ( )
[static]

```

#### 8.1.3.97 optixGetTransformTypeFromHandle()

```

static __forceinline__ __device__ OptixTransformType
optixGetTransformTypeFromHandle (
    OptixTraversableHandle handle ) [static]

```

### 8.1.3.98 optixGetTriangleBarycentrics()

```
static __forceinline__ __device__ float2 optixGetTriangleBarycentrics ( )  
[static]
```

### 8.1.3.99 optixGetTriangleVertexData()

```
static __forceinline__ __device__ void optixGetTriangleVertexData (   
    OptixTraversableHandle gas,  
    unsigned int primIdx,  
    unsigned int sbtGASIndex,  
    float time,  
    float3 data[3] ) [static]
```

### 8.1.3.100 optixGetWorldRayDirection()

```
static __forceinline__ __device__ float3 optixGetWorldRayDirection ( ) [static]
```

### 8.1.3.101 optixGetWorldRayOrigin()

```
static __forceinline__ __device__ float3 optixGetWorldRayOrigin ( ) [static]
```

### 8.1.3.102 optixGetWorldToObjectTransformMatrix()

```
static __forceinline__ __device__ void optixGetWorldToObjectTransformMatrix  
(  
    float m[12] ) [static]
```

### 8.1.3.103 optixHitObjectGetAttribute\_0()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_0  
( ) [static]
```

### 8.1.3.104 optixHitObjectGetAttribute\_1()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_1  
( ) [static]
```

### 8.1.3.105 optixHitObjectGetAttribute\_2()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_2  
( ) [static]
```

### 8.1.3.106 optixHitObjectGetAttribute\_3()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_3  
( ) [static]
```

### 8.1.3.107 optixHitObjectGetAttribute\_4()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_4  
( ) [static]
```

### 8.1.3.108 optixHitObjectGetAttribute\_5()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_5  
( ) [static]
```

### 8.1.3.109 optixHitObjectGetAttribute\_6()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_6  
( ) [static]
```

### 8.1.3.110 optixHitObjectGetAttribute\_7()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_7  
( ) [static]
```

### 8.1.3.111 optixHitObjectGetHitKind()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetHitKind ( )  
[static]
```

### 8.1.3.112 optixHitObjectGetInstanceId()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetInstanceId ( )  
[static]
```

### 8.1.3.113 optixHitObjectGetInstanceIndex()

```
static __forceinline__ __device__ unsigned int  
optixHitObjectGetInstanceIndex ( ) [static]
```

### 8.1.3.114 optixHitObjectGetPrimitiveIndex()

```
static __forceinline__ __device__ unsigned int  
optixHitObjectGetPrimitiveIndex ( ) [static]
```

### 8.1.3.115 optixHitObjectGetRayTime()

```
static __forceinline__ __device__ float optixHitObjectGetRayTime ( ) [static]
```

### 8.1.3.116 optixHitObjectGetRayTmax()

```
static __forceinline__ __device__ float optixHitObjectGetRayTmax ( ) [static]
```

### 8.1.3.117 optixHitObjectGetRayTmin()

```
static __forceinline__ __device__ float optixHitObjectGetRayTmin ( ) [static]
```

### 8.1.3.118 optixHitObjectGetSbtDataPointer()

```
static __forceinline__ __device__ CUdeviceptr  
optixHitObjectGetSbtDataPointer ( ) [static]
```

### 8.1.3.119 optixHitObjectGetSbtGASIndex()

```
static __forceinline__ __device__ unsigned int optixHitObjectGetSbtGASIndex  
( ) [static]
```

## 8.1.3.120 optixHitObjectGetSbtRecordIndex()

```
static __forceinline__ __device__ unsigned int
optixHitObjectGetSbtRecordIndex ( ) [static]
```

## 8.1.3.121 optixHitObjectGetTransformListHandle()

```
static __forceinline__ __device__ OptixTraversableHandle
optixHitObjectGetTransformListHandle (
    unsigned int index ) [static]
```

## 8.1.3.122 optixHitObjectGetTransformListSize()

```
static __forceinline__ __device__ unsigned int
optixHitObjectGetTransformListSize ( ) [static]
```

## 8.1.3.123 optixHitObjectGetWorldRayDirection()

```
static __forceinline__ __device__ float3 optixHitObjectGetWorldRayDirection
( ) [static]
```

## 8.1.3.124 optixHitObjectGetWorldRayOrigin()

```
static __forceinline__ __device__ float3 optixHitObjectGetWorldRayOrigin ( )
[static]
```

## 8.1.3.125 optixHitObjectIsHit()

```
static __forceinline__ __device__ bool optixHitObjectIsHit ( ) [static]
```

## 8.1.3.126 optixHitObjectIsMiss()

```
static __forceinline__ __device__ bool optixHitObjectIsMiss ( ) [static]
```

## 8.1.3.127 optixHitObjectIsNop()

```
static __forceinline__ __device__ bool optixHitObjectIsNop ( ) [static]
```

## 8.1.3.128 optixIgnoreIntersection()

```
static __forceinline__ __device__ void optixIgnoreIntersection ( ) [static]
```

## 8.1.3.129 optixInvoke() [1/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixInvoke (
    OptixPayloadTypeID type,
    Payload &... payload ) [static]
```

## 8.1.3.130 optixInvoke() [2/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixInvoke (
    Payload &... payload ) [static]
```

## 8.1.3.131 optixIsBackFaceHit() [1/2]

```
static __forceinline__ __device__ bool optixIsBackFaceHit ( ) [static]
```

## 8.1.3.132 optixIsBackFaceHit() [2/2]

```
static __forceinline__ __device__ bool optixIsBackFaceHit (
    unsigned int hitKind ) [static]
```

## 8.1.3.133 optixIsDisplacedMicromeshTriangleBackFaceHit()

```
static __forceinline__ __device__ bool
optixIsDisplacedMicromeshTriangleBackFaceHit ( ) [static]
```

## 8.1.3.134 optixIsDisplacedMicromeshTriangleFrontFaceHit()

```
static __forceinline__ __device__ bool
optixIsDisplacedMicromeshTriangleFrontFaceHit ( ) [static]
```

## 8.1.3.135 optixIsDisplacedMicromeshTriangleHit()

```
static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleHit
( ) [static]
```

## 8.1.3.136 optixIsFrontFaceHit() [1/2]

```
static __forceinline__ __device__ bool optixIsFrontFaceHit ( ) [static]
```

## 8.1.3.137 optixIsFrontFaceHit() [2/2]

```
static __forceinline__ __device__ bool optixIsFrontFaceHit (
    unsigned int hitKind ) [static]
```

## 8.1.3.138 optixIsTriangleBackFaceHit()

```
static __forceinline__ __device__ bool optixIsTriangleBackFaceHit ( ) [static]
```

## 8.1.3.139 optixIsTriangleFrontFaceHit()

```
static __forceinline__ __device__ bool optixIsTriangleFrontFaceHit ( ) [static]
```

## 8.1.3.140 optixIsTriangleHit()

```
static __forceinline__ __device__ bool optixIsTriangleHit ( ) [static]
```

## 8.1.3.141 optixMakeHitObject() [1/2]

```
template<typename... RegAttributes>
```

```
static __forceinline__ __device__ void optixMakeHitObject (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
```



```

    float rayTime,
    unsigned int sbtOffset,
    unsigned int sbtStride,
    unsigned int instIdx,
    const OptixTraversableHandle * transforms,
    unsigned int numTransforms,
    unsigned int sbtGASIdx,
    unsigned int primIdx,
    unsigned int hitKind,
    RegAttributes... regAttributes ) [static]

```

#### 8.1.3.142 optixMakeHitObject() [2/2]

```

template<typename... RegAttributes>
static __forceinline__ __device__ void optixMakeHitObject (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    unsigned int sbtOffset,
    unsigned int sbtStride,
    unsigned int instIdx,
    unsigned int sbtGASIdx,
    unsigned int primIdx,
    unsigned int hitKind,
    RegAttributes... regAttributes ) [static]

```

#### 8.1.3.143 optixMakeHitObjectWithRecord()

```

template<typename... RegAttributes>
static __forceinline__ __device__ void optixMakeHitObjectWithRecord (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    unsigned int sbtRecordIndex,
    unsigned int instIdx,
    const OptixTraversableHandle * transforms,
    unsigned int numTransforms,
    unsigned int sbtGASIdx,

```

```

    unsigned int primIdx,
    unsigned int hitKind,
    RegAttributes... regAttributes ) [static]

```

#### 8.1.3.144 optixMakeMissHitObject()

```

static __forceinline__ __device__ void optixMakeMissHitObject (
    unsigned int missSBTIndex,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime ) [static]

```

#### 8.1.3.145 optixMakeNopHitObject()

```

static __forceinline__ __device__ void optixMakeNopHitObject ( ) [static]

```

#### 8.1.3.146 optixReorder() [1/2]

```

static __forceinline__ __device__ void optixReorder ( ) [static]

```

#### 8.1.3.147 optixReorder() [2/2]

```

static __forceinline__ __device__ void optixReorder (
    unsigned int coherenceHint,
    unsigned int numCoherenceHintBits ) [static]

```

#### 8.1.3.148 optixReportIntersection() [1/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind ) [static]

```

#### 8.1.3.149 optixReportIntersection() [2/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0 ) [static]

```

#### 8.1.3.150 optixReportIntersection() [3/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1 ) [static]

```

#### 8.1.3.151 optixReportIntersection() [4/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2 ) [static]
```

#### 8.1.3.152 optixReportIntersection() [5/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3 ) [static]
```

#### 8.1.3.153 optixReportIntersection() [6/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4 ) [static]
```

#### 8.1.3.154 optixReportIntersection() [7/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4,
    unsigned int a5 ) [static]
```

#### 8.1.3.155 optixReportIntersection() [8/9]

```
static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
```

```

    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4,
    unsigned int a5,
    unsigned int a6 ) [static]

```

#### 8.1.3.156 optixReportIntersection() [9/9]

```

static __forceinline__ __device__ bool optixReportIntersection (
    float hitT,
    unsigned int hitKind,
    unsigned int a0,
    unsigned int a1,
    unsigned int a2,
    unsigned int a3,
    unsigned int a4,
    unsigned int a5,
    unsigned int a6,
    unsigned int a7 ) [static]

```

#### 8.1.3.157 optixSetPayload\_0()

```

static __forceinline__ __device__ void optixSetPayload_0 (
    unsigned int p ) [static]

```

#### 8.1.3.158 optixSetPayload\_1()

```

static __forceinline__ __device__ void optixSetPayload_1 (
    unsigned int p ) [static]

```

#### 8.1.3.159 optixSetPayload\_10()

```

static __forceinline__ __device__ void optixSetPayload_10 (
    unsigned int p ) [static]

```

#### 8.1.3.160 optixSetPayload\_11()

```

static __forceinline__ __device__ void optixSetPayload_11 (
    unsigned int p ) [static]

```

#### 8.1.3.161 optixSetPayload\_12()

```

static __forceinline__ __device__ void optixSetPayload_12 (
    unsigned int p ) [static]

```

### 8.1.3.162 optixSetPayload\_13()

```
static __forceinline__ __device__ void optixSetPayload_13 (  
    unsigned int p ) [static]
```

### 8.1.3.163 optixSetPayload\_14()

```
static __forceinline__ __device__ void optixSetPayload_14 (  
    unsigned int p ) [static]
```

### 8.1.3.164 optixSetPayload\_15()

```
static __forceinline__ __device__ void optixSetPayload_15 (  
    unsigned int p ) [static]
```

### 8.1.3.165 optixSetPayload\_16()

```
static __forceinline__ __device__ void optixSetPayload_16 (  
    unsigned int p ) [static]
```

### 8.1.3.166 optixSetPayload\_17()

```
static __forceinline__ __device__ void optixSetPayload_17 (  
    unsigned int p ) [static]
```

### 8.1.3.167 optixSetPayload\_18()

```
static __forceinline__ __device__ void optixSetPayload_18 (  
    unsigned int p ) [static]
```

### 8.1.3.168 optixSetPayload\_19()

```
static __forceinline__ __device__ void optixSetPayload_19 (  
    unsigned int p ) [static]
```

### 8.1.3.169 optixSetPayload\_2()

```
static __forceinline__ __device__ void optixSetPayload_2 (  
    unsigned int p ) [static]
```

### 8.1.3.170 optixSetPayload\_20()

```
static __forceinline__ __device__ void optixSetPayload_20 (  
    unsigned int p ) [static]
```

### 8.1.3.171 optixSetPayload\_21()

```
static __forceinline__ __device__ void optixSetPayload_21 (  
    unsigned int p ) [static]
```

### 8.1.3.172 optixSetPayload\_22()

```
static __forceinline__ __device__ void optixSetPayload_22 (  

```

unsigned int *p* ) *[static]*

#### 8.1.3.173 optixSetPayload\_23()

```
static __forceinline__ __device__ void optixSetPayload_23 (  
    unsigned int p ) [static]
```

#### 8.1.3.174 optixSetPayload\_24()

```
static __forceinline__ __device__ void optixSetPayload_24 (  
    unsigned int p ) [static]
```

#### 8.1.3.175 optixSetPayload\_25()

```
static __forceinline__ __device__ void optixSetPayload_25 (  
    unsigned int p ) [static]
```

#### 8.1.3.176 optixSetPayload\_26()

```
static __forceinline__ __device__ void optixSetPayload_26 (  
    unsigned int p ) [static]
```

#### 8.1.3.177 optixSetPayload\_27()

```
static __forceinline__ __device__ void optixSetPayload_27 (  
    unsigned int p ) [static]
```

#### 8.1.3.178 optixSetPayload\_28()

```
static __forceinline__ __device__ void optixSetPayload_28 (  
    unsigned int p ) [static]
```

#### 8.1.3.179 optixSetPayload\_29()

```
static __forceinline__ __device__ void optixSetPayload_29 (  
    unsigned int p ) [static]
```

#### 8.1.3.180 optixSetPayload\_3()

```
static __forceinline__ __device__ void optixSetPayload_3 (  
    unsigned int p ) [static]
```

#### 8.1.3.181 optixSetPayload\_30()

```
static __forceinline__ __device__ void optixSetPayload_30 (  
    unsigned int p ) [static]
```

#### 8.1.3.182 optixSetPayload\_31()

```
static __forceinline__ __device__ void optixSetPayload_31 (  
    unsigned int p ) [static]
```

### 8.1.3.183 optixSetPayload\_4()

```
static __forceinline__ __device__ void optixSetPayload_4 (  
    unsigned int p ) [static]
```

### 8.1.3.184 optixSetPayload\_5()

```
static __forceinline__ __device__ void optixSetPayload_5 (  
    unsigned int p ) [static]
```

### 8.1.3.185 optixSetPayload\_6()

```
static __forceinline__ __device__ void optixSetPayload_6 (  
    unsigned int p ) [static]
```

### 8.1.3.186 optixSetPayload\_7()

```
static __forceinline__ __device__ void optixSetPayload_7 (  
    unsigned int p ) [static]
```

### 8.1.3.187 optixSetPayload\_8()

```
static __forceinline__ __device__ void optixSetPayload_8 (  
    unsigned int p ) [static]
```

### 8.1.3.188 optixSetPayload\_9()

```
static __forceinline__ __device__ void optixSetPayload_9 (  
    unsigned int p ) [static]
```

### 8.1.3.189 optixSetPayloadTypes()

```
static __forceinline__ __device__ void optixSetPayloadTypes (  
    unsigned int types ) [static]
```

### 8.1.3.190 optixTerminateRay()

```
static __forceinline__ __device__ void optixTerminateRay ( ) [static]
```

### 8.1.3.191 optixTexFootprint2D()

```
static __forceinline__ __device__ uint4 optixTexFootprint2D (  
    unsigned long long tex,  
    unsigned int texInfo,  
    float x,  
    float y,  
    unsigned int * singleMipLevel ) [static]
```

### 8.1.3.192 optixTexFootprint2DGrad()

```
static __forceinline__ __device__ uint4 optixTexFootprint2DGrad (  
    unsigned long long tex,
```

```

    unsigned int texInfo,
    float x,
    float y,
    float dPdx_x,
    float dPdx_y,
    float dPdy_x,
    float dPdy_y,
    bool coarse,
    unsigned int * singleMipLevel ) [static]

```

#### 8.1.3.193 optixTexFootprint2DLod()

```

static __forceinline__ __device__ uint4 optixTexFootprint2DLod (
    unsigned long long tex,
    unsigned int texInfo,
    float x,
    float y,
    float level,
    bool coarse,
    unsigned int * singleMipLevel ) [static]

```

#### 8.1.3.194 optixThrowException() [1/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode ) [static]

```

#### 8.1.3.195 optixThrowException() [2/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0 ) [static]

```

#### 8.1.3.196 optixThrowException() [3/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1 ) [static]

```

#### 8.1.3.197 optixThrowException() [4/9]

```

static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2 ) [static]

```



### 8.1.3.198 optixThrowException() [5/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3 ) [static]
```

### 8.1.3.199 optixThrowException() [6/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4 ) [static]
```

### 8.1.3.200 optixThrowException() [7/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4,
    unsigned int exceptionDetail5 ) [static]
```

### 8.1.3.201 optixThrowException() [8/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4,
    unsigned int exceptionDetail5,
    unsigned int exceptionDetail6 ) [static]
```

### 8.1.3.202 optixThrowException() [9/9]

```
static __forceinline__ __device__ void optixThrowException (
    int exceptionCode,
    unsigned int exceptionDetail0,
```

```

    unsigned int exceptionDetail1,
    unsigned int exceptionDetail2,
    unsigned int exceptionDetail3,
    unsigned int exceptionDetail4,
    unsigned int exceptionDetail5,
    unsigned int exceptionDetail6,
    unsigned int exceptionDetail7 ) [static]

```

#### 8.1.3.203 optixTrace() [1/2]

```

template<typename... Payload>
static __forceinline__ __device__ void optixTrace (
    OptixPayloadTypeID type,
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBTOffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]

```

#### 8.1.3.204 optixTrace() [2/2]

```

template<typename... Payload>
static __forceinline__ __device__ void optixTrace (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBTOffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]

```

## 8.1.3.205 optixTransformNormalFromObjectToWorldSpace()

```
static __forceinline__ __device__ float3
optixTransformNormalFromObjectToWorldSpace (
    float3 normal ) [static]
```

## 8.1.3.206 optixTransformNormalFromWorldToObjectSpace()

```
static __forceinline__ __device__ float3
optixTransformNormalFromWorldToObjectSpace (
    float3 normal ) [static]
```

## 8.1.3.207 optixTransformPointFromObjectToWorldSpace()

```
static __forceinline__ __device__ float3
optixTransformPointFromObjectToWorldSpace (
    float3 point ) [static]
```

## 8.1.3.208 optixTransformPointFromWorldToObjectSpace()

```
static __forceinline__ __device__ float3
optixTransformPointFromWorldToObjectSpace (
    float3 point ) [static]
```

## 8.1.3.209 optixTransformVectorFromObjectToWorldSpace()

```
static __forceinline__ __device__ float3
optixTransformVectorFromObjectToWorldSpace (
    float3 vec ) [static]
```

## 8.1.3.210 optixTransformVectorFromWorldToObjectSpace()

```
static __forceinline__ __device__ float3
optixTransformVectorFromWorldToObjectSpace (
    float3 vec ) [static]
```

## 8.1.3.211 optixTraverse() [1/2]

```
template<typename... Payload>
static __forceinline__ __device__ void optixTraverse (
    OptixPayloadTypeID type,
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
```

```

    unsigned int SBToffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]

```

### 8.1.3.212 optixTraverse() [2/2]

```

template<typename... Payload>
static __forceinline__ __device__ void optixTraverse (
    OptixTraversableHandle handle,
    float3 rayOrigin,
    float3 rayDirection,
    float tmin,
    float tmax,
    float rayTime,
    OptixVisibilityMask visibilityMask,
    unsigned int rayFlags,
    unsigned int SBToffset,
    unsigned int SBTstride,
    unsigned int missSBTIndex,
    Payload &... payload ) [static]

```

### 8.1.3.213 optixUndefinedValue()

```

static __forceinline__ __device__ unsigned int optixUndefinedValue ( ) [static]

```

## 8.2 optix\_device\_impl.h

[Go to the documentation of this file.](#)

```

1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
5  * rights in and to this software, related documentation and any modifications thereto.
6  * Any use, reproduction, disclosure or distribution of this software and related
7  * documentation without an express license agreement from NVIDIA Corporation is strictly
8  * prohibited.
9  *
10 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
11 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
12 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A
13 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
14 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
15 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
16 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
17 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
18 * SUCH DAMAGES
19 */
20
21 #if !defined(__OPTIX_INCLUDE_INTERNAL_HEADERS__)
22 #error("optix_device_impl.h is an internal header file and must not be used directly. Please use
23 optix_device.h or optix.h instead.")
24 #endif
25
26 #ifndef OPTIX_DEVICE_IMPL_H

```

```

34 #define OPTIX_DEVICE_IMPL_H
35
36 #include "internal/optix_device_impl_transformations.h"
37
38 #ifndef __CUDACC_RTC__
39 #include <initializer_list>
40 #include <type_traits>
41 #endif
42
43 namespace optix_internal {
44 template <typename...>
45 struct TypePack{};
46 } // namespace optix_internal
47
48 template <typename... Payload>
49 static __forceinline__ __device__ void optixTrace(OptixTraversableHandle handle,
50  float3 rayOrigin,
51  float3 rayDirection,
52  float tmin,
53  float tmax,
54  float rayTime,
55  OptixVisibilityMask visibilityMask,
56  unsigned int rayFlags,
57  unsigned int SBTOffset,
58  unsigned int SBTstride,
59  unsigned int missSBTIndex,
60  Payload&... payload)
61 {
62     static_assert(sizeof...(Payload) <= 32, "Only up to 32 payload values are allowed.");
63     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
64     // TypePack 1    unsigned int    T0    T1    T2    ...    Tn-1    Tn
65     // TypePack 2      T0            T1    T2    T3    ...    Tn      unsigned int
66 #ifndef __CUDACC_RTC__
67     static_assert(std::is_same<optix_internal::TypePack<unsigned int, Payload...>,
68 optix_internal::TypePack<Payload..., unsigned int>::value,
69 "All payload parameters need to be unsigned int.");
70 #endif
71     OptixPayloadTypeID type = OPTIX_PAYLOAD_TYPE_DEFAULT;
72     float ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
73     float dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
74     unsigned int p[32] = { 0, payload... };
75     int payloadSize = (int)sizeof...(Payload);
76     asm volatile(
77         "call"
78
79         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26,%27,%28,%29,%30,%31),"
80         "_optix_trace_typed_32,"
81
82         "(%32,%33,%34,%35,%36,%37,%38,%39,%40,%41,%42,%43,%44,%45,%46,%47,%48,%49,%50,%51,%52,%53,%54,%55,%56,%57,%58,%59,%60,%61,%62,%63,%64,%65,%66,%67,%68,%69,%70,%71,%72,%73,%74,%75,%76,%77,%78,%79,%80);"
83         : "=r"(p[1]), "=r"(p[2]), "=r"(p[3]), "=r"(p[4]), "=r"(p[5]), "=r"(p[6]), "=r"(p[7]),
84           "=r"(p[8]), "=r"(p[9]), "=r"(p[10]), "=r"(p[11]), "=r"(p[12]), "=r"(p[13]), "=r"(p[14]),
85           "=r"(p[15]), "=r"(p[16]), "=r"(p[17]), "=r"(p[18]), "=r"(p[19]), "=r"(p[20]), "=r"(p[21]),
86           "=r"(p[22]), "=r"(p[23]), "=r"(p[24]), "=r"(p[25]), "=r"(p[26]), "=r"(p[27]), "=r"(p[28]),
87           "=r"(p[29]), "=r"(p[30]), "=r"(p[31]), "=r"(p[32])
88         : "r"(type), "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin),
89           "f"(tmax), "f"(rayTime), "r"(visibilityMask), "r"(rayFlags), "r"(SBTOffset), "r"(SBTstride),
90           "r"(missSBTIndex), "r"(payloadSize), "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]),
91           "r"(p[6]), "r"(p[7]), "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]),
92           "r"(p[14]), "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]),
93           "r"(p[21]), "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]),
94           "r"(p[28]), "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
95         :);
96     unsigned int index = 1;
97     (void)std::initializer_list<unsigned int>{index, (payload = p[index++])...};

```

```

98 }
99
100 template <typename... Payload>
101 static __forceinline__ __device__ void optixTraverse(OptixTraversableHandle handle,
102   float3 rayOrigin,
103   float3 rayDirection,
104   float tmin,
105   float tmax,
106   float rayTime,
107   OptixVisibilityMask visibilityMask,
108   unsigned int rayFlags,
109   unsigned int SBTOffset,
110   unsigned int SBTstride,
111   unsigned int missSBTIndex,
112   Payload&... payload)
113 {
114     static_assert(sizeof...(Payload) <= 32, "Only up to 32 payload values are allowed.");
115     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
116     // TypePack 1 unsigned int T0 T1 T2 ... Tn-1 Tn
117     // TypePack 2 T0 T1 T2 T3 ... Tn unsigned int
118     #ifndef __CUDA_RTC__
119         static_assert(std::is_same<optix_internal::TypePack<unsigned int, Payload...>,
120 optix_internal::TypePack<Payload..., unsigned int>::value,
121 "All payload parameters need to be unsigned int.");
122     #endif
123     OptixPayloadTypeID type = OPTIX_PAYLOAD_TYPE_DEFAULT;
124     float ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
125     float dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
126     unsigned int p[33] = {0, payload...};
127     int payloadSize = (int)sizeof...(Payload);
128     asm volatile(
129         "call"
130
131         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26,%27,%28,%29,%30,%31),"
132         "_optix_hitobject_traverse,"
133
134         "(%32,%33,%34,%35,%36,%37,%38,%39,%40,%41,%42,%43,%44,%45,%46,%47,%48,%49,%50,%51,%52,%53,%54,%55,%56,%57,%58,%59,%60,%61,%62,%63,%64,%65,%66,%67,%68,%69,%70,%71,%72,%73,%74,%75,%76,%77,%78,%79,%80);"
135         : "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]), "r"(p[6]), "r"(p[7]),
136         "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]), "r"(p[14]),
137         "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]), "r"(p[21]),
138         "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]), "r"(p[28]),
139         "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
140         : "r"(type), "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin),
141         "f"(tmax), "f"(rayTime), "r"(visibilityMask), "r"(rayFlags), "r"(SBTOffset), "r"(SBTstride),
142         "r"(missSBTIndex), "r"(payloadSize), "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]),
143         "r"(p[6]), "r"(p[7]), "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]),
144         "r"(p[14]), "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]),
145         "r"(p[21]), "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]),
146         "r"(p[28]), "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
147         :);
148     unsigned int index = 1;
149     (void)std::initializer_list<unsigned int>{index, (payload = p[index++])...};
150 }
151
152 template <typename... Payload>
153 static __forceinline__ __device__ void optixTrace(OptixPayloadTypeID type,
154   OptixTraversableHandle handle,
155   float3 rayOrigin,
156   float3 rayDirection,
157   float tmin,
158   float tmax,
159   float rayTime,
160   OptixVisibilityMask visibilityMask,
161   unsigned int rayFlags,

```

```

162                                     unsigned int      SBTOffset,
163                                     unsigned int      SBTstride,
164                                     unsigned int      missSBTIndex,
165                                     Payload&...      payload)
166 {
167     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
168     // TypePack 1      unsigned int      T0      T1      T2      ...      Tn-1      Tn
169     // TypePack 2      T0      T1      T2      T3      ...      Tn      unsigned int
170     static_assert(sizeof...(Payload) <= 32, "Only up to 32 payload values are allowed.");
171     #ifndef __CUDACC_RTC__
172     static_assert(std::is_same<optix_internal::TypePack<unsigned int, Payload...>,
optix_internal::TypePack<Payload..., unsigned int>::value,
173                 "All payload parameters need to be unsigned int.");
174     #endif
175
176     float      ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
177     float      dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
178     unsigned int p[33]      = {0, payload...};
179     int      payloadSize = (int)sizeof...(Payload);
180
181     asm volatile(
182         "call"
183
184         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26,%27,%28,%29,%30,%31),"
185         "_optix_trace_typed_32,"
186
187         "(%32,%33,%34,%35,%36,%37,%38,%39,%40,%41,%42,%43,%44,%45,%46,%47,%48,%49,%50,%51,%52,%53,%54,%55,%56,%57,%58,%59,%60,%61,%62,%63,%64,%65,%66,%67,%68,%69,%70,%71,%72,%73,%74,%75,%76,%77,%78,%79,%80);"
188         : "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]), "r"(p[6]), "r"(p[7]),
189         "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]), "r"(p[14]),
190         "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]), "r"(p[21]),
191         "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]), "r"(p[28]),
192         "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
193         : "r"(type), "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin),
194         "f"(tmax), "f"(rayTime), "r"(visibilityMask), "r"(rayFlags), "r"(SBTOffset), "r"(SBTstride),
195         "r"(missSBTIndex), "r"(payloadSize), "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]),
196         "r"(p[6]), "r"(p[7]), "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]),
197         "r"(p[14]), "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]),
198         "r"(p[21]), "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]),
199         "r"(p[28]), "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
200         :);
201     unsigned int index = 1;
202     (void)std::initializer_list<unsigned int>{index, (payload = p[index++])...};
203 }
204
205 template <typename... Payload>
206 static __forceinline__ __device__ void optixTraverse(OptixPayloadTypeID      type,
207                                     OptixTraversableHandle handle,
208                                     float3      rayOrigin,
209                                     float3      rayDirection,
210                                     float      tmin,
211                                     float      tmax,
212                                     float      rayTime,
213                                     OptixVisibilityMask visibilityMask,
214                                     unsigned int rayFlags,
215                                     unsigned int SBTOffset,
216                                     unsigned int SBTstride,
217                                     unsigned int missSBTIndex,
218                                     Payload&... payload)
219 {
220     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
221     // TypePack 1      unsigned int      T0      T1      T2      ...      Tn-1      Tn
222     // TypePack 2      T0      T1      T2      T3      ...      Tn      unsigned int
223     static_assert(sizeof...(Payload) <= 32, "Only up to 32 payload values are allowed.");
224     #ifndef __CUDACC_RTC__
225     static_assert(std::is_same<optix_internal::TypePack<unsigned int, Payload...>,

```

```

optix_internal::TypePack<Payload..., unsigned int>::value,
226         "All payload parameters need to be unsigned int.");
227 #endif
228
229     float      ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
230     float      dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
231     unsigned int p[33]      = {0, payload...};
232     int         payloadSize = (int)sizeof...(Payload);
233     asm volatile(
234         "call"
235
236         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26,%27,%28,%29,%30,%31),"
237         "_optix_hitobject_traverse,"
238
239         "(%32,%33,%34,%35,%36,%37,%38,%39,%40,%41,%42,%43,%44,%45,%46,%47,%48,%49,%50,%51,%52,%53,%54,%55,%56,%57,%58,%59,%60,%61,%62,%63,%64,%65,%66,%67,%68,%69,%70,%71,%72,%73,%74,%75,%76,%77,%78,%79,%80);"
240         : "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]), "r"(p[6]), "r"(p[7]),
241           "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]), "r"(p[14]),
242           "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]), "r"(p[21]),
243           "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]), "r"(p[28]),
244           "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
245         : "r"(type), "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin),
246           "f"(tmax), "f"(rayTime), "r"(visibilityMask), "r"(rayFlags), "r"(SBTOffset), "r"(SBTstride),
247           "r"(missSBTIndex), "r"(payloadSize), "r"(p[1]), "r"(p[2]), "r"(p[3]), "r"(p[4]), "r"(p[5]),
248           "r"(p[6]), "r"(p[7]), "r"(p[8]), "r"(p[9]), "r"(p[10]), "r"(p[11]), "r"(p[12]), "r"(p[13]),
249           "r"(p[14]), "r"(p[15]), "r"(p[16]), "r"(p[17]), "r"(p[18]), "r"(p[19]), "r"(p[20]),
250           "r"(p[21]), "r"(p[22]), "r"(p[23]), "r"(p[24]), "r"(p[25]), "r"(p[26]), "r"(p[27]),
251           "r"(p[28]), "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
252         :);
253     unsigned int index = 1;
254     (void)std::initializer_list<unsigned int>{index, (payload = p[index++])...};
255 }
256
257 static __forceinline__ __device__ void optixReorder(unsigned int coherenceHint, unsigned int
numCoherenceHintBits)
258 {
259     asm volatile(
260         "call"
261         "(),"
262         "_optix_hitobject_reorder,"
263         "(%0,%1);"
264         :
265         : "r"(coherenceHint), "r"(numCoherenceHintBits)
266         :);
267 }
268
269 static __forceinline__ __device__ void optixReorder()
270 {
271     unsigned int coherenceHint = 0;
272     unsigned int numCoherenceHintBits = 0;
273     asm volatile(
274         "call"
275         "(),"
276         "_optix_hitobject_reorder,"
277         "(%0,%1);"
278         :
279         : "r"(coherenceHint), "r"(numCoherenceHintBits)
280         :);
281 }
282
283 template <typename... Payload>
284 static __forceinline__ __device__ void optixInvoke(OptixPayloadTypeID type, Payload&... payload)
285 {
286     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
287     // TypePack 1      unsigned int      T0      T1      T2      ...      Tn-1      Tn
288     // TypePack 2      T0      T1      T2      T3      ...      Tn      unsigned int

```



```

289     static_assert(sizeof...(Payload) <= 32, "Only up to 32 payload values are allowed.");
290 #ifndef __CUDACC_RTC__
291     static_assert(std::is_same<optix_internal::TypePack<unsigned int, Payload...>,
optix_internal::TypePack<Payload..., unsigned int>::value,
292         "All payload parameters need to be unsigned int.");
293 #endif
294
295     unsigned int p[33]      = {0, payload...};
296     int          payloadSize = (int)sizeof...(Payload);
297
298     asm volatile(
299         "call"
300
301         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26,%27,%28,%29,%30,%31), "
302         "_optix_hitobject_invoke, "
303
304         "(%32,%33,%34,%35,%36,%37,%38,%39,%40,%41,%42,%43,%44,%45,%46,%47,%48,%49,%50,%51,%52,%53,%54,%55,%56,%57,%58,%59,%60,%61,%62,%63,%64,%65); "
305         : "=r"(p[1]), "=r"(p[2]), "=r"(p[3]), "=r"(p[4]), "=r"(p[5]), "=r"(p[6]), "=r"(p[7]),
306         "=r"(p[8]), "=r"(p[9]), "=r"(p[10]), "=r"(p[11]), "=r"(p[12]), "=r"(p[13]), "=r"(p[14]),
307         "=r"(p[15]), "=r"(p[16]), "=r"(p[17]), "=r"(p[18]), "=r"(p[19]), "=r"(p[20]), "=r"(p[21]),
308         "=r"(p[22]), "=r"(p[23]), "=r"(p[24]), "=r"(p[25]), "=r"(p[26]), "=r"(p[27]), "=r"(p[28]),
309         "=r"(p[29]), "=r"(p[30]), "=r"(p[31]), "=r"(p[32])
310         : "r"(type), "r"(payloadSize), "r"(p[1]), "r"(p[2]),
311         "r"(p[3]), "r"(p[4]), "r"(p[5]), "r"(p[6]), "r"(p[7]), "r"(p[8]), "r"(p[9]), "r"(p[10]),
312         "r"(p[11]), "r"(p[12]), "r"(p[13]), "r"(p[14]), "r"(p[15]), "r"(p[16]), "r"(p[17]),
313         "r"(p[18]), "r"(p[19]), "r"(p[20]), "r"(p[21]), "r"(p[22]), "r"(p[23]), "r"(p[24]),
314         "r"(p[25]), "r"(p[26]), "r"(p[27]), "r"(p[28]), "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
315         :);
316
317     unsigned int index = 1;
318     (void)std::initializer_list<unsigned int>{index, (payload = p[index++])...};
319 }
320
321 template <typename... Payload>
322 static __forceinline__ __device__ void optixInvoke(Payload&... payload)
323 {
324     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
325     // TypePack 1      unsigned int    T0      T1      T2      ...   Tn-1      Tn
326     // TypePack 2      T0              T1      T2      T3      ...   Tn          unsigned int
327     static_assert(sizeof...(Payload) <= 32, "Only up to 32 payload values are allowed.");
328 #ifndef __CUDACC_RTC__
329     static_assert(std::is_same<optix_internal::TypePack<unsigned int, Payload...>,
optix_internal::TypePack<Payload..., unsigned int>::value,
330         "All payload parameters need to be unsigned int.");
331 #endif
332
333     OptixPayloadTypeID type      = OPTIX_PAYLOAD_TYPE_DEFAULT;
334     unsigned int        p[33]    = {0, payload...};
335     int                  payloadSize = (int)sizeof...(Payload);
336
337     asm volatile(
338         "call"
339
340         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26,%27,%28,%29,%30,%31), "
341         "_optix_hitobject_invoke, "
342
343         "(%32,%33,%34,%35,%36,%37,%38,%39,%40,%41,%42,%43,%44,%45,%46,%47,%48,%49,%50,%51,%52,%53,%54,%55,%56,%57,%58,%59,%60,%61,%62,%63,%64,%65); "
344         : "=r"(p[1]), "=r"(p[2]), "=r"(p[3]), "=r"(p[4]), "=r"(p[5]), "=r"(p[6]), "=r"(p[7]),
345         "=r"(p[8]), "=r"(p[9]), "=r"(p[10]), "=r"(p[11]), "=r"(p[12]), "=r"(p[13]), "=r"(p[14]),
346         "=r"(p[15]), "=r"(p[16]), "=r"(p[17]), "=r"(p[18]), "=r"(p[19]), "=r"(p[20]), "=r"(p[21]),
347         "=r"(p[22]), "=r"(p[23]), "=r"(p[24]), "=r"(p[25]), "=r"(p[26]), "=r"(p[27]), "=r"(p[28]),
348         "=r"(p[29]), "=r"(p[30]), "=r"(p[31]), "=r"(p[32])
349         : "r"(type), "r"(payloadSize), "r"(p[1]), "r"(p[2]),

```

```

350         "r"(p[3]), "r"(p[4]), "r"(p[5]), "r"(p[6]), "r"(p[7]), "r"(p[8]), "r"(p[9]), "r"(p[10]),
351         "r"(p[11]), "r"(p[12]), "r"(p[13]), "r"(p[14]), "r"(p[15]), "r"(p[16]), "r"(p[17]),
352         "r"(p[18]), "r"(p[19]), "r"(p[20]), "r"(p[21]), "r"(p[22]), "r"(p[23]), "r"(p[24]),
353         "r"(p[25]), "r"(p[26]), "r"(p[27]), "r"(p[28]), "r"(p[29]), "r"(p[30]), "r"(p[31]), "r"(p[32])
354     );
355
356     unsigned int index = 1;
357     (void)std::initializer_list<unsigned int>{index, (payload = p[index++])...};
358 }
359
360 template <typename... RegAttributes>
361 static __forceinline__ __device__ void optixMakeHitObject(OptixTraversableHandle handle,
362   float3      rayOrigin,
363   float3      rayDirection,
364   float      tmin,
365   float      tmax,
366   float      rayTime,
367   unsigned int sbtOffset,
368   unsigned int sbtStride,
369   unsigned int instIdx,
370   unsigned int sbtGASIdx,
371   unsigned int primIdx,
372   unsigned int hitKind,
373   RegAttributes... regAttributes)
374 {
375     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
376     // TypePack 1      unsigned int      T0      T1      T2      ...      Tn-1      Tn
377     // TypePack 2      T0      T1      T2      T3      ...      Tn      unsigned int
378     static_assert(sizeof...(RegAttributes) <= 8, "Only up to 8 register attribute values are allowed.");
379 #ifndef __CUDA_RTC__
380     static_assert(
381         std::is_same<optix_internal::TypePack<unsigned int, RegAttributes...>,
382         optix_internal::TypePack<RegAttributes..., unsigned int>::value,
383         "All register attribute parameters need to be unsigned int.");
384 #endif
385
386     float      ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
387     float      dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
388     unsigned int a[9] = {0, regAttributes...};
389     int      attrSize = (int)sizeof...(RegAttributes);
390
391     OptixTraversableHandle* transforms = nullptr;
392     unsigned int      numTransforms = 0;
393
394     asm volatile(
395         "call\n"
396         "(),\n"
397         "_optix_hitobject_make_hit,\n"
398         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26);\n"
399         :
400         : "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin), "f"(tmax),
401         "f"(rayTime), "r"(sbtOffset), "r"(sbtStride), "r"(instIdx), "l"(transforms),
402         "r"(numTransforms),
403         "r"(sbtGASIdx), "r"(primIdx), "r"(hitKind), "r"(attrSize), "r"(a[1]), "r"(a[2]), "r"(a[3]),
404         "r"(a[4]), "r"(a[5]), "r"(a[6]), "r"(a[7]), "r"(a[8])
405     );
406
407 template <typename... RegAttributes>
408 static __forceinline__ __device__ void optixMakeHitObject(OptixTraversableHandle handle,
409   float3      rayOrigin,
410   float3      rayDirection,
411   float      tmin,
412   float      tmax,
413   float      rayTime,
414   unsigned int sbtOffset,

```

```

414                                     unsigned int          sbtStride,
415                                     unsigned int          instIdx,
416                                     const OptixTraversableHandle* transforms,
417                                     unsigned int          numTransforms,
418                                     unsigned int          sbtGASIdx,
419                                     unsigned int          primIdx,
420                                     unsigned int          hitKind,
421                                     RegAttributes... regAttributes)
422 {
423     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
424     // TypePack 1      unsigned int    T0      T1      T2      ...   Tn-1      Tn
425     // TypePack 2      T0              T1      T2      T3      ...   Tn      unsigned int
426     static_assert(sizeof...(RegAttributes) <= 8, "Only up to 8 register attribute values are allowed.");
427 #ifndef __CUDACC_RTC__
428     static_assert(
429         std::is_same<optix_internal::TypePack<unsigned int, RegAttributes...>,
430         optix_internal::TypePack<RegAttributes..., unsigned int>::value,
431         "All register attribute parameters need to be unsigned int.");
432 #endif
433     float      ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
434     float      dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
435     unsigned int a[9] = {0, regAttributes...};
436     int        attrSize = (int)sizeof...(RegAttributes);
437
438     asm volatile(
439         "call"
440         "(),",
441         "_optix_hitobject_make_hit,",
442         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25,%26);",
443         :
444         : "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin), "f"(tmax),
445         "f"(rayTime), "r"(sbtOffset), "r"(sbtStride), "r"(instIdx), "l"(transforms),
446         "r"(numTransforms),
447         "r"(sbtGASIdx), "r"(primIdx), "r"(hitKind), "r"(attrSize), "r"(a[1]), "r"(a[2]), "r"(a[3]),
448         "r"(a[4]), "r"(a[5]), "r"(a[6]), "r"(a[7]), "r"(a[8])
449         :);
450
451 template <typename... RegAttributes>
452 static __forceinline__ __device__ void optixMakeHitObjectWithRecord(OptixTraversableHandle handle,
453                             float3 rayOrigin,
454                             float3 rayDirection,
455                             float tmin,
456                             float tmax,
457                             float rayTime,
458                             unsigned int sbtRecordIndex,
459                             unsigned int instIdx,
460                             const OptixTraversableHandle* transforms,
461                             unsigned int numTransforms,
462                             unsigned int sbtGASIdx,
463                             unsigned int primIdx,
464                             unsigned int hitKind,
465                             RegAttributes... regAttributes)
466 {
467     // std::is_same compares each type in the two TypePacks to make sure that all types are unsigned int.
468     // TypePack 1      unsigned int    T0      T1      T2      ...   Tn-1      Tn
469     // TypePack 2      T0              T1      T2      T3      ...   Tn      unsigned int
470     static_assert(sizeof...(RegAttributes) <= 8, "Only up to 8 register attribute values are allowed.");
471 #ifndef __CUDACC_RTC__
472     static_assert(
473         std::is_same<optix_internal::TypePack<unsigned int, RegAttributes...>,
474         optix_internal::TypePack<RegAttributes..., unsigned int>::value,
475         "All register attribute parameters need to be unsigned int.");
476 #endif

```

```

477     float      ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
478     float      dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
479     unsigned int a[9] = {0, regAttributes...};
480     int        attrSize = (int)sizeof...(RegAttributes);
481
482     asm volatile(
483         "call"
484         "(), "
485         "_optix_hitobject_make_hit_with_record, "
486         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9,%10,%11,%12,%13,%14,%15,%16,%17,%18,%19,%20,%21,%22,%23,%24,%25);"
487         :
488         : "l"(handle), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin), "f"(tmax),
489           "f"(rayTime), "r"(sbtRecordIndex), "r"(instIdx), "l"(transforms), "r"(numTransforms),
490           "r"(sbtGASIdx), "r"(primIdx), "r"(hitKind), "r"(attrSize), "r"(a[1]), "r"(a[2]), "r"(a[3]),
491           "r"(a[4]), "r"(a[5]), "r"(a[6]), "r"(a[7]), "r"(a[8])
492         :);
493 }
494
495 static __forceinline__ __device__ void optixMakeMissHitObject(unsigned int missSbtIndex,
496   float3      rayOrigin,
497   float3      rayDirection,
498   float      tmin,
499   float      tmax,
500   float      rayTime)
501 {
502     float ox = rayOrigin.x, oy = rayOrigin.y, oz = rayOrigin.z;
503     float dx = rayDirection.x, dy = rayDirection.y, dz = rayDirection.z;
504
505     asm volatile(
506         "call"
507         "(), "
508         "_optix_hitobject_make_miss, "
509         "(%0,%1,%2,%3,%4,%5,%6,%7,%8,%9);"
510         :
511         : "r"(missSbtIndex), "f"(ox), "f"(oy), "f"(oz), "f"(dx), "f"(dy), "f"(dz), "f"(tmin),
512           "f"(tmax), "f"(rayTime)
513         :);
514 }
515
516 static __forceinline__ __device__ void optixMakeNopHitObject()
517 {
518     asm volatile(
519         "call"
520         "(), "
521         "_optix_hitobject_make_nop, "
522         "();"
523         :
524         :
525         :);
526 }
527
528 static __forceinline__ __device__ bool optixHitObjectIsHit()
529 {
530     unsigned int result;
531     asm volatile(
532         "call (%0), _optix_hitobject_is_hit, "
533         "();"
534         : "=r"(result)
535         :
536         :);
537     return result;
538 }
539
540 static __forceinline__ __device__ bool optixHitObjectIsMiss()
541 {
542     unsigned int result;

```

```

543     asm volatile(
544         "call (%0), _optix_hitobject_is_miss,"
545         "();"
546         : "=r"(result)
547         :
548         :);
549     return result;
550 }
551
552 static __forceinline__ __device__ bool optixHitObjectIsNop()
553 {
554     unsigned int result;
555     asm volatile(
556         "call (%0), _optix_hitobject_is_nop,"
557         "();"
558         : "=r"(result)
559         :
560         :);
561     return result;
562 }
563
564 static __forceinline__ __device__ unsigned int optixHitObjectGetInstanceId()
565 {
566     unsigned int result;
567     asm volatile(
568         "call (%0), _optix_hitobject_get_instance_id,"
569         "();"
570         : "=r"(result)
571         :
572         :);
573     return result;
574 }
575
576 static __forceinline__ __device__ unsigned int optixHitObjectGetInstanceIndex()
577 {
578     unsigned int result;
579     asm volatile(
580         "call (%0), _optix_hitobject_get_instance_idx,"
581         "();"
582         : "=r"(result)
583         :
584         :);
585     return result;
586 }
587
588 static __forceinline__ __device__ unsigned int optixHitObjectGetPrimitiveIndex()
589 {
590     unsigned int result;
591     asm volatile(
592         "call (%0), _optix_hitobject_get_primitive_idx,"
593         "();"
594         : "=r"(result)
595         :
596         :);
597     return result;
598 }
599
600 static __forceinline__ __device__ unsigned int optixHitObjectGetTransformListSize()
601 {
602     unsigned int result;
603     asm volatile(
604         "call (%0), _optix_hitobject_get_transform_list_size,"
605         "();"
606         : "=r"(result)
607         :
608         :);
609     return result;

```

```

610 }
611
612 static __forceinline__ __device__ OptixTraversableHandle optixHitObjectGetTransformListHandle(unsigned
int index)
613 {
614     unsigned long long result;
615     asm volatile(
616         "call (%0), _optix_hitobject_get_transform_list_handle,"
617         "(%1);"
618         : "=l"(result)
619         : "r"(index)
620         :);
621     return result;
622 }
623
624 static __forceinline__ __device__ unsigned int optixHitObjectGetSbtGASIndex()
625 {
626     unsigned int result;
627     asm volatile(
628         "call (%0), _optix_hitobject_get_sbt_gas_idx,"
629         "();"
630         : "=r"(result)
631         :
632         :);
633     return result;
634 }
635
636 static __forceinline__ __device__ unsigned int optixHitObjectGetHitKind()
637 {
638     unsigned int result;
639     asm volatile(
640         "call (%0), _optix_hitobject_get_hitkind,"
641         "();"
642         : "=r"(result)
643         :
644         :);
645     return result;
646 }
647
648 static __forceinline__ __device__ float3 optixHitObjectGetWorldRayOrigin()
649 {
650     float x, y, z;
651     asm volatile(
652         "call (%0), _optix_hitobject_get_world_ray_origin_x,"
653         "();"
654         : "=f"(x)
655         :
656         :);
657     asm volatile(
658         "call (%0), _optix_hitobject_get_world_ray_origin_y,"
659         "();"
660         : "=f"(y)
661         :
662         :);
663     asm volatile(
664         "call (%0), _optix_hitobject_get_world_ray_origin_z,"
665         "();"
666         : "=f"(z)
667         :
668         :);
669     return make_float3(x, y, z);
670 }
671
672 static __forceinline__ __device__ float3 optixHitObjectGetWorldRayDirection()
673 {
674     float x, y, z;
675     asm volatile(

```

```

676         "call (%0), _optix_hitobject_get_world_ray_direction_x,"
677         "();"
678         : "=f"(x)
679         :
680         :);
681     asm volatile(
682         "call (%0), _optix_hitobject_get_world_ray_direction_y,"
683         "();"
684         : "=f"(y)
685         :
686         :);
687     asm volatile(
688         "call (%0), _optix_hitobject_get_world_ray_direction_z,"
689         "();"
690         : "=f"(z)
691         :
692         :);
693     return make_float3(x, y, z);
694 }
695
696 static __forceinline__ __device__ float optixHitObjectGetRayTmin()
697 {
698     float result;
699     asm volatile(
700         "call (%0), _optix_hitobject_get_ray_tmin,"
701         "();"
702         : "=f"(result)
703         :
704         :);
705     return result;
706 }
707
708 static __forceinline__ __device__ float optixHitObjectGetRayTmax()
709 {
710     float result;
711     asm volatile(
712         "call (%0), _optix_hitobject_get_ray_tmax,"
713         "();"
714         : "=f"(result)
715         :
716         :);
717     return result;
718 }
719
720 static __forceinline__ __device__ float optixHitObjectGetRayTime()
721 {
722     float result;
723     asm volatile(
724         "call (%0), _optix_hitobject_get_ray_time,"
725         "();"
726         : "=f"(result)
727         :
728         :);
729     return result;
730 }
731
732 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_0()
733 {
734     unsigned int ret;
735     asm volatile(
736         "call (%0), _optix_hitobject_get_attribute,"
737         "(%1);"
738         : "=r"(ret)
739         : "r"(0)
740         :);
741     return ret;
742 }

```

```

743
744 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_1()
745 {
746     unsigned int ret;
747     asm volatile(
748         "call (%0), _optix_hitobject_get_attribute,"
749         "(%1);"
750         : "=r"(ret)
751         : "r"(1)
752         :);
753     return ret;
754 }
755
756 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_2()
757 {
758     unsigned int ret;
759     asm volatile(
760         "call (%0), _optix_hitobject_get_attribute,"
761         "(%1);"
762         : "=r"(ret)
763         : "r"(2)
764         :);
765     return ret;
766 }
767
768 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_3()
769 {
770     unsigned int ret;
771     asm volatile(
772         "call (%0), _optix_hitobject_get_attribute,"
773         "(%1);"
774         : "=r"(ret)
775         : "r"(3)
776         :);
777     return ret;
778 }
779
780 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_4()
781 {
782     unsigned int ret;
783     asm volatile(
784         "call (%0), _optix_hitobject_get_attribute,"
785         "(%1);"
786         : "=r"(ret)
787         : "r"(4)
788         :);
789     return ret;
790 }
791
792 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_5()
793 {
794     unsigned int ret;
795     asm volatile(
796         "call (%0), _optix_hitobject_get_attribute,"
797         "(%1);"
798         : "=r"(ret)
799         : "r"(5)
800         :);
801     return ret;
802 }
803
804 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_6()
805 {
806     unsigned int ret;
807     asm volatile(
808         "call (%0), _optix_hitobject_get_attribute,"
809         "(%1);"

```



```

810         : "=r"(ret)
811         : "r"(6)
812         :);
813     return ret;
814 }
815
816 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_7()
817 {
818     unsigned int ret;
819     asm volatile(
820         "call (%0), _optix_hitobject_get_attribute,"
821         "(%1);"
822         : "=r"(ret)
823         : "r"(7)
824         :);
825     return ret;
826 }
827
828 static __forceinline__ __device__ unsigned int optixHitObjectGetSbtRecordIndex()
829 {
830     unsigned int result;
831     asm volatile(
832         "call (%0), _optix_hitobject_get_sbt_record_index,"
833         "();"
834         : "=r"(result)
835         :
836         :);
837     return result;
838 }
839
840 static __forceinline__ __device__ CUdeviceptr optixHitObjectGetSbtDataPointer()
841 {
842     unsigned long long ptr;
843     asm volatile(
844         "call (%0), _optix_hitobject_get_sbt_data_pointer,"
845         "();"
846         : "=l"(ptr)
847         :
848         :);
849     return ptr;
850 }
851
852 static __forceinline__ __device__ void optixSetPayload_0(unsigned int p)
853 {
854     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(0), "r"(p) :);
855 }
856
857 static __forceinline__ __device__ void optixSetPayload_1(unsigned int p)
858 {
859     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(1), "r"(p) :);
860 }
861
862 static __forceinline__ __device__ void optixSetPayload_2(unsigned int p)
863 {
864     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(2), "r"(p) :);
865 }
866
867 static __forceinline__ __device__ void optixSetPayload_3(unsigned int p)
868 {
869     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(3), "r"(p) :);
870 }
871
872 static __forceinline__ __device__ void optixSetPayload_4(unsigned int p)
873 {
874     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(4), "r"(p) :);
875 }
876

```

```

877 static __forceinline__ __device__ void optixSetPayload_5(unsigned int p)
878 {
879     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(5), "r"(p) :);
880 }
881
882 static __forceinline__ __device__ void optixSetPayload_6(unsigned int p)
883 {
884     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(6), "r"(p) :);
885 }
886
887 static __forceinline__ __device__ void optixSetPayload_7(unsigned int p)
888 {
889     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(7), "r"(p) :);
890 }
891
892 static __forceinline__ __device__ void optixSetPayload_8(unsigned int p)
893 {
894     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(8), "r"(p) :);
895 }
896
897 static __forceinline__ __device__ void optixSetPayload_9(unsigned int p)
898 {
899     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(9), "r"(p) :);
900 }
901
902 static __forceinline__ __device__ void optixSetPayload_10(unsigned int p)
903 {
904     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(10), "r"(p) :);
905 }
906
907 static __forceinline__ __device__ void optixSetPayload_11(unsigned int p)
908 {
909     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(11), "r"(p) :);
910 }
911
912 static __forceinline__ __device__ void optixSetPayload_12(unsigned int p)
913 {
914     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(12), "r"(p) :);
915 }
916
917 static __forceinline__ __device__ void optixSetPayload_13(unsigned int p)
918 {
919     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(13), "r"(p) :);
920 }
921
922 static __forceinline__ __device__ void optixSetPayload_14(unsigned int p)
923 {
924     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(14), "r"(p) :);
925 }
926
927 static __forceinline__ __device__ void optixSetPayload_15(unsigned int p)
928 {
929     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(15), "r"(p) :);
930 }
931
932 static __forceinline__ __device__ void optixSetPayload_16(unsigned int p)
933 {
934     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(16), "r"(p) :);
935 }
936
937 static __forceinline__ __device__ void optixSetPayload_17(unsigned int p)
938 {
939     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(17), "r"(p) :);
940 }
941
942 static __forceinline__ __device__ void optixSetPayload_18(unsigned int p)
943 {

```

```

944     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(18), "r"(p) :);
945 }
946
947 static __forceinline__ __device__ void optixSetPayload_19(unsigned int p)
948 {
949     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(19), "r"(p) :);
950 }
951
952 static __forceinline__ __device__ void optixSetPayload_20(unsigned int p)
953 {
954     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(20), "r"(p) :);
955 }
956
957 static __forceinline__ __device__ void optixSetPayload_21(unsigned int p)
958 {
959     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(21), "r"(p) :);
960 }
961
962 static __forceinline__ __device__ void optixSetPayload_22(unsigned int p)
963 {
964     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(22), "r"(p) :);
965 }
966
967 static __forceinline__ __device__ void optixSetPayload_23(unsigned int p)
968 {
969     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(23), "r"(p) :);
970 }
971
972 static __forceinline__ __device__ void optixSetPayload_24(unsigned int p)
973 {
974     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(24), "r"(p) :);
975 }
976
977 static __forceinline__ __device__ void optixSetPayload_25(unsigned int p)
978 {
979     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(25), "r"(p) :);
980 }
981
982 static __forceinline__ __device__ void optixSetPayload_26(unsigned int p)
983 {
984     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(26), "r"(p) :);
985 }
986
987 static __forceinline__ __device__ void optixSetPayload_27(unsigned int p)
988 {
989     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(27), "r"(p) :);
990 }
991
992 static __forceinline__ __device__ void optixSetPayload_28(unsigned int p)
993 {
994     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(28), "r"(p) :);
995 }
996
997 static __forceinline__ __device__ void optixSetPayload_29(unsigned int p)
998 {
999     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(29), "r"(p) :);
1000 }
1001
1002 static __forceinline__ __device__ void optixSetPayload_30(unsigned int p)
1003 {
1004     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(30), "r"(p) :);
1005 }
1006
1007 static __forceinline__ __device__ void optixSetPayload_31(unsigned int p)
1008 {
1009     asm volatile("call _optix_set_payload, (%0, %1);" : : "r"(31), "r"(p) :);
1010 }

```

```

1011
1012 static __forceinline__ __device__ unsigned int optixGetPayload_0()
1013 {
1014     unsigned int result;
1015     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(0) :);
1016     return result;
1017 }
1018
1019 static __forceinline__ __device__ unsigned int optixGetPayload_1()
1020 {
1021     unsigned int result;
1022     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(1) :);
1023     return result;
1024 }
1025
1026 static __forceinline__ __device__ unsigned int optixGetPayload_2()
1027 {
1028     unsigned int result;
1029     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(2) :);
1030     return result;
1031 }
1032
1033 static __forceinline__ __device__ unsigned int optixGetPayload_3()
1034 {
1035     unsigned int result;
1036     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(3) :);
1037     return result;
1038 }
1039
1040 static __forceinline__ __device__ unsigned int optixGetPayload_4()
1041 {
1042     unsigned int result;
1043     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(4) :);
1044     return result;
1045 }
1046
1047 static __forceinline__ __device__ unsigned int optixGetPayload_5()
1048 {
1049     unsigned int result;
1050     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(5) :);
1051     return result;
1052 }
1053
1054 static __forceinline__ __device__ unsigned int optixGetPayload_6()
1055 {
1056     unsigned int result;
1057     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(6) :);
1058     return result;
1059 }
1060
1061 static __forceinline__ __device__ unsigned int optixGetPayload_7()
1062 {
1063     unsigned int result;
1064     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(7) :);
1065     return result;
1066 }
1067
1068 static __forceinline__ __device__ unsigned int optixGetPayload_8()
1069 {
1070     unsigned int result;
1071     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(8) :);
1072     return result;
1073 }
1074
1075 static __forceinline__ __device__ unsigned int optixGetPayload_9()
1076 {
1077     unsigned int result;

```

```

1078     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(9) :);
1079     return result;
1080 }
1081
1082 static __forceinline__ __device__ unsigned int optixGetPayload_10()
1083 {
1084     unsigned int result;
1085     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(10) :);
1086     return result;
1087 }
1088
1089 static __forceinline__ __device__ unsigned int optixGetPayload_11()
1090 {
1091     unsigned int result;
1092     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(11) :);
1093     return result;
1094 }
1095
1096 static __forceinline__ __device__ unsigned int optixGetPayload_12()
1097 {
1098     unsigned int result;
1099     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(12) :);
1100     return result;
1101 }
1102
1103 static __forceinline__ __device__ unsigned int optixGetPayload_13()
1104 {
1105     unsigned int result;
1106     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(13) :);
1107     return result;
1108 }
1109
1110 static __forceinline__ __device__ unsigned int optixGetPayload_14()
1111 {
1112     unsigned int result;
1113     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(14) :);
1114     return result;
1115 }
1116
1117 static __forceinline__ __device__ unsigned int optixGetPayload_15()
1118 {
1119     unsigned int result;
1120     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(15) :);
1121     return result;
1122 }
1123
1124 static __forceinline__ __device__ unsigned int optixGetPayload_16()
1125 {
1126     unsigned int result;
1127     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(16) :);
1128     return result;
1129 }
1130
1131 static __forceinline__ __device__ unsigned int optixGetPayload_17()
1132 {
1133     unsigned int result;
1134     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(17) :);
1135     return result;
1136 }
1137
1138 static __forceinline__ __device__ unsigned int optixGetPayload_18()
1139 {
1140     unsigned int result;
1141     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(18) :);
1142     return result;
1143 }
1144

```

```

1145 static __forceinline__ __device__ unsigned int optixGetPayload_19()
1146 {
1147     unsigned int result;
1148     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(19) :);
1149     return result;
1150 }
1151
1152 static __forceinline__ __device__ unsigned int optixGetPayload_20()
1153 {
1154     unsigned int result;
1155     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(20) :);
1156     return result;
1157 }
1158
1159 static __forceinline__ __device__ unsigned int optixGetPayload_21()
1160 {
1161     unsigned int result;
1162     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(21) :);
1163     return result;
1164 }
1165
1166 static __forceinline__ __device__ unsigned int optixGetPayload_22()
1167 {
1168     unsigned int result;
1169     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(22) :);
1170     return result;
1171 }
1172
1173 static __forceinline__ __device__ unsigned int optixGetPayload_23()
1174 {
1175     unsigned int result;
1176     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(23) :);
1177     return result;
1178 }
1179
1180 static __forceinline__ __device__ unsigned int optixGetPayload_24()
1181 {
1182     unsigned int result;
1183     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(24) :);
1184     return result;
1185 }
1186
1187 static __forceinline__ __device__ unsigned int optixGetPayload_25()
1188 {
1189     unsigned int result;
1190     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(25) :);
1191     return result;
1192 }
1193
1194 static __forceinline__ __device__ unsigned int optixGetPayload_26()
1195 {
1196     unsigned int result;
1197     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(26) :);
1198     return result;
1199 }
1200
1201 static __forceinline__ __device__ unsigned int optixGetPayload_27()
1202 {
1203     unsigned int result;
1204     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(27) :);
1205     return result;
1206 }
1207
1208 static __forceinline__ __device__ unsigned int optixGetPayload_28()
1209 {
1210     unsigned int result;
1211     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(28) :);

```

```

1212     return result;
1213 }
1214
1215 static __forceinline__ __device__ unsigned int optixGetPayload_29()
1216 {
1217     unsigned int result;
1218     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(29) :);
1219     return result;
1220 }
1221
1222 static __forceinline__ __device__ unsigned int optixGetPayload_30()
1223 {
1224     unsigned int result;
1225     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(30) :);
1226     return result;
1227 }
1228
1229 static __forceinline__ __device__ unsigned int optixGetPayload_31()
1230 {
1231     unsigned int result;
1232     asm volatile("call (%0), _optix_get_payload, (%1);" : "=r"(result) : "r"(31) :);
1233     return result;
1234 }
1235
1236 static __forceinline__ __device__ void optixSetPayloadTypes(unsigned int types)
1237 {
1238     asm volatile("call _optix_set_payload_types, (%0);" : : "r"(types) :);
1239 }
1240
1241 static __forceinline__ __device__ unsigned int optixUndefinedValue()
1242 {
1243     unsigned int u0;
1244     asm("call (%0), _optix_undef_value, ();" : "=r"(u0) :);
1245     return u0;
1246 }
1247
1248 static __forceinline__ __device__ float3 optixGetWorldRayOrigin()
1249 {
1250     float f0, f1, f2;
1251     asm("call (%0), _optix_get_world_ray_origin_x, ();" : "=f"(f0) :);
1252     asm("call (%0), _optix_get_world_ray_origin_y, ();" : "=f"(f1) :);
1253     asm("call (%0), _optix_get_world_ray_origin_z, ();" : "=f"(f2) :);
1254     return make_float3(f0, f1, f2);
1255 }
1256
1257 static __forceinline__ __device__ float3 optixGetWorldRayDirection()
1258 {
1259     float f0, f1, f2;
1260     asm("call (%0), _optix_get_world_ray_direction_x, ();" : "=f"(f0) :);
1261     asm("call (%0), _optix_get_world_ray_direction_y, ();" : "=f"(f1) :);
1262     asm("call (%0), _optix_get_world_ray_direction_z, ();" : "=f"(f2) :);
1263     return make_float3(f0, f1, f2);
1264 }
1265
1266 static __forceinline__ __device__ float3 optixGetObjectRayOrigin()
1267 {
1268     float f0, f1, f2;
1269     asm("call (%0), _optix_get_object_ray_origin_x, ();" : "=f"(f0) :);
1270     asm("call (%0), _optix_get_object_ray_origin_y, ();" : "=f"(f1) :);
1271     asm("call (%0), _optix_get_object_ray_origin_z, ();" : "=f"(f2) :);
1272     return make_float3(f0, f1, f2);
1273 }
1274
1275 static __forceinline__ __device__ float3 optixGetObjectRayDirection()
1276 {
1277     float f0, f1, f2;
1278     asm("call (%0), _optix_get_object_ray_direction_x, ();" : "=f"(f0) :);

```

```

1279     asm("call (%0), _optix_get_object_ray_direction_y, ();" : "=f"(f1) :);
1280     asm("call (%0), _optix_get_object_ray_direction_z, ();" : "=f"(f2) :);
1281     return make_float3(f0, f1, f2);
1282 }
1283
1284 static __forceinline__ __device__ float optixGetRayTmin()
1285 {
1286     float f0;
1287     asm("call (%0), _optix_get_ray_tmin, ();" : "=f"(f0) :);
1288     return f0;
1289 }
1290
1291 static __forceinline__ __device__ float optixGetRayTmax()
1292 {
1293     float f0;
1294     asm("call (%0), _optix_get_ray_tmax, ();" : "=f"(f0) :);
1295     return f0;
1296 }
1297
1298 static __forceinline__ __device__ float optixGetRayTime()
1299 {
1300     float f0;
1301     asm("call (%0), _optix_get_ray_time, ();" : "=f"(f0) :);
1302     return f0;
1303 }
1304
1305 static __forceinline__ __device__ unsigned int optixGetRayFlags()
1306 {
1307     unsigned int u0;
1308     asm("call (%0), _optix_get_ray_flags, ();" : "=r"(u0) :);
1309     return u0;
1310 }
1311
1312 static __forceinline__ __device__ unsigned int optixGetRayVisibilityMask()
1313 {
1314     unsigned int u0;
1315     asm("call (%0), _optix_get_ray_visibility_mask, ();" : "=r"(u0) :);
1316     return u0;
1317 }
1318
1319 static __forceinline__ __device__ OptixTraversableHandle
optixGetInstanceTraversableFromIAS(OptixTraversableHandle ias,
1320                                  instIdx)                                unsigned int
1321 {
1322     unsigned long long handle;
1323     asm("call (%0), _optix_get_instance_traversable_from_ias, (%1, %2);"
1324         : "=l"(handle) : "l"(ias), "r"(instIdx));
1325     return (OptixTraversableHandle)handle;
1326 }
1327
1328
1329 static __forceinline__ __device__ void optixGetTriangleVertexData(OptixTraversableHandle gas,
1330   unsigned int      primIdx,
1331   unsigned int      sbtGASIndex,
1332   float             time,
1333   float3            data[3])
1334 {
1335     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8), _optix_get_triangle_vertex_data, "
1336         : "%0, %10, %11, %12);"
1337         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[1].x), "=f"(data[1].y),
1338           "=f"(data[1].z), "=f"(data[2].x), "=f"(data[2].y), "=f"(data[2].z)
1339         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1340         :);
1341 }
1342
1343 static __forceinline__ __device__ void optixGetMicroTriangleVertexData(float3 data[3])

```



```

1344 {
1345     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8), _optix_get_microtriangle_vertex_data, "
1346         "());"
1347         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[1].x), "=f"(data[1].y),
1348         "=f"(data[1].z), "=f"(data[2].x), "=f"(data[2].y), "=f"(data[2].z)
1349         :);
1350 }
1351 static __forceinline__ __device__ void optixGetMicroTriangleBarycentricsData(float2 data[3])
1352 {
1353     asm("call (%0, %1, %2, %3, %4, %5), _optix_get_microtriangle_barycentrics_data, "
1354         "());"
1355         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[1].x), "=f"(data[1].y), "=f"(data[2].x),
1356         "=f"(data[2].y)
1357         :);
1358 }
1359 static __forceinline__ __device__ void optixGetLinearCurveVertexData(OptixTraversableHandle gas,
1360  unsigned int      primIdx,
1361  unsigned int      sbtGASIndex,
1362  float             time,
1363  float4           data[2])
1364 {
1365     asm("call (%0, %1, %2, %3, %4, %5, %6, %7), _optix_get_linear_curve_vertex_data, "
1366         "(%8, %9, %10, %11);"
1367         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w),
1368         "=f"(data[1].x), "=f"(data[1].y), "=f"(data[1].z), "=f"(data[1].w)
1369         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1370         :);
1371 }
1372
1373 static __forceinline__ __device__ void optixGetQuadraticBSplineVertexData(OptixTraversableHandle gas,
1374  unsigned int      primIdx,
1375  unsigned int      sbtGASIndex,
1376  float             time,
1377  float4           data[3])
1378 {
1379     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8, %9, %10, %11),
1380         _optix_get_quadratic_bspline_vertex_data, "
1381         "(%12, %13, %14, %15);"
1382         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w),
1383         "=f"(data[1].x), "=f"(data[1].y), "=f"(data[1].z), "=f"(data[1].w),
1384         "=f"(data[2].x), "=f"(data[2].y), "=f"(data[2].z), "=f"(data[2].w)
1385         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1386         :);
1387 }
1388 static __forceinline__ __device__ void optixGetCubicBSplineVertexData(OptixTraversableHandle gas,
1389  unsigned int      primIdx,
1390  unsigned int      sbtGASIndex,
1391  float             time,
1392  float4           data[4])
1393 {
1394     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8, %9, %10, %11, %12, %13, %14, %15), "
1395         "_optix_get_cubic_bspline_vertex_data, "
1396         "(%16, %17, %18, %19);"
1397         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w),
1398         "=f"(data[1].x), "=f"(data[1].y), "=f"(data[1].z), "=f"(data[1].w),
1399         "=f"(data[2].x), "=f"(data[2].y), "=f"(data[2].z), "=f"(data[2].w),
1400         "=f"(data[3].x), "=f"(data[3].y), "=f"(data[3].z), "=f"(data[3].w)
1401         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1402         :);
1403 }
1404
1405 static __forceinline__ __device__ void optixGetCatmullRomVertexData(OptixTraversableHandle gas,
1406  unsigned int      primIdx,
1407  unsigned int      sbtGASIndex,
1408  float             time,

```

```

1409                                     float4                                data[4])
1410 {
1411     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8, %9, %10, %11, %12, %13, %14, %15), "
1412         "_optix_get_catmullrom_vertex_data, "
1413         "(%16, %17, %18, %19);"
1414         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w), "=f"(data[1].x),
1415           "=f"(data[1].y), "=f"(data[1].z), "=f"(data[1].w), "=f"(data[2].x), "=f"(data[2].y),
1416           "=f"(data[2].z), "=f"(data[2].w), "=f"(data[3].x), "=f"(data[3].y), "=f"(data[3].z),
1417           "=f"(data[3].w)
1418         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1419         :);
1420 }
1421 static __forceinline__ __device__ void optixGetCubicBezierVertexData(OptixTraversableHandle gas,
1422                                     unsigned int                                primIdx,
1423                                     unsigned int                                sbtGASIndex,
1424                                     float  time,
1425                                     float4                                       data[4])
1426 {
1427     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8, %9, %10, %11, %12, %13, %14, %15), "
1428         "_optix_get_cubic_bezier_vertex_data, "
1429         "(%16, %17, %18, %19);"
1430         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w), "=f"(data[1].x),
1431           "=f"(data[1].y), "=f"(data[1].z), "=f"(data[1].w), "=f"(data[2].x), "=f"(data[2].y),
1432           "=f"(data[2].z), "=f"(data[2].w), "=f"(data[3].x), "=f"(data[3].y), "=f"(data[3].z),
1433           "=f"(data[3].w)
1434         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1435         :);
1436 }
1437 static __forceinline__ __device__ void optixGetRibbonVertexData(OptixTraversableHandle gas,
1438                                     unsigned int                                primIdx,
1439                                     unsigned int                                sbtGASIndex,
1440                                     float  time,
1441                                     float4                                       data[3])
1442 {
1443     asm("call (%0, %1, %2, %3, %4, %5, %6, %7, %8, %9, %10, %11), _optix_get_ribbon_vertex_data, "
1444         "(%12, %13, %14, %15);"
1445         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w), "=f"(data[1].x),
1446           "=f"(data[1].y),
1447           "=f"(data[1].z), "=f"(data[1].w), "=f"(data[2].x), "=f"(data[2].y), "=f"(data[2].z),
1448           "=f"(data[2].w)
1449         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1450         :);
1451 }
1452 static __forceinline__ __device__ float3 optixGetRibbonNormal(OptixTraversableHandle gas,
1453                                     unsigned int                                primIdx,
1454                                     unsigned int                                sbtGASIndex,
1455                                     float  time,
1456                                     float2                                       ribbonParameters)
1457 {
1458     float3 normal;
1459     asm("call (%0, %1, %2), _optix_get_ribbon_normal, "
1460         "(%3, %4, %5, %6, %7, %8);"
1461         : "=f"(normal.x), "=f"(normal.y), "=f"(normal.z)
1462         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time),
1463           "f"(ribbonParameters.x), "f"(ribbonParameters.y)
1464         :);
1465     return normal;
1466 }
1467 static __forceinline__ __device__ void optixGetSphereData(OptixTraversableHandle gas,
1468                                     unsigned int                                primIdx,
1469                                     unsigned int                                sbtGASIndex,
1470                                     float  time,
1471                                     float4                                       data[1])

```

```

1472 {
1473     asm("call (%0, %1, %2, %3), "
1474         "_optix_get_sphere_data, "
1475         "(%4, %5, %6, %7);"
1476         : "=f"(data[0].x), "=f"(data[0].y), "=f"(data[0].z), "=f"(data[0].w)
1477         : "l"(gas), "r"(primIdx), "r"(sbtGASIndex), "f"(time)
1478         :);
1479 }
1480
1481 static __forceinline__ __device__ OptixTraversableHandle optixGetGASTraversableHandle()
1482 {
1483     unsigned long long handle;
1484     asm("call (%0), _optix_get_gas_traversable_handle, ();" : "=l"(handle) :);
1485     return (OptixTraversableHandle)handle;
1486 }
1487
1488 static __forceinline__ __device__ float optixGetGASMotionTimeBegin(OptixTraversableHandle handle)
1489 {
1490     float f0;
1491     asm("call (%0), _optix_get_gas_motion_time_begin, (%1);" : "=f"(f0) : "l"(handle) :);
1492     return f0;
1493 }
1494
1495 static __forceinline__ __device__ float optixGetGASMotionTimeEnd(OptixTraversableHandle handle)
1496 {
1497     float f0;
1498     asm("call (%0), _optix_get_gas_motion_time_end, (%1);" : "=f"(f0) : "l"(handle) :);
1499     return f0;
1500 }
1501
1502 static __forceinline__ __device__ unsigned int optixGetGASMotionStepCount(OptixTraversableHandle handle)
1503 {
1504     unsigned int u0;
1505     asm("call (%0), _optix_get_gas_motion_step_count, (%1);" : "=r"(u0) : "l"(handle) :);
1506     return u0;
1507 }
1508
1509 static __forceinline__ __device__ void optixGetWorldToObjectTransformMatrix(float m[12])
1510 {
1511     if(optixGetTransformListSize() == 0)
1512     {
1513         m[0] = 1.0f;
1514         m[1] = 0.0f;
1515         m[2] = 0.0f;
1516         m[3] = 0.0f;
1517         m[4] = 0.0f;
1518         m[5] = 1.0f;
1519         m[6] = 0.0f;
1520         m[7] = 0.0f;
1521         m[8] = 0.0f;
1522         m[9] = 0.0f;
1523         m[10] = 1.0f;
1524         m[11] = 0.0f;
1525         return;
1526     }
1527
1528     float4 m0, m1, m2;
1529     optix_impl::optixGetWorldToObjectTransformMatrix(m0, m1, m2);
1530     m[0] = m0.x;
1531     m[1] = m0.y;
1532     m[2] = m0.z;
1533     m[3] = m0.w;
1534     m[4] = m1.x;
1535     m[5] = m1.y;
1536     m[6] = m1.z;
1537     m[7] = m1.w;
1538     m[8] = m2.x;

```

```

1539     m[9]  = m2.y;
1540     m[10] = m2.z;
1541     m[11] = m2.w;
1542 }
1543
1544 static __forceinline__ __device__ void optixGetObjectToWorldTransformMatrix(float m[12])
1545 {
1546     if(optixGetTransformListSize() == 0)
1547     {
1548         m[0]  = 1.0f;
1549         m[1]  = 0.0f;
1550         m[2]  = 0.0f;
1551         m[3]  = 0.0f;
1552         m[4]  = 0.0f;
1553         m[5]  = 1.0f;
1554         m[6]  = 0.0f;
1555         m[7]  = 0.0f;
1556         m[8]  = 0.0f;
1557         m[9]  = 0.0f;
1558         m[10] = 1.0f;
1559         m[11] = 0.0f;
1560         return;
1561     }
1562
1563     float4 m0, m1, m2;
1564     optix_impl::optixGetObjectToWorldTransformMatrix(m0, m1, m2);
1565     m[0]  = m0.x;
1566     m[1]  = m0.y;
1567     m[2]  = m0.z;
1568     m[3]  = m0.w;
1569     m[4]  = m1.x;
1570     m[5]  = m1.y;
1571     m[6]  = m1.z;
1572     m[7]  = m1.w;
1573     m[8]  = m2.x;
1574     m[9]  = m2.y;
1575     m[10] = m2.z;
1576     m[11] = m2.w;
1577 }
1578
1579 static __forceinline__ __device__ float3 optixTransformPointFromWorldToObjectSpace(float3 point)
1580 {
1581     if(optixGetTransformListSize() == 0)
1582         return point;
1583
1584     float4 m0, m1, m2;
1585     optix_impl::optixGetWorldToObjectTransformMatrix(m0, m1, m2);
1586     return optix_impl::optixTransformPoint(m0, m1, m2, point);
1587 }
1588
1589 static __forceinline__ __device__ float3 optixTransformVectorFromWorldToObjectSpace(float3 vec)
1590 {
1591     if(optixGetTransformListSize() == 0)
1592         return vec;
1593
1594     float4 m0, m1, m2;
1595     optix_impl::optixGetWorldToObjectTransformMatrix(m0, m1, m2);
1596     return optix_impl::optixTransformVector(m0, m1, m2, vec);
1597 }
1598
1599 static __forceinline__ __device__ float3 optixTransformNormalFromWorldToObjectSpace(float3 normal)
1600 {
1601     if(optixGetTransformListSize() == 0)
1602         return normal;
1603
1604     float4 m0, m1, m2;
1605     optix_impl::optixGetObjectToWorldTransformMatrix(m0, m1, m2); // inverse of

```

```

optixGetWorldToObjectTransformMatrix()
1606     return optix_impl::optixTransformNormal(m0, m1, m2, normal);
1607 }
1608
1609 static __forceinline__ __device__ float3 optixTransformPointFromObjectToWorldSpace(float3 point)
1610 {
1611     if(optixGetTransformListSize() == 0)
1612         return point;
1613
1614     float4 m0, m1, m2;
1615     optix_impl::optixGetObjectToWorldTransformMatrix(m0, m1, m2);
1616     return optix_impl::optixTransformPoint(m0, m1, m2, point);
1617 }
1618
1619 static __forceinline__ __device__ float3 optixTransformVectorFromObjectToWorldSpace(float3 vec)
1620 {
1621     if(optixGetTransformListSize() == 0)
1622         return vec;
1623
1624     float4 m0, m1, m2;
1625     optix_impl::optixGetObjectToWorldTransformMatrix(m0, m1, m2);
1626     return optix_impl::optixTransformVector(m0, m1, m2, vec);
1627 }
1628
1629 static __forceinline__ __device__ float3 optixTransformNormalFromObjectToWorldSpace(float3 normal)
1630 {
1631     if(optixGetTransformListSize() == 0)
1632         return normal;
1633
1634     float4 m0, m1, m2;
1635     optix_impl::optixGetWorldToObjectTransformMatrix(m0, m1, m2); // inverse of
optixGetObjectToWorldTransformMatrix()
1636     return optix_impl::optixTransformNormal(m0, m1, m2, normal);
1637 }
1638
1639 static __forceinline__ __device__ unsigned int optixGetTransformListSize()
1640 {
1641     unsigned int u0;
1642     asm("call (%0), _optix_get_transform_list_size, ();" : "=r"(u0) :);
1643     return u0;
1644 }
1645
1646 static __forceinline__ __device__ OptixTraversableHandle optixGetTransformListHandle(unsigned int index)
1647 {
1648     unsigned long long u0;
1649     asm("call (%0), _optix_get_transform_list_handle, (%1);" : "=l"(u0) : "r"(index) :);
1650     return u0;
1651 }
1652
1653 static __forceinline__ __device__ OptixTransformType
optixGetTransformTypeFromHandle(OptixTraversableHandle handle)
1654 {
1655     int i0;
1656     asm("call (%0), _optix_get_transform_type_from_handle, (%1);" : "=r"(i0) : "l"(handle) :);
1657     return (OptixTransformType)i0;
1658 }
1659
1660 static __forceinline__ __device__ const OptixStaticTransform*
optixGetStaticTransformFromHandle(OptixTraversableHandle handle)
1661 {
1662     unsigned long long ptr;
1663     asm("call (%0), _optix_get_static_transform_from_handle, (%1);" : "=l"(ptr) : "l"(handle) :);
1664     return (const OptixStaticTransform*)ptr;
1665 }
1666
1667 static __forceinline__ __device__ const OptixSRTMotionTransform*
optixGetSRTMotionTransformFromHandle(OptixTraversableHandle handle)

```

```

1668 {
1669     unsigned long long ptr;
1670     asm("call (%0), _optix_get_srt_motion_transform_from_handle, (%1);" : "=l"(ptr) : "l"(handle) :);
1671     return (const OptixSRTMotionTransform*)ptr;
1672 }
1673
1674 static __forceinline__ __device__ const OptixMatrixMotionTransform*
optixGetMatrixMotionTransformFromHandle(OptixTraversableHandle handle)
1675 {
1676     unsigned long long ptr;
1677     asm("call (%0), _optix_get_matrix_motion_transform_from_handle, (%1);" : "=l"(ptr) : "l"(handle) :);
1678     return (const OptixMatrixMotionTransform*)ptr;
1679 }
1680
1681 static __forceinline__ __device__ unsigned int optixGetInstanceIdFromHandle(OptixTraversableHandle
handle)
1682 {
1683     int i0;
1684     asm("call (%0), _optix_get_instance_id_from_handle, (%1);" : "=r"(i0) : "l"(handle) :);
1685     return i0;
1686 }
1687
1688 static __forceinline__ __device__ OptixTraversableHandle
optixGetInstanceChildFromHandle(OptixTraversableHandle handle)
1689 {
1690     unsigned long long i0;
1691     asm("call (%0), _optix_get_instance_child_from_handle, (%1);" : "=l"(i0) : "l"(handle) :);
1692     return (OptixTraversableHandle)i0;
1693 }
1694
1695 static __forceinline__ __device__ const float4*
optixGetInstanceTransformFromHandle(OptixTraversableHandle handle)
1696 {
1697     unsigned long long ptr;
1698     asm("call (%0), _optix_get_instance_transform_from_handle, (%1);" : "=l"(ptr) : "l"(handle) :);
1699     return (const float4*)ptr;
1700 }
1701
1702 static __forceinline__ __device__ const float4*
optixGetInstanceInverseTransformFromHandle(OptixTraversableHandle handle)
1703 {
1704     unsigned long long ptr;
1705     asm("call (%0), _optix_get_instance_inverse_transform_from_handle, (%1);" : "=l"(ptr) : "l"(handle)
:);
1706     return (const float4*)ptr;
1707 }
1708
1709 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind)
1710 {
1711     int ret;
1712     asm volatile(
1713         "call (%0), _optix_report_intersection_0"
1714         ", (%1, %2);"
1715         : "=r"(ret)
1716         : "f"(hitT), "r"(hitKind)
1717         :);
1718     return ret;
1719 }
1720
1721 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind,
unsigned int a0)
1722 {
1723     int ret;
1724     asm volatile(
1725         "call (%0), _optix_report_intersection_1"
1726         ", (%1, %2, %3);"
1727         : "=r"(ret)

```

```

1728         : "f"(hitT), "r"(hitKind), "r"(a0)
1729         :);
1730     return ret;
1731 }
1732
1733 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind,
1734 unsigned int a0, unsigned int a1)
1735 {
1736     int ret;
1737     asm volatile(
1738         "call (%0), _optix_report_intersection_2"
1739         ", (%1, %2, %3, %4);"
1740         : "=r"(ret)
1741         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1)
1742         :);
1743     return ret;
1744 }
1745
1746 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind,
1747 unsigned int a0, unsigned int a1, unsigned int a2)
1748 {
1749     int ret;
1750     asm volatile(
1751         "call (%0), _optix_report_intersection_3"
1752         ", (%1, %2, %3, %4, %5);"
1753         : "=r"(ret)
1754         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1), "r"(a2)
1755         :);
1756     return ret;
1757 }
1758
1759 static __forceinline__ __device__ bool optixReportIntersection(float hitT,
1760 unsigned int hitKind,
1761 unsigned int a0,
1762 unsigned int a1,
1763 unsigned int a2,
1764 unsigned int a3)
1765 {
1766     int ret;
1767     asm volatile(
1768         "call (%0), _optix_report_intersection_4"
1769         ", (%1, %2, %3, %4, %5, %6);"
1770         : "=r"(ret)
1771         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1), "r"(a2), "r"(a3)
1772         :);
1773     return ret;
1774 }
1775
1776 static __forceinline__ __device__ bool optixReportIntersection(float hitT,
1777 unsigned int hitKind,
1778 unsigned int a0,
1779 unsigned int a1,
1780 unsigned int a2,
1781 unsigned int a3,
1782 unsigned int a4)
1783 {
1784     int ret;
1785     asm volatile(
1786         "call (%0), _optix_report_intersection_5"
1787         ", (%1, %2, %3, %4, %5, %6, %7);"
1788         : "=r"(ret)
1789         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1), "r"(a2), "r"(a3), "r"(a4)
1790         :);
1791     return ret;
1792 }
1793
1794 static __forceinline__ __device__ bool optixReportIntersection(float hitT,

```

```

1793                                     unsigned int hitKind,
1794                                     unsigned int a0,
1795                                     unsigned int a1,
1796                                     unsigned int a2,
1797                                     unsigned int a3,
1798                                     unsigned int a4,
1799                                     unsigned int a5)
1800 {
1801     int ret;
1802     asm volatile(
1803         "call (%0), _optix_report_intersection_6"
1804         ", (%1, %2, %3, %4, %5, %6, %7, %8);"
1805         : "=r"(ret)
1806         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1), "r"(a2), "r"(a3), "r"(a4), "r"(a5)
1807         :);
1808     return ret;
1809 }
1810
1811 static __forceinline__ __device__ bool optixReportIntersection(float hitT,
1812                                     unsigned int hitKind,
1813                                     unsigned int a0,
1814                                     unsigned int a1,
1815                                     unsigned int a2,
1816                                     unsigned int a3,
1817                                     unsigned int a4,
1818                                     unsigned int a5,
1819                                     unsigned int a6)
1820 {
1821     int ret;
1822     asm volatile(
1823         "call (%0), _optix_report_intersection_7"
1824         ", (%1, %2, %3, %4, %5, %6, %7, %8, %9);"
1825         : "=r"(ret)
1826         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1), "r"(a2), "r"(a3), "r"(a4), "r"(a5), "r"(a6)
1827         :);
1828     return ret;
1829 }
1830
1831 static __forceinline__ __device__ bool optixReportIntersection(float hitT,
1832                                     unsigned int hitKind,
1833                                     unsigned int a0,
1834                                     unsigned int a1,
1835                                     unsigned int a2,
1836                                     unsigned int a3,
1837                                     unsigned int a4,
1838                                     unsigned int a5,
1839                                     unsigned int a6,
1840                                     unsigned int a7)
1841 {
1842     int ret;
1843     asm volatile(
1844         "call (%0), _optix_report_intersection_8"
1845         ", (%1, %2, %3, %4, %5, %6, %7, %8, %9, %10);"
1846         : "=r"(ret)
1847         : "f"(hitT), "r"(hitKind), "r"(a0), "r"(a1), "r"(a2), "r"(a3), "r"(a4), "r"(a5), "r"(a6), "r"(a7)
1848         :);
1849     return ret;
1850 }
1851
1852 #define OPTIX_DEFINE_optixGetAttribute_BODY(which)
1853 unsigned int ret;
1854 asm("call (%0), _optix_get_attribute_" #which ", ();" : "=r"(ret) :);
1855     return ret;
1856

```



```

1857 static __forceinline__ __device__ unsigned int optixGetAttribute_0()
1858 {
1859     OPTIX_DEFINE_optixGetAttribute_BODY(0);
1860 }
1861
1862 static __forceinline__ __device__ unsigned int optixGetAttribute_1()
1863 {
1864     OPTIX_DEFINE_optixGetAttribute_BODY(1);
1865 }
1866
1867 static __forceinline__ __device__ unsigned int optixGetAttribute_2()
1868 {
1869     OPTIX_DEFINE_optixGetAttribute_BODY(2);
1870 }
1871
1872 static __forceinline__ __device__ unsigned int optixGetAttribute_3()
1873 {
1874     OPTIX_DEFINE_optixGetAttribute_BODY(3);
1875 }
1876
1877 static __forceinline__ __device__ unsigned int optixGetAttribute_4()
1878 {
1879     OPTIX_DEFINE_optixGetAttribute_BODY(4);
1880 }
1881
1882 static __forceinline__ __device__ unsigned int optixGetAttribute_5()
1883 {
1884     OPTIX_DEFINE_optixGetAttribute_BODY(5);
1885 }
1886
1887 static __forceinline__ __device__ unsigned int optixGetAttribute_6()
1888 {
1889     OPTIX_DEFINE_optixGetAttribute_BODY(6);
1890 }
1891
1892 static __forceinline__ __device__ unsigned int optixGetAttribute_7()
1893 {
1894     OPTIX_DEFINE_optixGetAttribute_BODY(7);
1895 }
1896
1897 #undef OPTIX_DEFINE_optixGetAttribute_BODY
1898
1899 static __forceinline__ __device__ void optixTerminateRay()
1900 {
1901     asm volatile("call _optix_terminate_ray, ();");
1902 }
1903
1904 static __forceinline__ __device__ void optixIgnoreIntersection()
1905 {
1906     asm volatile("call _optix_ignore_intersection, ();");
1907 }
1908
1909 static __forceinline__ __device__ unsigned int optixGetPrimitiveIndex()
1910 {
1911     unsigned int u0;
1912     asm("call (%0), _optix_read_primitive_idx, ();" : "=r"(u0) :);
1913     return u0;
1914 }
1915
1916 static __forceinline__ __device__ unsigned int optixGetSbtGASIndex()
1917 {
1918     unsigned int u0;
1919     asm("call (%0), _optix_read_sbt_gas_idx, ();" : "=r"(u0) :);
1920     return u0;
1921 }
1922
1923 static __forceinline__ __device__ unsigned int optixGetInstanceId()

```

```

1924 {
1925     unsigned int u0;
1926     asm("call (%0), _optix_read_instance_id, ();" : "=r"(u0) :);
1927     return u0;
1928 }
1929
1930 static __forceinline__ __device__ unsigned int optixGetInstanceIndex()
1931 {
1932     unsigned int u0;
1933     asm("call (%0), _optix_read_instance_idx, ();" : "=r"(u0) :);
1934     return u0;
1935 }
1936
1937 static __forceinline__ __device__ unsigned int optixGetHitKind()
1938 {
1939     unsigned int u0;
1940     asm("call (%0), _optix_get_hit_kind, ();" : "=r"(u0) :);
1941     return u0;
1942 }
1943
1944 static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType(unsigned int hitKind)
1945 {
1946     unsigned int u0;
1947     asm("call (%0), _optix_get_primitive_type_from_hit_kind, (%1);" : "=r"(u0) : "r"(hitKind));
1948     return (OptixPrimitiveType)u0;
1949 }
1950
1951 static __forceinline__ __device__ bool optixIsBackFaceHit(unsigned int hitKind)
1952 {
1953     unsigned int u0;
1954     asm("call (%0), _optix_get_backface_from_hit_kind, (%1);" : "=r"(u0) : "r"(hitKind));
1955     return (u0 == 0x1);
1956 }
1957
1958 static __forceinline__ __device__ bool optixIsFrontFaceHit(unsigned int hitKind)
1959 {
1960     return !optixIsBackFaceHit(hitKind);
1961 }
1962
1963
1964 static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType()
1965 {
1966     return optixGetPrimitiveType(optixGetHitKind());
1967 }
1968
1969 static __forceinline__ __device__ bool optixIsBackFaceHit()
1970 {
1971     return optixIsBackFaceHit(optixGetHitKind());
1972 }
1973
1974 static __forceinline__ __device__ bool optixIsFrontFaceHit()
1975 {
1976     return optixIsFrontFaceHit(optixGetHitKind());
1977 }
1978
1979 static __forceinline__ __device__ bool optixIsTriangleHit()
1980 {
1981     return optixIsTriangleFrontFaceHit() || optixIsTriangleBackFaceHit();
1982 }
1983
1984 static __forceinline__ __device__ bool optixIsTriangleFrontFaceHit()
1985 {
1986     return optixGetHitKind() == OPTIX_HIT_KIND_TRIANGLE_FRONT_FACE;
1987 }
1988
1989 static __forceinline__ __device__ bool optixIsTriangleBackFaceHit()
1990 {

```

```

1991     return optixGetHitKind() == OPTIX_HIT_KIND_TRIANGLE_BACK_FACE;
1992 }
1993
1994 static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleHit()
1995 {
1996     return optixGetPrimitiveType(optixGetHitKind()) ==
OPTIX_PRIMITIVE_TYPE_DISPLACED_MICROMESH_TRIANGLE;
1997 }
1998
1999 static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleFrontFaceHit()
2000 {
2001     return optixIsDisplacedMicromeshTriangleHit() && optixIsFrontFaceHit();
2002 }
2003
2004 static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleBackFaceHit()
2005 {
2006     return optixIsDisplacedMicromeshTriangleHit() && optixIsBackFaceHit();
2007 }
2008
2009 static __forceinline__ __device__ float optixGetCurveParameter()
2010 {
2011     float f0;
2012     asm("call (%0), _optix_get_curve_parameter, ();" : "=f"(f0) :);
2013     return f0;
2014 }
2015
2016 static __forceinline__ __device__ float2 optixGetRibbonParameters()
2017 {
2018     float f0, f1;
2019     asm("call (%0, %1), _optix_get_ribbon_parameters, ();" : "=f"(f0), "=f"(f1) :);
2020     return make_float2(f0, f1);
2021 }
2022
2023 static __forceinline__ __device__ float2 optixGetTriangleBarycentrics()
2024 {
2025     float f0, f1;
2026     asm("call (%0, %1), _optix_get_triangle_barycentrics, ();" : "=f"(f0), "=f"(f1) :);
2027     return make_float2(f0, f1);
2028 }
2029
2030 static __forceinline__ __device__ uint3 optixGetLaunchIndex()
2031 {
2032     unsigned int u0, u1, u2;
2033     asm("call (%0), _optix_get_launch_index_x, ();" : "=r"(u0) :);
2034     asm("call (%0), _optix_get_launch_index_y, ();" : "=r"(u1) :);
2035     asm("call (%0), _optix_get_launch_index_z, ();" : "=r"(u2) :);
2036     return make_uint3(u0, u1, u2);
2037 }
2038
2039 static __forceinline__ __device__ uint3 optixGetLaunchDimensions()
2040 {
2041     unsigned int u0, u1, u2;
2042     asm("call (%0), _optix_get_launch_dimension_x, ();" : "=r"(u0) :);
2043     asm("call (%0), _optix_get_launch_dimension_y, ();" : "=r"(u1) :);
2044     asm("call (%0), _optix_get_launch_dimension_z, ();" : "=r"(u2) :);
2045     return make_uint3(u0, u1, u2);
2046 }
2047
2048 static __forceinline__ __device__ CUdeviceptr optixGetSbtDataPointer()
2049 {
2050     unsigned long long ptr;
2051     asm("call (%0), _optix_get_sbt_data_ptr_64, ();" : "=l"(ptr) :);
2052     return (CUdeviceptr)ptr;
2053 }
2054
2055 static __forceinline__ __device__ void optixThrowException(int exceptionCode)
2056 {

```

```

2057     asm volatile(
2058         "call _optix_throw_exception_0, (%0);"
2059         : /* no return value */
2060         : "r"(exceptionCode)
2061         :);
2062 }
2063
2064 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0)
2065 {
2066     asm volatile(
2067         "call _optix_throw_exception_1, (%0, %1);"
2068         : /* no return value */
2069         : "r"(exceptionCode), "r"(exceptionDetail0)
2070         :);
2071 }
2072
2073 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1)
2074 {
2075     asm volatile(
2076         "call _optix_throw_exception_2, (%0, %1, %2);"
2077         : /* no return value */
2078         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1)
2079         :);
2080 }
2081
2082 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2)
2083 {
2084     asm volatile(
2085         "call _optix_throw_exception_3, (%0, %1, %2, %3);"
2086         : /* no return value */
2087         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1), "r"(exceptionDetail2)
2088         :);
2089 }
2090
2091 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int
exceptionDetail3)
2092 {
2093     asm volatile(
2094         "call _optix_throw_exception_4, (%0, %1, %2, %3, %4);"
2095         : /* no return value */
2096         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1), "r"(exceptionDetail2),
"r"(exceptionDetail3)
2097         :);
2098 }
2099
2100 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int
exceptionDetail3, unsigned int exceptionDetail4)
2101 {
2102     asm volatile(
2103         "call _optix_throw_exception_5, (%0, %1, %2, %3, %4, %5);"
2104         : /* no return value */
2105         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1), "r"(exceptionDetail2),
"r"(exceptionDetail3), "r"(exceptionDetail4)
2106         :);
2107 }
2108
2109 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int
exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5)
2110 {
2111     asm volatile(
2112         "call _optix_throw_exception_6, (%0, %1, %2, %3, %4, %5, %6);"

```

```

2113         : /* no return value */
2114         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1), "r"(exceptionDetail2),
2115         : "r"(exceptionDetail3), "r"(exceptionDetail4), "r"(exceptionDetail5)
2116         :);
2117 }
2118 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int
exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int
exceptionDetail6)
2119 {
2120     asm volatile(
2121         "call _optix_throw_exception_7, (%0, %1, %2, %3, %4, %5, %6, %7);"
2122         : /* no return value */
2123         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1), "r"(exceptionDetail2),
2124         : "r"(exceptionDetail3), "r"(exceptionDetail4), "r"(exceptionDetail5), "r"(exceptionDetail6)
2125         :);
2126 }
2127 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int
exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int
exceptionDetail6, unsigned int exceptionDetail7)
2128 {
2129     asm volatile(
2130         "call _optix_throw_exception_8, (%0, %1, %2, %3, %4, %5, %6, %7, %8);"
2131         : /* no return value */
2132         : "r"(exceptionCode), "r"(exceptionDetail0), "r"(exceptionDetail1), "r"(exceptionDetail2),
2133         : "r"(exceptionDetail3), "r"(exceptionDetail4), "r"(exceptionDetail5), "r"(exceptionDetail6),
2134         : "r"(exceptionDetail7)
2135         :);
2136 }
2137 static __forceinline__ __device__ int optixGetExceptionCode()
2138 {
2139     int s0;
2140     asm("call (%0), _optix_get_exception_code, ();" : "=r"(s0) :);
2141     return s0;
2142 }
2143 #define OPTIX_DEFINE_optixGetExceptionDetail_BODY(which)
2144 \
2145 unsigned int ret;
2146 \
2147 asm("call (%0), _optix_get_exception_detail_" #which ", ();" : "=r"(ret) :);
2148 \
2149 return ret;
2150 }
2151 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_0()
2152 {
2153     OPTIX_DEFINE_optixGetExceptionDetail_BODY(0);
2154 }
2155 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_1()
2156 {
2157     OPTIX_DEFINE_optixGetExceptionDetail_BODY(1);
2158 }
2159 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_2()
2160 {
2161     OPTIX_DEFINE_optixGetExceptionDetail_BODY(2);
2162 }
2163 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_3()
2164 {
2165     OPTIX_DEFINE_optixGetExceptionDetail_BODY(3);
2166 }

```

```

2167
2168 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_4()
2169 {
2170     OPTIX_DEFINE_optixGetExceptionDetail_BODY(4);
2171 }
2172
2173 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_5()
2174 {
2175     OPTIX_DEFINE_optixGetExceptionDetail_BODY(5);
2176 }
2177
2178 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_6()
2179 {
2180     OPTIX_DEFINE_optixGetExceptionDetail_BODY(6);
2181 }
2182
2183 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_7()
2184 {
2185     OPTIX_DEFINE_optixGetExceptionDetail_BODY(7);
2186 }
2187
2188 #undef OPTIX_DEFINE_optixGetExceptionDetail_BODY
2189
2190
2191 static __forceinline__ __device__ char* optixGetExceptionLineInfo()
2192 {
2193     unsigned long long ptr;
2194     asm("call (%0), _optix_get_exception_line_info, ();" : "=l"(ptr) :);
2195     return (char*)ptr;
2196 }
2197
2198 template <typename ReturnT, typename... ArgTypes>
2199 static __forceinline__ __device__ ReturnT optixDirectCall(unsigned int sbtIndex, ArgTypes... args)
2200 {
2201     unsigned long long func;
2202     asm("call (%0), _optix_call_direct_callable, (%1);" : "=l"(func) : "r"(sbtIndex) :);
2203     using funcT = ReturnT (*)(ArgTypes...);
2204     funcT call = (funcT)(func);
2205     return call(args...);
2206 }
2207
2208 template <typename ReturnT, typename... ArgTypes>
2209 static __forceinline__ __device__ ReturnT optixContinuationCall(unsigned int sbtIndex, ArgTypes... args)
2210 {
2211     unsigned long long func;
2212     asm("call (%0), _optix_call_continuation_callable, (%1);" : "=l"(func) : "r"(sbtIndex) :);
2213     using funcT = ReturnT (*)(ArgTypes...);
2214     funcT call = (funcT)(func);
2215     return call(args...);
2216 }
2217
2218 static __forceinline__ __device__ uint4 optixTexFootprint2D(unsigned long long tex, unsigned int
texInfo, float x, float y, unsigned int* singleMipLevel)
2219 {
2220     uint4 result;
2221     unsigned long long resultPtr = reinterpret_cast<unsigned long long>(&result);
2222     unsigned long long singleMipLevelPtr = reinterpret_cast<unsigned long long>(singleMipLevel);
2223     // Cast float args to integers, because the intrinsics take .b32 arguments when compiled to PTX.
2224     asm volatile(
2225         "call _optix_tex_footprint_2d_v2"
2226         ", (%0, %1, %2, %3, %4, %5);"
2227         :
2228         : "l"(tex), "r"(texInfo), "r"(__float_as_uint(x)), "r"(__float_as_uint(y)),
2229         "l"(singleMipLevelPtr), "l"(resultPtr)
2230         :);
2231     return result;
2232 }

```

```

2233
2234 static __forceinline__ __device__ uint4 optixTexFootprint2DGrad(unsigned long long tex,
2235  unsigned int    texInfo,
2236  float          x,
2237  float          y,
2238  float          dPdx_x,
2239  float          dPdx_y,
2240  float          dPdy_x,
2241  float          dPdy_y,
2242  bool           coarse,
2243  unsigned int*  singleMipLevel)
2244 {
2245     uint4          result;
2246     unsigned long long resultPtr      = reinterpret_cast<unsigned long long>(&result);
2247     unsigned long long singleMipLevelPtr = reinterpret_cast<unsigned long long>(singleMipLevel);
2248     // Cast float args to integers, because the intrinsics take .b32 arguments when compiled to PTX.
2249     asm volatile(
2250         "call _optix_tex_footprint_2d_grad_v2"
2251         ", (%0, %1, %2, %3, %4, %5, %6, %7, %8, %9, %10);"
2252         :
2253         : "l"(tex), "r"(texInfo), "r"(__float_as_uint(x)), "r"(__float_as_uint(y)),
2254           "r"(__float_as_uint(dPdx_x)), "r"(__float_as_uint(dPdx_y)), "r"(__float_as_uint(dPdy_x)),
2255           "r"(__float_as_uint(dPdy_y)), "r"(static_cast<unsigned int>(coarse)), "l"(singleMipLevelPtr),
2256           "l"(resultPtr)
2257         :);
2258     return result;
2259 }
2260
2261 static __forceinline__ __device__ uint4
2262 optixTexFootprint2DLod(unsigned long long tex, unsigned int texInfo, float x, float y, float level, bool
coarse, unsigned int* singleMipLevel)
2263 {
2264     uint4          result;
2265     unsigned long long resultPtr      = reinterpret_cast<unsigned long long>(&result);
2266     unsigned long long singleMipLevelPtr = reinterpret_cast<unsigned long long>(singleMipLevel);
2267     // Cast float args to integers, because the intrinsics take .b32 arguments when compiled to PTX.
2268     asm volatile(
2269         "call _optix_tex_footprint_2d_lod_v2"
2270         ", (%0, %1, %2, %3, %4, %5, %6, %7);"
2271         :
2272         : "l"(tex), "r"(texInfo), "r"(__float_as_uint(x)), "r"(__float_as_uint(y)),
2273           "r"(__float_as_uint(level)), "r"(static_cast<unsigned int>(coarse)), "l"(singleMipLevelPtr),
2274           "l"(resultPtr)
2275         :);
2276     return result;
2277 }
2278 #endif // OPTIX_DEVICE_IMPL_H

```

## 8.3 optix\_device\_impl\_transformations.h File Reference

### Namespaces

- namespace [optix\\_impl](#)

### Functions

- static \_\_forceinline\_\_ \_\_device\_\_ float4 [optix\\_impl::optixAddFloat4](#) (const float4 &a, const float4 &b)
- static \_\_forceinline\_\_ \_\_device\_\_ float4 [optix\\_impl::optixMulFloat4](#) (const float4 &a, float b)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 [optix\\_impl::optixLdg](#) (unsigned long long addr)
- template<class T >  
static \_\_forceinline\_\_ \_\_device\_\_ T [optix\\_impl::optixLoadReadOnlyAlign16](#) (const T \*ptr)

- static \_\_forceinline\_\_ \_\_device\_\_ float4 `optix_impl::optixMultiplyRowMatrix` (const float4 vec, const float4 m0, const float4 m1, const float4 m2)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixGetMatrixFromSrt` (float4 &m0, float4 &m1, float4 &m2, const `OptixSRTData` &srt)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixInvertMatrix` (float4 &m0, float4 &m1, float4 &m2)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixLoadInterpolatedMatrixKey` (float4 &m0, float4 &m1, float4 &m2, const float4 \*matrix, const float t1)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixLoadInterpolatedSrtKey` (float4 &srt0, float4 &srt1, float4 &srt2, float4 &srt3, const float4 \*srt, const float t1)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixResolveMotionKey` (float &localt, int &key, const `OptixMotionOptions` &options, const float globalt)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixGetInterpolatedTransformation` (float4 &trf0, float4 &trf1, float4 &trf2, const `OptixMatrixMotionTransform` \*transformData, const float time)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixGetInterpolatedTransformation` (float4 &trf0, float4 &trf1, float4 &trf2, const `OptixSRTMotionTransform` \*transformData, const float time)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixGetInterpolatedTransformationFromHandle` (float4 &trf0, float4 &trf1, float4 &trf2, const `OptixTraversableHandle` handle, const float time, const bool objectToWorld)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixGetWorldToObjectTransformMatrix` (float4 &m0, float4 &m1, float4 &m2)
- static \_\_forceinline\_\_ \_\_device\_\_ void `optix_impl::optixGetObjectToWorldTransformMatrix` (float4 &m0, float4 &m1, float4 &m2)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 `optix_impl::optixTransformPoint` (const float4 &m0, const float4 &m1, const float4 &m2, const float3 &p)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 `optix_impl::optixTransformVector` (const float4 &m0, const float4 &m1, const float4 &m2, const float3 &v)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 `optix_impl::optixTransformNormal` (const float4 &m0, const float4 &m1, const float4 &m2, const float3 &n)

### 8.3.1 Detailed Description

OptiX public API.

Author

NVIDIA Corporation

OptiX public API Reference - Device side implementation for transformation helper functions.

## 8.4 optix\_device\_impl\_transformations.h

[Go to the documentation of this file.](#)

```

1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
5  * rights in and to this software, related documentation and any modifications thereto.
6  * Any use, reproduction, disclosure or distribution of this software and related
7  * documentation without an express license agreement from NVIDIA Corporation is strictly
8  * prohibited.
9  *
10 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
```



```

11 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
12 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A
13 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
14 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
15 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
16 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
17 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
18 * SUCH DAMAGES
19 */
20
21 #if !defined(__OPTIX_INCLUDE_INTERNAL_HEADERS__)
22 #error("optix_device_impl_transformations.h is an internal header file and must not be used directly.
Please use optix_device.h or optix.h instead.")
23 #endif
24
25 #ifndef OPTIX_DEVICE_IMPL_TRANSFORMATIONS_H
26 #define OPTIX_DEVICE_IMPL_TRANSFORMATIONS_H
27
28 namespace optix_impl {
29
30 static __forceinline__ __device__ float4 optixAddFloat4(const float4& a, const float4& b)
31 {
32     return make_float4(a.x + b.x, a.y + b.y, a.z + b.z, a.w + b.w);
33 }
34
35 static __forceinline__ __device__ float4 optixMulFloat4(const float4& a, float b)
36 {
37     return make_float4(a.x * b, a.y * b, a.z * b, a.w * b);
38 }
39
40 static __forceinline__ __device__ uint4 optixLdg(unsigned long long addr)
41 {
42     const uint4* ptr;
43     asm volatile("cvta.to.global.u64 %0, %1;" : "=l"(ptr) : "l"(addr));
44     uint4 ret;
45     asm volatile("ld.global.v4.u32 {%0,%1,%2,%3}, [%4];"
46                 : "=r"(ret.x), "=r"(ret.y), "=r"(ret.z), "=r"(ret.w)
47                 : "l"(ptr));
48     return ret;
49 }
50
51 template <class T>
52 static __forceinline__ __device__ T optixLoadReadOnlyAlign16(const T* ptr)
53 {
54     // Debug mode may keep this temporary variable
55     // If T does not enforce 16B alignment, v may not be 16B aligned and storing the loaded data from ptr
56     // fails
57     __align__(16) T v;
58     for(int ofs = 0; ofs < sizeof(T); ofs += 16)
59         *(uint4*)((char*)&v + ofs) = optixLdg((unsigned long long)((char*)ptr + ofs));
60     return v;
61 }
62
63 // Multiplies the row vector vec with the 3x4 matrix with rows m0, m1, and m2
64 static __forceinline__ __device__ float4 optixMultiplyRowMatrix(const float4 vec, const float4 m0, const
float4 m1, const float4 m2)
65 {
66     float4 result;
67
68     result.x = vec.x * m0.x + vec.y * m1.x + vec.z * m2.x;
69     result.y = vec.x * m0.y + vec.y * m1.y + vec.z * m2.y;
70     result.z = vec.x * m0.z + vec.y * m1.z + vec.z * m2.z;
71     result.w = vec.x * m0.w + vec.y * m1.w + vec.z * m2.w + vec.w;
72
73     return result;
74 }
75
76
77

```

```

83 // Converts the SRT transformation srt into a 3x4 matrix with rows m0, m1, and m2
84 static __forceinline__ __device__ void optixGetMatrixFromSrt(float4& m0, float4& m1, float4& m2, const
OptixSRTData& srt)
85 {
86     const float4 q = {srt.qx, srt.qy, srt.qz, srt.qw};
87
88     // normalize
89     const float inv_sq1 = 1.f / (srt.qx * srt.qx + srt.qy * srt.qy + srt.qz * srt.qz + srt.qw * srt.qw);
90     const float4 nq = optixMulFloat4(q, inv_sq1);
91
92     const float sqw = q.w * nq.w;
93     const float sqx = q.x * nq.x;
94     const float sqy = q.y * nq.y;
95     const float sqz = q.z * nq.z;
96
97     const float xy = q.x * nq.y;
98     const float zw = q.z * nq.w;
99     const float xz = q.x * nq.z;
100     const float yw = q.y * nq.w;
101     const float yz = q.y * nq.z;
102     const float xw = q.x * nq.w;
103
104     m0.x = (sqx - sqy - sqz + sqw);
105     m0.y = 2.0f * (xy - zw);
106     m0.z = 2.0f * (xz + yw);
107
108     m1.x = 2.0f * (xy + zw);
109     m1.y = (-sqx + sqy - sqz + sqw);
110     m1.z = 2.0f * (yz - xw);
111
112     m2.x = 2.0f * (xz - yw);
113     m2.y = 2.0f * (yz + xw);
114     m2.z = (-sqx - sqy + sqz + sqw);
115
116     m0.w = m0.x * srt.pvx + m0.y * srt.pvy + m0.z * srt.pvz + srt.tx;
117     m1.w = m1.x * srt.pvx + m1.y * srt.pvy + m1.z * srt.pvz + srt.ty;
118     m2.w = m2.x * srt.pvx + m2.y * srt.pvy + m2.z * srt.pvz + srt.tz;
119
120     m0.z = m0.x * srt.b + m0.y * srt.c + m0.z * srt.sz;
121     m1.z = m1.x * srt.b + m1.y * srt.c + m1.z * srt.sz;
122     m2.z = m2.x * srt.b + m2.y * srt.c + m2.z * srt.sz;
123
124     m0.y = m0.x * srt.a + m0.y * srt.sy;
125     m1.y = m1.x * srt.a + m1.y * srt.sy;
126     m2.y = m2.x * srt.a + m2.y * srt.sy;
127
128     m0.x = m0.x * srt.sx;
129     m1.x = m1.x * srt.sx;
130     m2.x = m2.x * srt.sx;
131 }
132
133 // Inverts a 3x4 matrix in place
134 static __forceinline__ __device__ void optixInvertMatrix(float4& m0, float4& m1, float4& m2)
135 {
136     const float det3 =
137         m0.x * (m1.y * m2.z - m1.z * m2.y) - m0.y * (m1.x * m2.z - m1.z * m2.x) + m0.z * (m1.x * m2.y -
m1.y * m2.x);
138
139     const float inv_det3 = 1.0f / det3;
140
141     float inv3[3][3];
142     inv3[0][0] = inv_det3 * (m1.y * m2.z - m2.y * m1.z);
143     inv3[0][1] = inv_det3 * (m0.z * m2.y - m2.z * m0.y);
144     inv3[0][2] = inv_det3 * (m0.y * m1.z - m1.y * m0.z);
145
146     inv3[1][0] = inv_det3 * (m1.z * m2.x - m2.z * m1.x);
147     inv3[1][1] = inv_det3 * (m0.x * m2.z - m2.x * m0.z);

```

```

148     inv3[1][2] = inv_det3 * (m0.z * m1.x - m1.z * m0.x);
149
150     inv3[2][0] = inv_det3 * (m1.x * m2.y - m2.x * m1.y);
151     inv3[2][1] = inv_det3 * (m0.y * m2.x - m2.y * m0.x);
152     inv3[2][2] = inv_det3 * (m0.x * m1.y - m1.x * m0.y);
153
154     const float b[3] = {m0.w, m1.w, m2.w};
155
156     m0.x = inv3[0][0];
157     m0.y = inv3[0][1];
158     m0.z = inv3[0][2];
159     m0.w = -inv3[0][0] * b[0] - inv3[0][1] * b[1] - inv3[0][2] * b[2];
160
161     m1.x = inv3[1][0];
162     m1.y = inv3[1][1];
163     m1.z = inv3[1][2];
164     m1.w = -inv3[1][0] * b[0] - inv3[1][1] * b[1] - inv3[1][2] * b[2];
165
166     m2.x = inv3[2][0];
167     m2.y = inv3[2][1];
168     m2.z = inv3[2][2];
169     m2.w = -inv3[2][0] * b[0] - inv3[2][1] * b[1] - inv3[2][2] * b[2];
170 }
171
172 static __forceinline__ __device__ void optixLoadInterpolatedMatrixKey(float4& m0, float4& m1, float4&
m2, const float4* matrix, const float t1)
173 {
174     m0 = optixLoadReadOnlyAlign16(&matrix[0]);
175     m1 = optixLoadReadOnlyAlign16(&matrix[1]);
176     m2 = optixLoadReadOnlyAlign16(&matrix[2]);
177
178     // The conditional prevents concurrent loads leading to spills
179     if(t1 > 0.0f)
180     {
181         const float t0 = 1.0f - t1;
182         m0 = optixAddFloat4(optixMulFloat4(m0, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&matrix[3]),
t1));
183         m1 = optixAddFloat4(optixMulFloat4(m1, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&matrix[4]),
t1));
184         m2 = optixAddFloat4(optixMulFloat4(m2, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&matrix[5]),
t1));
185     }
186 }
187
188 static __forceinline__ __device__ void optixLoadInterpolatedSrtKey(float4&      srt0,
189                             float4&      srt1,
190                             float4&      srt2,
191                             float4&      srt3,
192                             const float4* srt,
193                             const float  t1)
194 {
195     srt0 = optixLoadReadOnlyAlign16(&srt[0]);
196     srt1 = optixLoadReadOnlyAlign16(&srt[1]);
197     srt2 = optixLoadReadOnlyAlign16(&srt[2]);
198     srt3 = optixLoadReadOnlyAlign16(&srt[3]);
199
200     // The conditional prevents concurrent loads leading to spills
201     if(t1 > 0.0f)
202     {
203         const float t0 = 1.0f - t1;
204         srt0 = optixAddFloat4(optixMulFloat4(srt0, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&srt[4]),
t1));
205         srt1 = optixAddFloat4(optixMulFloat4(srt1, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&srt[5]),
t1));
206         srt2 = optixAddFloat4(optixMulFloat4(srt2, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&srt[6]),
t1));
207         srt3 = optixAddFloat4(optixMulFloat4(srt3, t0), optixMulFloat4(optixLoadReadOnlyAlign16(&srt[7]),

```

```

t1));
208
209     float inv_length = 1.f / sqrt(srt2.y * srt2.y + srt2.z * srt2.z + srt2.w * srt2.w + srt3.x *
srt3.x);
210     srt2.y *= inv_length;
211     srt2.z *= inv_length;
212     srt2.w *= inv_length;
213     srt3.x *= inv_length;
214 }
215 }
216
217 static __forceinline__ __device__ void optixResolveMotionKey(float& localt, int& key, const
OptixMotionOptions& options, const float globalt)
218 {
219     const float timeBegin    = options.timeBegin;
220     const float timeEnd      = options.timeEnd;
221     const float numIntervals = (float)(options.numKeys - 1);
222
223     // No need to check the motion flags. If data originates from a valid transform list handle, then
globalt is in
224     // range, or vanish flags are not set.
225
226     // should be NaN or in [0,numIntervals]
227     float time = max(0.f, min(numIntervals, numIntervals * __fdividef(globalt - timeBegin, timeEnd -
timeBegin)));
228
229     // catch NaN (for example when timeBegin=timeEnd)
230     if(time != time)
231         time = 0.f;
232
233     const float fltKey = fminf(floorf(time), numIntervals - 1);
234
235     localt = time - fltKey;
236     key    = (int)fltKey;
237 }
238
239 // Returns the interpolated transformation matrix for a particular matrix motion transformation and point
in time.
240 static __forceinline__ __device__ void optixGetInterpolatedTransformation(float4&
trf0,
241                                     float4&                                trf1,
242                                     float4&                                trf2,
243                                     const OptixMatrixMotionTransform*
transformData,
244                                     const float                                time)
245 {
246     // Compute key and intra key time
247     float keyTime;
248     int    key;
249     optixResolveMotionKey(keyTime, key, optixLoadReadOnlyAlign16(transformData).motionOptions, time);
250
251     // Get pointer to left key
252     const float4* transform = (const float4*)&transformData->transform[key][0];
253
254     // Load and interpolate matrix keys
255     optixLoadInterpolatedMatrixKey(trf0, trf1, trf2, transform, keyTime);
256 }
257
258 // Returns the interpolated transformation matrix for a particular SRT motion transformation and point in
time.
259 static __forceinline__ __device__ void optixGetInterpolatedTransformation(float4&
trf0,
260                                     float4&                                trf1,
261                                     float4&                                trf2,
262                                     const OptixSRTMotionTransform*
transformData,
263                                     const float                                time)

```

```

264 {
265     // Compute key and intra key time
266     float keyTime;
267     int key;
268     optixResolveMotionKey(keyTime, key, optixLoadReadOnlyAlign16(transformData).motionOptions, time);
269
270     // Get pointer to left key
271     const float4* dataPtr = reinterpret_cast<const float4*>(&transformData->srtData[key]);
272
273     // Load and interpolated SRT keys
274     float4 data[4];
275     optixLoadInterpolatedSrtKey(data[0], data[1], data[2], data[3], dataPtr, keyTime);
276
277     OptixSRTData srt = {data[0].x, data[0].y, data[0].z, data[0].w, data[1].x, data[1].y, data[1].z,
278 data[1].w,
279 data[2].x, data[2].y, data[2].z, data[2].w, data[3].x, data[3].y, data[3].z,
280 data[3].w};
281
282     // Convert SRT into a matrix
283     optixGetMatrixFromSrt(trf0, trf1, trf2, srt);
284 }
285
286 // Returns the interpolated transformation matrix for a particular traversable handle and point in time.
287 static __forceinline__ __device__ void optixGetInterpolatedTransformationFromHandle(float4&
288 trf0,
289 float4&
290 trf1,
291 float4&
292 trf2,
293 const
294 OptixTraversableHandle handle,
295 const float
296 time,
297 const bool objectToWorld)
298 {
299     const OptixTransformType type = optixGetTransformTypeFromHandle(handle);
300
301     if(type == OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM || type ==
302 OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM)
303     {
304         if(type == OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM)
305         {
306             const OptixMatrixMotionTransform* transformData =
307             optixGetMatrixMotionTransformFromHandle(handle);
308             optixGetInterpolatedTransformation(trf0, trf1, trf2, transformData, time);
309         }
310         else
311         {
312             const OptixSRTMotionTransform* transformData = optixGetSRTMotionTransformFromHandle(handle);
313             optixGetInterpolatedTransformation(trf0, trf1, trf2, transformData, time);
314         }
315
316         if(!objectToWorld)
317             optixInvertMatrix(trf0, trf1, trf2);
318     }
319     else if(type == OPTIX_TRANSFORM_TYPE_INSTANCE || type == OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM)
320     {
321         const float4* transform;
322
323         if(type == OPTIX_TRANSFORM_TYPE_INSTANCE)
324         {
325             transform = (objectToWorld) ? optixGetInstanceTransformFromHandle(handle) :
326 optixGetInstanceInverseTransformFromHandle(handle);
327         }
328         else
329         {
330             const OptixStaticTransform* traversable = optixGetStaticTransformFromHandle(handle);

```

```

322         transform = (const float4*)((objectToWorld) ? traversable->transform :
traversable->invTransform);
323     }
324
325     trf0 = optixLoadReadOnlyAlign16(&transform[0]);
326     trf1 = optixLoadReadOnlyAlign16(&transform[1]);
327     trf2 = optixLoadReadOnlyAlign16(&transform[2]);
328 }
329 else
330 {
331     trf0 = {1.0f, 0.0f, 0.0f, 0.0f};
332     trf1 = {0.0f, 1.0f, 0.0f, 0.0f};
333     trf2 = {0.0f, 0.0f, 1.0f, 0.0f};
334 }
335 }
336
337 // Returns the world-to-object transformation matrix resulting from the current transform stack and
current ray time.
338 static __forceinline__ __device__ void optixGetWorldToObjectTransformMatrix(float4& m0, float4& m1,
float4& m2)
339 {
340     const unsigned int size = optixGetTransformListSize();
341     const float        time = optixGetRayTime();
342
343     #pragma unroll 1
344     for(unsigned int i = 0; i < size; ++i)
345     {
346         OptixTraversableHandle handle = optixGetTransformListHandle(i);
347
348         float4 trf0, trf1, trf2;
349         optixGetInterpolatedTransformationFromHandle(trf0, trf1, trf2, handle, time, /*objectToWorld*/
false);
350
351         if(i == 0)
352         {
353             m0 = trf0;
354             m1 = trf1;
355             m2 = trf2;
356         }
357         else
358         {
359             // m := trf * m
360             float4 tmp0 = m0, tmp1 = m1, tmp2 = m2;
361             m0 = optixMultiplyRowMatrix(trf0, tmp0, tmp1, tmp2);
362             m1 = optixMultiplyRowMatrix(trf1, tmp0, tmp1, tmp2);
363             m2 = optixMultiplyRowMatrix(trf2, tmp0, tmp1, tmp2);
364         }
365     }
366 }
367
368 // Returns the object-to-world transformation matrix resulting from the current transform stack and
current ray time.
369 static __forceinline__ __device__ void optixGetObjectToWorldTransformMatrix(float4& m0, float4& m1,
float4& m2)
370 {
371     const int    size = optixGetTransformListSize();
372     const float  time = optixGetRayTime();
373
374     #pragma unroll 1
375     for(int i = size - 1; i >= 0; --i)
376     {
377         OptixTraversableHandle handle = optixGetTransformListHandle(i);
378
379         float4 trf0, trf1, trf2;
380         optixGetInterpolatedTransformationFromHandle(trf0, trf1, trf2, handle, time, /*objectToWorld*/
true);
381

```

```

382         if(i == size - 1)
383         {
384             m0 = trf0;
385             m1 = trf1;
386             m2 = trf2;
387         }
388         else
389         {
390             // m := trf * m
391             float4 tmp0 = m0, tmp1 = m1, tmp2 = m2;
392             m0 = optixMultiplyRowMatrix(trf0, tmp0, tmp1, tmp2);
393             m1 = optixMultiplyRowMatrix(trf1, tmp0, tmp1, tmp2);
394             m2 = optixMultiplyRowMatrix(trf2, tmp0, tmp1, tmp2);
395         }
396     }
397 }
398
399 // Multiplies the 3x4 matrix with rows m0, m1, m2 with the point p.
400 static __forceinline__ __device__ float3 optixTransformPoint(const float4& m0, const float4& m1, const
float4& m2, const float3& p)
401 {
402     float3 result;
403     result.x = m0.x * p.x + m0.y * p.y + m0.z * p.z + m0.w;
404     result.y = m1.x * p.x + m1.y * p.y + m1.z * p.z + m1.w;
405     result.z = m2.x * p.x + m2.y * p.y + m2.z * p.z + m2.w;
406     return result;
407 }
408
409 // Multiplies the 3x3 linear submatrix of the 3x4 matrix with rows m0, m1, m2 with the vector v.
410 static __forceinline__ __device__ float3 optixTransformVector(const float4& m0, const float4& m1, const
float4& m2, const float3& v)
411 {
412     float3 result;
413     result.x = m0.x * v.x + m0.y * v.y + m0.z * v.z;
414     result.y = m1.x * v.x + m1.y * v.y + m1.z * v.z;
415     result.z = m2.x * v.x + m2.y * v.y + m2.z * v.z;
416     return result;
417 }
418
419 // Multiplies the transpose of the 3x3 linear submatrix of the 3x4 matrix with rows m0, m1, m2 with the
normal n.
420 // Note that the given matrix is supposed to be the inverse of the actual transformation matrix.
421 static __forceinline__ __device__ float3 optixTransformNormal(const float4& m0, const float4& m1, const
float4& m2, const float3& n)
422 {
423     float3 result;
424     result.x = m0.x * n.x + m1.x * n.y + m2.x * n.z;
425     result.y = m0.y * n.x + m1.y * n.y + m2.y * n.z;
426     result.z = m0.z * n.x + m1.z * n.y + m2.z * n.z;
427     return result;
428 }
429
430 } // namespace optix_impl
431
432 #endif // OPTIX_DEVICE_IMPL_TRANSFORMATIONS_H

```

## 8.5 optix\_micromap\_impl.h File Reference

### Namespaces

- namespace [optix\\_impl](#)

### Macros

- #define [OPTIX\\_MICROMAP\\_FUNC](#)
- #define [OPTIX\\_MICROMAP\\_INLINE\\_FUNC](#) [OPTIX\\_MICROMAP\\_FUNC](#) inline

- `#define OPTIX_MICROMAP_FLOAT2_SUB(a, b) { a.x - b.x, a.y - b.y }`

## Functions

- `OPTIX_MICROMAP_INLINE_FUNC float optix_impl::__uint_as_float (unsigned int x)`
- `OPTIX_MICROMAP_INLINE_FUNC unsigned int optix_impl::extractEvenBits (unsigned int x)`
- `OPTIX_MICROMAP_INLINE_FUNC unsigned int optix_impl::prefixEor (unsigned int x)`
- `OPTIX_MICROMAP_INLINE_FUNC void optix_impl::index2dbary (unsigned int index, unsigned int &u, unsigned int &v, unsigned int &w)`
- `OPTIX_MICROMAP_INLINE_FUNC void optix_impl::micro2bary (unsigned int index, unsigned int subdivisionLevel, float2 &bary0, float2 &bary1, float2 &bary2)`
- `OPTIX_MICROMAP_INLINE_FUNC float2 optix_impl::base2micro (const float2 &baseBarycentrics, const float2 microVertexBaseBarycentrics[3])`

### 8.5.1 Detailed Description

OptiX micromap helper functions.

Author

NVIDIA Corporation

### 8.5.2 Macro Definition Documentation

#### 8.5.2.1 OPTIX\_MICROMAP\_FUNC

```
#define OPTIX_MICROMAP_FUNC
```

## 8.6 optix\_micromap\_impl.h

[Go to the documentation of this file.](#)

```
1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * Redistribution and use in source and binary forms, with or without
5  * modification, are permitted provided that the following conditions
6  * are met:
7  * * Redistributions of source code must retain the above copyright
8  * notice, this list of conditions and the following disclaimer.
9  * * Redistributions in binary form must reproduce the above copyright
10 * notice, this list of conditions and the following disclaimer in the
11 * documentation and/or other materials provided with the distribution.
12 * * Neither the name of NVIDIA CORPORATION nor the names of its
13 * contributors may be used to endorse or promote products derived
14 * from this software without specific prior written permission.
15 *
16 * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS "AS IS" AND ANY
17 * EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
18 * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
19 * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
20 * CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
21 * EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
22 * PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
23 * PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY
24 * OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
25 * (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
26 * OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
27 */
28
29
```



```

36 #ifndef OPTIX_OPTIX_MICROMAP_IMPL_H
37 #define OPTIX_OPTIX_MICROMAP_IMPL_H
38
39 #ifndef OPTIX_MICROMAP_FUNC
40 #ifdef __CUDACC__
41 #define OPTIX_MICROMAP_FUNC __device__
42 #else
43 #define OPTIX_MICROMAP_FUNC
44 #endif
45 #endif
46
47 namespace optix_impl {
48
49 #define OPTIX_MICROMAP_INLINE_FUNC OPTIX_MICROMAP_FUNC inline
50
51 #ifdef __CUDACC__
52 // the device implementation of __uint_as_float is declared in cuda_runtime.h
53 #else
54 // the host implementation of __uint_as_float
55 OPTIX_MICROMAP_INLINE_FUNC float __uint_as_float(unsigned int x)
56 {
57     union { float f; unsigned int i; } var;
58     var.i = x;
59     return var.f;
60 }
61 #endif
62
63 // Extract even bits
64 OPTIX_MICROMAP_INLINE_FUNC unsigned int extractEvenBits(unsigned int x)
65 {
66     x &= 0x55555555;
67     x = (x | (x >> 1)) & 0x33333333;
68     x = (x | (x >> 2)) & 0x0f0f0f0f;
69     x = (x | (x >> 4)) & 0x00ff00ff;
70     x = (x | (x >> 8)) & 0x0000ffff;
71     return x;
72 }
73
74 // Calculate exclusive prefix or (log(n) XOR's and SHF's)
75 OPTIX_MICROMAP_INLINE_FUNC unsigned int prefixEor(unsigned int x)
76 {
77     x ^= x >> 1;
78     x ^= x >> 2;
79     x ^= x >> 4;
80     x ^= x >> 8;
81     return x;
82 }
83
84 // Convert distance along the curve to discrete barycentrics
85 OPTIX_MICROMAP_INLINE_FUNC void index2dbary(unsigned int index, unsigned int& u, unsigned int& v, unsigned
int& w)
86 {
87     unsigned int b0 = extractEvenBits(index);
88     unsigned int b1 = extractEvenBits(index >> 1);
89
90     unsigned int fx = prefixEor(b0);
91     unsigned int fy = prefixEor(b0 & ~b1);
92
93     unsigned int t = fy ^ b1;
94
95     u = (fx & ~t) | (b0 & ~t) | (~b0 & ~fx & t);
96     v = fy ^ b0;
97     w = (~fx & ~t) | (b0 & ~t) | (~b0 & fx & t);
98 }
99
100 // Compute barycentrics of a sub or micro triangle wrt a base triangle. The order of the returned

```

```

106 // bary0, bary1, bary2 matters and allows for using this function for sub triangles and the
107 // conversion from sub triangle to base triangle barycentric space
108 OPTIX_MICROMAP_INLINE_FUNC void micro2bary(unsigned int index, unsigned int subdivisionLevel, float2&
bary0, float2& bary1, float2& bary2)
109 {
110     if(subdivisionLevel == 0)
111     {
112         bary0 = { 0, 0 };
113         bary1 = { 1, 0 };
114         bary2 = { 0, 1 };
115         return;
116     }
117
118     unsigned int iu, iv, iw;
119     index2dbary(index, iu, iv, iw);
120
121     // we need to only look at "level" bits
122     iu = iu & ((1 « subdivisionLevel) - 1);
123     iv = iv & ((1 « subdivisionLevel) - 1);
124     iw = iw & ((1 « subdivisionLevel) - 1);
125
126     int yFlipped = (iu & 1) ^ (iv & 1) ^ (iw & 1) ^ 1;
127
128     int xFlipped = ((0x8888888888888888ull ^ 0xf000f000f000f000ull ^ 0xffff000000000000ull) » index) & 1;
129     xFlipped ^= ((0x8888888888888888ull ^ 0xf000f000f000f000ull ^ 0xffff000000000000ull) » (index »
6)) & 1;
130
131     const float levelScale = __uint_as_float((127u - subdivisionLevel) « 23);
132
133     // scale the barycentric coordinate to the global space/scale
134     float du = 1.f * levelScale;
135     float dv = 1.f * levelScale;
136
137     // scale the barycentric coordinate to the global space/scale
138     float u = (float)iu * levelScale;
139     float v = (float)iv * levelScale;
140
141     //      c      d
142     //      x-----x
143     //      / \    /
144     //     /   \ /
145     //    x-----x
146     //   a       b
147     //
148     // !xFlipped && !yFlipped: abc
149     // !xFlipped && yFlipped: cdb
150     // xFlipped && !yFlipped: bac
151     // xFlipped && yFlipped: dcb
152
153     bary0 = { u + xFlipped * du, v + yFlipped * dv };
154     bary1 = { u + (1-xFlipped) * du, v + yFlipped * dv };
155     bary2 = { u + yFlipped * du, v + (1-yFlipped) * dv };
156 }
157
158 // avoid any conflicts due to multiple definitions
159 #define OPTIX_MICROMAP_FLOAT2_SUB(a,b) { a.x - b.x, a.y - b.y }
160
161 // Compute barycentrics for micro triangle from base barycentrics
162 OPTIX_MICROMAP_INLINE_FUNC float2 base2micro(const float2& baseBarycentrics, const float2
microVertexBaseBarycentrics[3])
163 {
164     float2 baryV0P = OPTIX_MICROMAP_FLOAT2_SUB(baseBarycentrics, microVertexBaseBarycentrics[0]);
165     float2 baryV0V1 = OPTIX_MICROMAP_FLOAT2_SUB(microVertexBaseBarycentrics[1],
microVertexBaseBarycentrics[0]);
166     float2 baryV0V2 = OPTIX_MICROMAP_FLOAT2_SUB(microVertexBaseBarycentrics[2],
microVertexBaseBarycentrics[0]);
167

```

```

168     float rdetA = 1.f / (baryV0V1.x * baryV0V2.y - baryV0V1.y * baryV0V2.x);
169     float4 A      = { baryV0V2.y, -baryV0V2.x, -baryV0V1.y, baryV0V1.x };
170
171     float2 localUV;
172     localUV.x = rdetA * (baryV0P.x * A.x + baryV0P.y * A.y);
173     localUV.y = rdetA * (baryV0P.x * A.z + baryV0P.y * A.w);
174
175     return localUV;
176 }
177 #undef OPTIX_MICROMAP_FLOAT2_SUB
178 // end group optix_utilities
180
181 } // namespace optix_impl
182
183 #endif // OPTIX_OPTIX_MICROMAP_IMPL_H

```

## 8.7 optix.h File Reference

### Macros

- #define `OPTIX_VERSION` 80000

### 8.7.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

Includes the host api if compiling host code, includes the cuda api if compiling device code. For the math library routines include `optix_math.h`

### 8.7.2 Macro Definition Documentation

#### 8.7.2.1 OPTIX\_VERSION

```
#define OPTIX_VERSION 80000
```

The OptiX version.

- major = `OPTIX_VERSION/10000`
- minor = `(OPTIX_VERSION%10000)/100`
- micro = `OPTIX_VERSION%100`

## 8.8 optix.h

[Go to the documentation of this file.](#)

```

1
2 /*
3 * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
4 *
5 * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
6 * rights in and to this software, related documentation and any modifications thereto.
7 * Any use, reproduction, disclosure or distribution of this software and related
8 * documentation without an express license agreement from NVIDIA Corporation is strictly
9 * prohibited.
10 *
11 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
12 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
13 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A

```

```

14 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
15 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
16 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
17 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
18 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
19 * SUCH DAMAGES
20 */
21
28
29 #ifndef OPTIX_OPTIX_H
30 #define OPTIX_OPTIX_H
31
37 #define OPTIX_VERSION 80000
38
39
40 #ifdef __CUDACC__
41 #include "optix_device.h"
42 #else
43 #include "optix_host.h"
44 #endif
45
46
47 #endif // OPTIX_OPTIX_H

```

## 8.9 optix\_denoiser\_tiling.h File Reference

### Classes

- struct [OptixUtilDenoiserImageTile](#)

### Functions

- [OptixResult optixUtilGetPixelStride](#) (const [OptixImage2D](#) &image, unsigned int &pixelStrideInBytes)
- [OptixResult optixUtilDenoiserSplitImage](#) (const [OptixImage2D](#) &input, const [OptixImage2D](#) &output, unsigned int overlapWindowSizeInPixels, unsigned int tileWidth, unsigned int tileHeight, std::vector< [OptixUtilDenoiserImageTile](#) > &tiles)
- [OptixResult optixUtilDenoiserInvokeTiled](#) ([OptixDenoiser](#) denoiser, [CUstream](#) stream, const [OptixDenoiserParams](#) \*params, [CUdeviceptr](#) denoiserState, size\_t denoiserStateSizeInBytes, const [OptixDenoiserGuideLayer](#) \*guideLayer, const [OptixDenoiserLayer](#) \*layers, unsigned int numLayers, [CUdeviceptr](#) scratch, size\_t scratchSizeInBytes, unsigned int overlapWindowSizeInPixels, unsigned int tileWidth, unsigned int tileHeight)

### 8.9.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

## 8.10 optix\_denoiser\_tiling.h

[Go to the documentation of this file.](#)

```

1 /*
2 * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3 *
4 * Redistribution and use in source and binary forms, with or without
5 * modification, are permitted provided that the following conditions
6 * are met:
7 * * Redistributions of source code must retain the above copyright

```

```

8 *   notice, this list of conditions and the following disclaimer.
9 * * Redistributions in binary form must reproduce the above copyright
10 *   notice, this list of conditions and the following disclaimer in the
11 *   documentation and/or other materials provided with the distribution.
12 * * Neither the name of NVIDIA CORPORATION nor the names of its
13 *   contributors may be used to endorse or promote products derived
14 *   from this software without specific prior written permission.
15 *
16 * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS "AS IS" AND ANY
17 * EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
18 * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
19 * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
20 * CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
21 * EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
22 * PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
23 * PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY
24 * OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
25 * (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
26 * OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
27 */
28
29
30
31
32
33 #ifndef OPTIX_DENOISER_TILING_H
34 #define OPTIX_DENOISER_TILING_H
35
36 #include <optix.h>
37
38 #include <algorithm>
39 #include <vector>
40
41 #ifdef __cplusplus
42 extern "C" {
43 #endif
44
45 struct OptixUtilDenoiserImageTile
46 {
47     // input tile image
48     OptixImage2D input;
49
50     // output tile image
51     OptixImage2D output;
52
53     // overlap offsets, parameters for #optixUtilDenoiserInvoke
54     unsigned int inputOffsetX;
55     unsigned int inputOffsetY;
56 };
57
58 inline OptixResult optixUtilGetPixelStride(const OptixImage2D& image, unsigned int& pixelStrideInBytes)
59 {
60     pixelStrideInBytes = image.pixelStrideInBytes;
61     if(pixelStrideInBytes == 0)
62     {
63         switch(image.format)
64         {
65             case OPTIX_PIXEL_FORMAT_HALF1:
66                 pixelStrideInBytes = 1 * sizeof(short);
67                 break;
68             case OPTIX_PIXEL_FORMAT_HALF2:
69                 pixelStrideInBytes = 2 * sizeof(short);
70                 break;
71             case OPTIX_PIXEL_FORMAT_HALF3:
72                 pixelStrideInBytes = 3 * sizeof(short);
73                 break;
74             case OPTIX_PIXEL_FORMAT_HALF4:
75                 pixelStrideInBytes = 4 * sizeof(short);
76                 break;
77             case OPTIX_PIXEL_FORMAT_FLOAT1:

```

```

93         pixelStrideInBytes = 1 * sizeof(float);
94         break;
95     case OPTIX_PIXEL_FORMAT_FLOAT2:
96         pixelStrideInBytes = 2 * sizeof(float);
97         break;
98     case OPTIX_PIXEL_FORMAT_FLOAT3:
99         pixelStrideInBytes = 3 * sizeof(float);
100        break;
101    case OPTIX_PIXEL_FORMAT_FLOAT4:
102        pixelStrideInBytes = 4 * sizeof(float);
103        break;
104    case OPTIX_PIXEL_FORMAT_UCHAR3:
105        pixelStrideInBytes = 3 * sizeof(char);
106        break;
107    case OPTIX_PIXEL_FORMAT_UCHAR4:
108        pixelStrideInBytes = 4 * sizeof(char);
109        break;
110    case OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER:
111        return OPTIX_ERROR_INVALID_VALUE;
112        break;
113    }
114 }
115 return OPTIX_SUCCESS;
116 }
117
118 inline OptixResult optixUtilDenoiserSplitImage(
119     const OptixImage2D& input,
120     const OptixImage2D& output,
121     unsigned int overlapWindowSizeInPixels,
122     unsigned int tileWidth,
123     unsigned int tileHeight,
124     std::vector<OptixUtilDenoiserImageTile>& tiles)
125 {
126     if(tileWidth == 0 || tileHeight == 0)
127         return OPTIX_ERROR_INVALID_VALUE;
128
129     unsigned int inPixelStride, outPixelStride;
130     if(const OptixResult res = optixUtilGetPixelStride(input, inPixelStride))
131         return res;
132     if(const OptixResult res = optixUtilGetPixelStride(output, outPixelStride))
133         return res;
134
135     int inp_w = std::min(tileWidth + 2 * overlapWindowSizeInPixels, input.width);
136     int inp_h = std::min(tileHeight + 2 * overlapWindowSizeInPixels, input.height);
137     int inp_y = 0, copied_y = 0;
138
139     int upscaleX = output.width / input.width;
140     int upscaleY = output.height / input.height;
141
142     do
143     {
144         int inputOffsetY = inp_y == 0 ? 0 : std::max((int)overlapWindowSizeInPixels, inp_h -
145             ((int)input.height - inp_y));
146         int copy_y = inp_y == 0 ? std::min(input.height, tileHeight + overlapWindowSizeInPixels) :
147             std::min(tileHeight, input.height - copied_y);
148
149         int inp_x = 0, copied_x = 0;
150         do
151         {
152             int inputOffsetX = inp_x == 0 ? 0 : std::max((int)overlapWindowSizeInPixels, inp_w -
153                 ((int)input.width - inp_x));
154             int copy_x = inp_x == 0 ? std::min(input.width, tileWidth + overlapWindowSizeInPixels) :
155                 std::min(tileWidth, input.width - copied_x);
156
157             OptixUtilDenoiserImageTile tile;
158             tile.input.data = input.data + (size_t)(inp_y - inputOffsetY) *
159                 input.rowStrideInBytes

```

```

166                                     + (size_t)(inp_x - inputOffsetX) * inPixelStride;
167     tile.input.width                  = inp_w;
168     tile.input.height                = inp_h;
169     tile.input.rowStrideInBytes      = input.rowStrideInBytes;
170     tile.input.pixelStrideInBytes    = input.pixelStrideInBytes;
171     tile.input.format                 = input.format;
172
173     tile.output.data                  = output.data + (size_t)(upscaleY * inp_y) *
output.rowStrideInBytes
174                                     + (size_t)(upscaleX * inp_x) * outPixelStride;
175     tile.output.width                 = upscaleX * copy_x;
176     tile.output.height               = upscaleY * copy_y;
177     tile.output.rowStrideInBytes      = output.rowStrideInBytes;
178     tile.output.pixelStrideInBytes    = output.pixelStrideInBytes;
179     tile.output.format                = output.format;
180
181     tile.inputOffsetX = inputOffsetX;
182     tile.inputOffsetY = inputOffsetY;
183
184     tiles.push_back(tile);
185
186     inp_x += inp_x == 0 ? tileWidth + overlapWindowSizeInPixels : tileWidth;
187     copied_x += copy_x;
188     } while(inp_x < static_cast<int>(input.width));
189
190     inp_y += inp_y == 0 ? tileHeight + overlapWindowSizeInPixels : tileHeight;
191     copied_y += copy_y;
192     } while(inp_y < static_cast<int>(input.height));
193
194     return OPTIX_SUCCESS;
195 }
196
200
207
223 inline OptixResult optixUtilDenoiserInvokeTiled(
224     OptixDenoiser                    denoiser,
225     CUstream                          stream,
226     const OptixDenoiserParams*       params,
227     CUdeviceptr                      denoiserState,
228     size_t                           denoiserStateSizeInBytes,
229     const OptixDenoiserGuideLayer*   guideLayer,
230     const OptixDenoiserLayer*        layers,
231     unsigned int                     numLayers,
232     CUdeviceptr                      scratch,
233     size_t                           scratchSizeInBytes,
234     unsigned int                     overlapWindowSizeInPixels,
235     unsigned int                     tileWidth,
236     unsigned int                     tileHeight)
237 {
238     if(!guideLayer || !layers)
239         return OPTIX_ERROR_INVALID_VALUE;
240
241     const unsigned int upscale = numLayers > 0 && layers[0].previousOutput.width == 2 *
layers[0].input.width ? 2 : 1;
242
243     std::vector<std::vector<OptixUtilDenoiserImageTile>> tiles(numLayers);
244     std::vector<std::vector<OptixUtilDenoiserImageTile>> prevTiles(numLayers);
245     for(unsigned int l = 0; l < numLayers; l++)
246     {
247         if(const OptixResult res = optixUtilDenoiserSplitImage(layers[l].input, layers[l].output,
248   overlapWindowSizeInPixels,
249   tileWidth, tileHeight, tiles[l]))
250             return res;
251
252         if(layers[l].previousOutput.data)
253         {
254             OptixImage2D dummyOutput = layers[l].previousOutput;

```

```

255         if(const OptixResult res = optixUtilDenoiserSplitImage(layers[1].previousOutput, dummyOutput,
256   upscale * overlapWindowSizeInPixels,
257   upscale * tileWidth, upscale * tileHeight,
prevTiles[1]))
258             return res;
259     }
260 }
261
262 std::vector<OptixUtilDenoiserImageTile> albedoTiles;
263 if(guidelayer->albedo.data)
264 {
265     OptixImage2D dummyOutput = guidelayer->albedo;
266     if(const OptixResult res = optixUtilDenoiserSplitImage(guidelayer->albedo, dummyOutput,
267   overlapWindowSizeInPixels,
268   tileWidth, tileHeight, albedoTiles))
269         return res;
270 }
271
272 std::vector<OptixUtilDenoiserImageTile> normalTiles;
273 if(guidelayer->normal.data)
274 {
275     OptixImage2D dummyOutput = guidelayer->normal;
276     if(const OptixResult res = optixUtilDenoiserSplitImage(guidelayer->normal, dummyOutput,
277   overlapWindowSizeInPixels,
278   tileWidth, tileHeight, normalTiles))
279         return res;
280 }
281
282 std::vector<OptixUtilDenoiserImageTile> flowTiles;
283 if(guidelayer->flow.data)
284 {
285     OptixImage2D dummyOutput = guidelayer->flow;
286     if(const OptixResult res = optixUtilDenoiserSplitImage(guidelayer->flow, dummyOutput,
287   overlapWindowSizeInPixels,
288   tileWidth, tileHeight, flowTiles))
289         return res;
290 }
291
292 std::vector<OptixUtilDenoiserImageTile> flowTrustTiles;
293 if(guidelayer->flowTrustworthiness.data)
294 {
295     OptixImage2D dummyOutput = guidelayer->flowTrustworthiness;
296     if(const OptixResult res = optixUtilDenoiserSplitImage(guidelayer->flowTrustworthiness,
dummyOutput,
297   overlapWindowSizeInPixels,
298   tileWidth, tileHeight, flowTrustTiles))
299         return res;
300 }
301
302 std::vector<OptixUtilDenoiserImageTile> internalGuideLayerTiles;
303 if(guidelayer->previousOutputInternalGuideLayer.data && guidelayer->outputInternalGuideLayer.data)
304 {
305     if(const OptixResult res =
optixUtilDenoiserSplitImage(guidelayer->previousOutputInternalGuideLayer,
306   guidelayer->outputInternalGuideLayer,
307   upscale * overlapWindowSizeInPixels,
308   upscale * tileWidth, upscale * tileHeight,
internalGuideLayerTiles))
309         return res;
310 }
311
312 for(size_t t = 0; t < tiles[0].size(); t++)
313 {
314     std::vector<OptixDenoiserLayer> tlayers;
315     for(unsigned int l = 0; l < numLayers; l++)
316     {
317         OptixDenoiserLayer layer = {};

```



```

318         layer.input = (tiles[l])[t].input;
319         layer.output = (tiles[l])[t].output;
320         if(layers[l].previousOutput.data)
321             layer.previousOutput = (prevTiles[l])[t].input;
322         layer.type = layers[l].type;
323         tlayers.push_back(layer);
324     }
325
326     OptixDenoiserGuideLayer gl = {};
327     if(guideLayer->albedo.data)
328         gl.albedo = albedoTiles[t].input;
329
330     if(guideLayer->normal.data)
331         gl.normal = normalTiles[t].input;
332
333     if(guideLayer->flow.data)
334         gl.flow = flowTiles[t].input;
335
336     if(guideLayer->flowTrustworthiness.data)
337         gl.flowTrustworthiness = flowTrustTiles[t].input;
338
339     if(guideLayer->previousOutputInternalGuideLayer.data)
340         gl.previousOutputInternalGuideLayer = internalGuideLayerTiles[t].input;
341
342     if(guideLayer->outputInternalGuideLayer.data)
343         gl.outputInternalGuideLayer = internalGuideLayerTiles[t].output;
344
345     if(const OptixResult res =
346         optixDenoiserInvoke(denoiser, stream, params, denoiserState, denoiserStateSizeInBytes,
347                             &gl, &tlayers[0], numLayers,
348                             (tiles[0])[t].inputOffsetX, (tiles[0])[t].inputOffsetY,
349                             scratch, scratchSizeInBytes))
350         return res;
351     }
352     return OPTIX_SUCCESS;
353 }
354 // end group optix_utilities
355
356 #ifdef __cplusplus
357 }
358 #endif
359 #endif
360 #endif // OPTIX_DENOISER_TILING_H

```

## 8.11 optix\_device.h File Reference

### Macros

- `#define __OPTIX_INCLUDE_INTERNAL_HEADERS__`

### Functions

- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTrace (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`  
`static __forceinline__ __device__ void optixTraverse (OptixTraversableHandle handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, OptixVisibilityMask visibilityMask, unsigned int rayFlags, unsigned int SBTOffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)`
- `template<typename... Payload>`

- static \_\_forceinline\_\_ \_\_device\_\_ void **optixTrace** (**OptixPayloadTypeID** type, **OptixTraversableHandle** handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, **OptixVisibilityMask** visibilityMask, unsigned int rayFlags, unsigned int SBToffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)
- template<typename... Payload>  
static \_\_forceinline\_\_ \_\_device\_\_ void **optixTraverse** (**OptixPayloadTypeID** type, **OptixTraversableHandle** handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, **OptixVisibilityMask** visibilityMask, unsigned int rayFlags, unsigned int SBToffset, unsigned int SBTstride, unsigned int missSBTIndex, Payload &... payload)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixReorder** (unsigned int coherenceHint, unsigned int numCoherenceHintBitsFromLSB)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixReorder** ()
  - template<typename... Payload>  
static \_\_forceinline\_\_ \_\_device\_\_ void **optixInvoke** (Payload &... payload)
  - template<typename... Payload>  
static \_\_forceinline\_\_ \_\_device\_\_ void **optixInvoke** (**OptixPayloadTypeID** type, Payload &... payload)
  - template<typename... RegAttributes>  
static \_\_forceinline\_\_ \_\_device\_\_ void **optixMakeHitObject** (**OptixTraversableHandle** handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int SBToffset, unsigned int SBTstride, unsigned int instIdx, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind, RegAttributes... regAttributes)
  - template<typename... RegAttributes>  
static \_\_forceinline\_\_ \_\_device\_\_ void **optixMakeHitObject** (**OptixTraversableHandle** handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int SBToffset, unsigned int SBTstride, unsigned int instIdx, const **OptixTraversableHandle** \*transforms, unsigned int numTransforms, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind, RegAttributes... regAttributes)
  - template<typename... RegAttributes>  
static \_\_forceinline\_\_ \_\_device\_\_ void **optixMakeHitObjectWithRecord** (**OptixTraversableHandle** handle, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime, unsigned int sbtRecordIndex, unsigned int instIdx, const **OptixTraversableHandle** \*transforms, unsigned int numTransforms, unsigned int sbtGASIdx, unsigned int primIdx, unsigned int hitKind, RegAttributes... regAttributes)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixMakeMissHitObject** (unsigned int missSBTIndex, float3 rayOrigin, float3 rayDirection, float tmin, float tmax, float rayTime)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixMakeNopHitObject** ()
  - static \_\_forceinline\_\_ \_\_device\_\_ bool **optixHitObjectIsHit** ()
  - static \_\_forceinline\_\_ \_\_device\_\_ bool **optixHitObjectIsMiss** ()
  - static \_\_forceinline\_\_ \_\_device\_\_ bool **optixHitObjectIsNop** ()
  - static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetSbtRecordIndex** ()
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_0** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_1** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_2** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_3** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_4** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_5** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_6** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_7** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_8** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_9** (unsigned int p)
  - static \_\_forceinline\_\_ \_\_device\_\_ void **optixSetPayload\_10** (unsigned int p)

- NVIDIA OptiX 8.0 API

- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_29 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_30 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetPayload\_31 ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixSetPayloadTypes (unsigned int typeMask)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixUndefinedValue ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetWorldRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixHitObjectGetWorldRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetWorldRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixHitObjectGetWorldRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetObjectRayOrigin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetObjectRayDirection ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTmin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixHitObjectGetRayTmin ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTmax ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixHitObjectGetRayTmax ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetRayTime ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixHitObjectGetRayTime ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetRayFlags ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetRayVisibilityMask ()
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetInstanceTraversableFromIAS (OptixTraversableHandle ias, unsigned int instIdx)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetTriangleVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float3 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetMicroTriangleVertexData (float3 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetMicroTriangleBarycentricsData (float2 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetLinearCurveVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[2])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetQuadraticBSplineVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCubicBSplineVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCatmullRomVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetCubicBezierVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetRibbonVertexData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3])
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixGetRibbonNormal (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float2 ribbonParameters)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetSphereData (OptixTraversableHandle gas, unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[1])
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetGASTraversableHandle ()
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetGASMotionTimeBegin (OptixTraversableHandle gas)
- static \_\_forceinline\_\_ \_\_device\_\_ float optixGetGASMotionTimeEnd (OptixTraversableHandle gas)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetGASMotionStepCount (OptixTraversableHandle gas)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetWorldToObjectTransformMatrix (float m[12])
- static \_\_forceinline\_\_ \_\_device\_\_ void optixGetObjectToWorldTransformMatrix (float m[12])

- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformPointFromWorldToObjectSpace (float3 point)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformVectorFromWorldToObjectSpace (float3 vec)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformNormalFromWorldToObjectSpace (float3 normal)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformPointFromObjectToWorldSpace (float3 point)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformVectorFromObjectToWorldSpace (float3 vec)
- static \_\_forceinline\_\_ \_\_device\_\_ float3 optixTransformNormalFromObjectToWorldSpace (float3 normal)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetTransformListSize ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixHitObjectGetTransformListSize ()
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetTransformListHandle (unsigned int index)
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixHitObjectGetTransformListHandle (unsigned int index)
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTransformType optixGetTransformTypeFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ const OptixStaticTransform \* optixGetStaticTransformFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ const OptixSRTMotionTransform \* optixGetSRTMotionTransformFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ const OptixMatrixMotionTransform \* optixGetMatrixMotionTransformFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetInstanceIdFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ OptixTraversableHandle optixGetInstanceChildFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ const float4 \* optixGetInstanceTransformFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ const float4 \* optixGetInstanceInverseTransformFromHandle (OptixTraversableHandle handle)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5)
- static \_\_forceinline\_\_ \_\_device\_\_ bool optixReportIntersection (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5, unsigned int a6)



- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixReportIntersection** (float hitT, unsigned int hitKind, unsigned int a0, unsigned int a1, unsigned int a2, unsigned int a3, unsigned int a4, unsigned int a5, unsigned int a6, unsigned int a7)
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_0** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_1** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_2** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_3** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_4** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_5** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_6** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetAttribute\_7** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_0** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_1** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_2** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_3** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_4** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_5** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_6** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetAttribute\_7** ()
- static \_\_forceinline\_\_ \_\_device\_\_ void **optixTerminateRay** ()
- static \_\_forceinline\_\_ \_\_device\_\_ void **optixIgnoreIntersection** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetPrimitiveIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetPrimitiveIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetSbtGASIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetSbtGASIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetInstanceId** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetInstanceId** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetInstanceIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetInstanceIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixGetHitKind** ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int **optixHitObjectGetHitKind** ()
- static \_\_forceinline\_\_ \_\_device\_\_ **OptixPrimitiveType** **optixGetPrimitiveType** (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsFrontFaceHit** (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsBackFaceHit** (unsigned int hitKind)
- static \_\_forceinline\_\_ \_\_device\_\_ **OptixPrimitiveType** **optixGetPrimitiveType** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsFrontFaceHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsBackFaceHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsTriangleHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsTriangleFrontFaceHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsTriangleBackFaceHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsDisplacedMicromeshTriangleHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsDisplacedMicromeshTriangleFrontFaceHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ bool **optixIsDisplacedMicromeshTriangleBackFaceHit** ()
- static \_\_forceinline\_\_ \_\_device\_\_ float2 **optixGetTriangleBarycentrics** ()
- static \_\_forceinline\_\_ \_\_device\_\_ float **optixGetCurveParameter** ()
- static \_\_forceinline\_\_ \_\_device\_\_ float2 **optixGetRibbonParameters** ()
- static \_\_forceinline\_\_ \_\_device\_\_ uint3 **optixGetLaunchIndex** ()
- static \_\_forceinline\_\_ \_\_device\_\_ uint3 **optixGetLaunchDimensions** ()
- static \_\_forceinline\_\_ \_\_device\_\_ CUdeviceptr **optixGetSbtDataPointer** ()

- static \_\_forceinline\_\_ \_\_device\_\_ CUdeviceptr optixHitObjectGetSbtDataPointer ()
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int exceptionDetail6)
- static \_\_forceinline\_\_ \_\_device\_\_ void optixThrowException (int exceptionCode, unsigned int exceptionDetail0, unsigned int exceptionDetail1, unsigned int exceptionDetail2, unsigned int exceptionDetail3, unsigned int exceptionDetail4, unsigned int exceptionDetail5, unsigned int exceptionDetail6, unsigned int exceptionDetail7)
- static \_\_forceinline\_\_ \_\_device\_\_ int optixGetExceptionCode ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_0 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_1 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_2 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_3 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_4 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_5 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_6 ()
- static \_\_forceinline\_\_ \_\_device\_\_ unsigned int optixGetExceptionDetail\_7 ()
- static \_\_forceinline\_\_ \_\_device\_\_ char \* optixGetExceptionLineInfo ()
- template<typename ReturnT , typename... ArgTypes>  
static \_\_forceinline\_\_ \_\_device\_\_ ReturnT optixDirectCall (unsigned int sbtIndex, ArgTypes... args)
- template<typename ReturnT , typename... ArgTypes>  
static \_\_forceinline\_\_ \_\_device\_\_ ReturnT optixContinuationCall (unsigned int sbtIndex, ArgTypes... args)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 optixTexFootprint2D (unsigned long long tex, unsigned int texInfo, float x, float y, unsigned int \*singleMipLevel)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 optixTexFootprint2DLod (unsigned long long tex, unsigned int texInfo, float x, float y, float level, bool coarse, unsigned int \*singleMipLevel)
- static \_\_forceinline\_\_ \_\_device\_\_ uint4 optixTexFootprint2DGrad (unsigned long long tex, unsigned int texInfo, float x, float y, float dPdx\_x, float dPdx\_y, float dPdy\_x, float dPdy\_y, bool coarse, unsigned int \*singleMipLevel)

### 8.11.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

OptiX public API Reference - Device API declarations

### 8.11.2 Macro Definition Documentation

#### 8.11.2.1 \_\_OPTIX\_INCLUDE\_INTERNAL\_HEADERS\_\_

```
#define __OPTIX_INCLUDE_INTERNAL_HEADERS__
```

## 8.12 optix\_device.h

[Go to the documentation of this file.](#)

```
1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
5  * rights in and to this software, related documentation and any modifications thereto.
6  * Any use, reproduction, disclosure or distribution of this software and related
7  * documentation without an express license agreement from NVIDIA Corporation is strictly
8  * prohibited.
9  *
10 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
11 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
12 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A
13 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
14 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
15 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
16 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
17 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
18 * SUCH DAMAGES
19 */
20
26
27 #ifndef OPTIX_DEVICE_H
28 #define OPTIX_DEVICE_H
29
30 #if defined(__cplusplus) && (__cplusplus < 201103L) && !defined(_WIN32)
31 #error Device code for OptiX requires at least C++11. Consider adding "--std c++11" to the nvcc
32 #endif
33
34 #include "optix_types.h"
35
38
60 template <typename... Payload>
61 static __forceinline__ __device__ void optixTrace(OptixTraversableHandle handle,
62  float3 rayOrigin,
63  float3 rayDirection,
64  float tmin,
65  float tmax,
66  float rayTime,
67  OptixVisibilityMask visibilityMask,
68  unsigned int rayFlags,
69  unsigned int SBTOffset,
70  unsigned int SBTstride,
71  unsigned int missSBTIndex,
72  Payload&... payload);
```



```

73
93 template <typename... Payload>
94 static __forceinline__ __device__ void optixTraverse(OptixTraversableHandle handle,
95   float3          rayOrigin,
96   float3          rayDirection,
97   float          tmin,
98   float          tmax,
99   float          rayTime,
100   OptixVisibilityMask visibilityMask,
101   unsigned int    rayFlags,
102   unsigned int    SBTOffset,
103   unsigned int    SBTStride,
104   unsigned int    missSBTIndex,
105   Payload&... payload);
106
124 template <typename... Payload>
125 static __forceinline__ __device__ void optixTrace(OptixPayloadTypeID type,
126   OptixTraversableHandle handle,
127   float3          rayOrigin,
128   float3          rayDirection,
129   float          tmin,
130   float          tmax,
131   float          rayTime,
132   OptixVisibilityMask visibilityMask,
133   unsigned int    rayFlags,
134   unsigned int    SBTOffset,
135   unsigned int    SBTStride,
136   unsigned int    missSBTIndex,
137   Payload&...      payload);
138
159 template <typename... Payload>
160 static __forceinline__ __device__ void optixTraverse(OptixPayloadTypeID type,
161   OptixTraversableHandle handle,
162   float3          rayOrigin,
163   float3          rayDirection,
164   float          tmin,
165   float          tmax,
166   float          rayTime,
167   OptixVisibilityMask visibilityMask,
168   unsigned int    rayFlags,
169   unsigned int    SBTOffset,
170   unsigned int    SBTStride,
171   unsigned int    missSBTIndex,
172   Payload&... payload);
173
184 static __forceinline__ __device__ void optixReorder(unsigned int coherenceHint, unsigned int
numCoherenceHintBitsFromLSB);
185
189 static __forceinline__ __device__ void optixReorder();
190
199 template <typename... Payload>
200 static __forceinline__ __device__ void optixInvoke(Payload&... payload);
201
211 template <typename... Payload>
212 static __forceinline__ __device__ void optixInvoke(OptixPayloadTypeID type, Payload&... payload);
213
232 template <typename... RegAttributes>
233 static __forceinline__ __device__ void optixMakeHitObject(OptixTraversableHandle handle,
234   float3          rayOrigin,
235   float3          rayDirection,
236   float          tmin,
237   float          tmax,
238   float          rayTime,
239   unsigned int    SBTOffset,
240   unsigned int    SBTStride,
241   unsigned int    instIdx,
242   unsigned int    sbtGASIdx,

```

```

243                                     unsigned int      primIdx,
244                                     unsigned int      hitKind,
245                                     RegAttributes... regAttributes);
246
269 template <typename... RegAttributes>
270 static __forceinline__ __device__ void optixMakeHitObject(OptixTraversableHandle handle,
271   float3      rayOrigin,
272   float3      rayDirection,
273   float      tmin,
274   float      tmax,
275   float      rayTime,
276   unsigned int SBTOffset,
277   unsigned int SBTStride,
278   unsigned int instIdx,
279   const OptixTraversableHandle* transforms,
280   unsigned int numTransforms,
281   unsigned int sbtGASIdx,
282   unsigned int primIdx,
283   unsigned int hitKind,
284   RegAttributes... regAttributes);
285
306 template <typename... RegAttributes>
307 static __forceinline__ __device__ void optixMakeHitObjectWithRecord(OptixTraversableHandle handle,
308   float3      rayOrigin,
309   float3      rayDirection,
310   float      tmin,
311   float      tmax,
312   float      rayTime,
313   unsigned int sbtRecordIndex,
314   unsigned int instIdx,
315   const OptixTraversableHandle* transforms,
316   unsigned int numTransforms,
317   unsigned int sbtGASIdx,
318   unsigned int primIdx,
319   unsigned int hitKind,
320   RegAttributes... regAttributes);
321
334 static __forceinline__ __device__ void optixMakeMissHitObject(unsigned int missSBTIndex,
335   float3      rayOrigin,
336   float3      rayDirection,
337   float      tmin,
338   float      tmax,
339   float      rayTime);
340
348 static __forceinline__ __device__ void optixMakeNopHitObject();
349
353 static __forceinline__ __device__ bool optixHitObjectIsHit();
354
358 static __forceinline__ __device__ bool optixHitObjectIsMiss();
359
365 static __forceinline__ __device__ bool optixHitObjectIsNop();
366
373 static __forceinline__ __device__ unsigned int optixHitObjectGetSbtRecordIndex();
374
380 static __forceinline__ __device__ void optixSetPayload_0(unsigned int p);
381 static __forceinline__ __device__ void optixSetPayload_1(unsigned int p);
382 static __forceinline__ __device__ void optixSetPayload_2(unsigned int p);
383 static __forceinline__ __device__ void optixSetPayload_3(unsigned int p);
384 static __forceinline__ __device__ void optixSetPayload_4(unsigned int p);
385 static __forceinline__ __device__ void optixSetPayload_5(unsigned int p);
386 static __forceinline__ __device__ void optixSetPayload_6(unsigned int p);
387 static __forceinline__ __device__ void optixSetPayload_7(unsigned int p);
388 static __forceinline__ __device__ void optixSetPayload_8(unsigned int p);
389 static __forceinline__ __device__ void optixSetPayload_9(unsigned int p);
390 static __forceinline__ __device__ void optixSetPayload_10(unsigned int p);
391 static __forceinline__ __device__ void optixSetPayload_11(unsigned int p);
392 static __forceinline__ __device__ void optixSetPayload_12(unsigned int p);

```

```

393 static __forceinline__ __device__ void optixSetPayload_13(unsigned int p);
394 static __forceinline__ __device__ void optixSetPayload_14(unsigned int p);
395 static __forceinline__ __device__ void optixSetPayload_15(unsigned int p);
396 static __forceinline__ __device__ void optixSetPayload_16(unsigned int p);
397 static __forceinline__ __device__ void optixSetPayload_17(unsigned int p);
398 static __forceinline__ __device__ void optixSetPayload_18(unsigned int p);
399 static __forceinline__ __device__ void optixSetPayload_19(unsigned int p);
400 static __forceinline__ __device__ void optixSetPayload_20(unsigned int p);
401 static __forceinline__ __device__ void optixSetPayload_21(unsigned int p);
402 static __forceinline__ __device__ void optixSetPayload_22(unsigned int p);
403 static __forceinline__ __device__ void optixSetPayload_23(unsigned int p);
404 static __forceinline__ __device__ void optixSetPayload_24(unsigned int p);
405 static __forceinline__ __device__ void optixSetPayload_25(unsigned int p);
406 static __forceinline__ __device__ void optixSetPayload_26(unsigned int p);
407 static __forceinline__ __device__ void optixSetPayload_27(unsigned int p);
408 static __forceinline__ __device__ void optixSetPayload_28(unsigned int p);
409 static __forceinline__ __device__ void optixSetPayload_29(unsigned int p);
410 static __forceinline__ __device__ void optixSetPayload_30(unsigned int p);
411 static __forceinline__ __device__ void optixSetPayload_31(unsigned int p);
412
418 static __forceinline__ __device__ unsigned int optixGetPayload_0();
419 static __forceinline__ __device__ unsigned int optixGetPayload_1();
420 static __forceinline__ __device__ unsigned int optixGetPayload_2();
421 static __forceinline__ __device__ unsigned int optixGetPayload_3();
422 static __forceinline__ __device__ unsigned int optixGetPayload_4();
423 static __forceinline__ __device__ unsigned int optixGetPayload_5();
424 static __forceinline__ __device__ unsigned int optixGetPayload_6();
425 static __forceinline__ __device__ unsigned int optixGetPayload_7();
426 static __forceinline__ __device__ unsigned int optixGetPayload_8();
427 static __forceinline__ __device__ unsigned int optixGetPayload_9();
428 static __forceinline__ __device__ unsigned int optixGetPayload_10();
429 static __forceinline__ __device__ unsigned int optixGetPayload_11();
430 static __forceinline__ __device__ unsigned int optixGetPayload_12();
431 static __forceinline__ __device__ unsigned int optixGetPayload_13();
432 static __forceinline__ __device__ unsigned int optixGetPayload_14();
433 static __forceinline__ __device__ unsigned int optixGetPayload_15();
434 static __forceinline__ __device__ unsigned int optixGetPayload_16();
435 static __forceinline__ __device__ unsigned int optixGetPayload_17();
436 static __forceinline__ __device__ unsigned int optixGetPayload_18();
437 static __forceinline__ __device__ unsigned int optixGetPayload_19();
438 static __forceinline__ __device__ unsigned int optixGetPayload_20();
439 static __forceinline__ __device__ unsigned int optixGetPayload_21();
440 static __forceinline__ __device__ unsigned int optixGetPayload_22();
441 static __forceinline__ __device__ unsigned int optixGetPayload_23();
442 static __forceinline__ __device__ unsigned int optixGetPayload_24();
443 static __forceinline__ __device__ unsigned int optixGetPayload_25();
444 static __forceinline__ __device__ unsigned int optixGetPayload_26();
445 static __forceinline__ __device__ unsigned int optixGetPayload_27();
446 static __forceinline__ __device__ unsigned int optixGetPayload_28();
447 static __forceinline__ __device__ unsigned int optixGetPayload_29();
448 static __forceinline__ __device__ unsigned int optixGetPayload_30();
449 static __forceinline__ __device__ unsigned int optixGetPayload_31();
450
459 static __forceinline__ __device__ void optixSetPayloadTypes(unsigned int typeMask);
460
464 static __forceinline__ __device__ unsigned int optixUndefinedValue();
465
472 static __forceinline__ __device__ float3 optixGetWorldRayOrigin();
473
480 static __forceinline__ __device__ float3 optixHitObjectGetWorldRayOrigin();
481
488 static __forceinline__ __device__ float3 optixGetWorldRayDirection();
489
496 static __forceinline__ __device__ float3 optixHitObjectGetWorldRayDirection();
497
501 static __forceinline__ __device__ float3 optixGetObjectRayOrigin();
502

```

```

506 static __forceinline__ __device__ float3 optixGetObjectRayDirection();
507
511 static __forceinline__ __device__ float optixGetRayTmin();
512
519 static __forceinline__ __device__ float optixHitObjectGetRayTmin();
520
529 static __forceinline__ __device__ float optixGetRayTmax();
530
539 static __forceinline__ __device__ float optixHitObjectGetRayTmax();
540
546 static __forceinline__ __device__ float optixGetRayTime();
547
554 static __forceinline__ __device__ float optixHitObjectGetRayTime();
555
559 static __forceinline__ __device__ unsigned int optixGetRayFlags();
560
564 static __forceinline__ __device__ unsigned int optixGetRayVisibilityMask();
565
572 static __forceinline__ __device__ OptixTraversableHandle
optixGetInstanceTraversableFromIAS(OptixTraversableHandle ias, unsigned int instIdx);
573
584 static __forceinline__ __device__ void optixGetTriangleVertexData(OptixTraversableHandle gas, unsigned
int primIdx, unsigned int sbtGASIndex, float time, float3 data[3]);
585
590 static __forceinline__ __device__ void optixGetMicroTriangleVertexData(float3 data[3]);
591
596 static __forceinline__ __device__ void optixGetMicroTriangleBarycentricsData(float2 data[3]);
597
610 static __forceinline__ __device__ void optixGetLinearCurveVertexData(OptixTraversableHandle gas,
unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[2]);
611
624 static __forceinline__ __device__ void optixGetQuadraticBSplineVertexData(OptixTraversableHandle gas,
unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[3]);
625
638 static __forceinline__ __device__ void optixGetCubicBSplineVertexData(OptixTraversableHandle gas,
unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4]);
639
652 static __forceinline__ __device__ void optixGetCatmullRomVertexData(OptixTraversableHandle gas, unsigned
int primIdx, unsigned int sbtGASIndex, float time, float4 data[4]);
653
666 static __forceinline__ __device__ void optixGetCubicBezierVertexData(OptixTraversableHandle gas,
unsigned int primIdx, unsigned int sbtGASIndex, float time, float4 data[4]);
667
680 static __forceinline__ __device__ void optixGetRibbonVertexData(OptixTraversableHandle gas, unsigned int
primIdx, unsigned int sbtGASIndex, float time, float4 data[3]);
681
685 static __forceinline__ __device__ float3 optixGetRibbonNormal(OptixTraversableHandle gas, unsigned int
primIdx, unsigned int sbtGASIndex, float time, float2 ribbonParameters);
686
699 static __forceinline__ __device__ void optixGetSphereData(OptixTraversableHandle gas, unsigned int
primIdx, unsigned int sbtGASIndex, float time, float4 data[1]);
700
705 static __forceinline__ __device__ OptixTraversableHandle optixGetGASTraversableHandle();
706
710 static __forceinline__ __device__ float optixGetGASMotionTimeBegin(OptixTraversableHandle gas);
711
715 static __forceinline__ __device__ float optixGetGASMotionTimeEnd(OptixTraversableHandle gas);
716
720 static __forceinline__ __device__ unsigned int optixGetGASMotionStepCount(OptixTraversableHandle gas);
721
728 static __forceinline__ __device__ void optixGetWorldToObjectTransformMatrix(float m[12]);
729
736 static __forceinline__ __device__ void optixGetObjectToWorldTransformMatrix(float m[12]);
737
744 static __forceinline__ __device__ float3 optixTransformPointFromWorldToObjectSpace(float3 point);
745
752 static __forceinline__ __device__ float3 optixTransformVectorFromWorldToObjectSpace(float3 vec);

```

```

753
760 static __forceinline__ __device__ float3 optixTransformNormalFromWorldToObjectSpace(float3 normal);
761
768 static __forceinline__ __device__ float3 optixTransformPointFromObjectToWorldSpace(float3 point);
769
776 static __forceinline__ __device__ float3 optixTransformVectorFromObjectToWorldSpace(float3 vec);
777
784 static __forceinline__ __device__ float3 optixTransformNormalFromObjectToWorldSpace(float3 normal);
785
789 static __forceinline__ __device__ unsigned int optixGetTransformListSize();
790
799 static __forceinline__ __device__ unsigned int optixHitObjectGetTransformListSize();
800
804 static __forceinline__ __device__ OptixTraversableHandle optixGetTransformListHandle(unsigned int index);
805
814 static __forceinline__ __device__ OptixTraversableHandle optixHitObjectGetTransformListHandle(unsigned
int index);
815
819 static __forceinline__ __device__ OptixTransformType
optixGetTransformTypeFromHandle(OptixTraversableHandle handle);
820
826 static __forceinline__ __device__ const OptixStaticTransform*
optixGetStaticTransformFromHandle(OptixTraversableHandle handle);
827
833 static __forceinline__ __device__ const OptixSRTMotionTransform*
optixGetSRTMotionTransformFromHandle(OptixTraversableHandle handle);
834
840 static __forceinline__ __device__ const OptixMatrixMotionTransform*
optixGetMatrixMotionTransformFromHandle(OptixTraversableHandle handle);
841
847 static __forceinline__ __device__ unsigned int optixGetInstanceIdFromHandle(OptixTraversableHandle
handle);
848
854 static __forceinline__ __device__ OptixTraversableHandle
optixGetInstanceChildFromHandle(OptixTraversableHandle handle);
855
861 static __forceinline__ __device__ const float4*
optixGetInstanceTransformFromHandle(OptixTraversableHandle handle);
862
868 static __forceinline__ __device__ const float4*
optixGetInstanceInverseTransformFromHandle(OptixTraversableHandle handle);
869
893 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind);
894
900 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind,
unsigned int a0);
901
907 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind,
unsigned int a0, unsigned int a1);
908
914 static __forceinline__ __device__ bool optixReportIntersection(float hitT, unsigned int hitKind,
unsigned int a0, unsigned int a1, unsigned int a2);
915
921 static __forceinline__ __device__ bool optixReportIntersection(float hitT,
922 unsigned int hitKind,
923 unsigned int a0,
924 unsigned int a1,
925 unsigned int a2,
926 unsigned int a3);
927
933 static __forceinline__ __device__ bool optixReportIntersection(float hitT,
934 unsigned int hitKind,
935 unsigned int a0,
936 unsigned int a1,
937 unsigned int a2,
938 unsigned int a3,
939 unsigned int a4);

```

```

940
946 static __forceinline__ __device__ bool optixReportIntersection(float      hitT,
947  unsigned int hitKind,
948  unsigned int a0,
949  unsigned int a1,
950  unsigned int a2,
951  unsigned int a3,
952  unsigned int a4,
953  unsigned int a5);
954
960 static __forceinline__ __device__ bool optixReportIntersection(float      hitT,
961  unsigned int hitKind,
962  unsigned int a0,
963  unsigned int a1,
964  unsigned int a2,
965  unsigned int a3,
966  unsigned int a4,
967  unsigned int a5,
968  unsigned int a6);
969
975 static __forceinline__ __device__ bool optixReportIntersection(float      hitT,
976  unsigned int hitKind,
977  unsigned int a0,
978  unsigned int a1,
979  unsigned int a2,
980  unsigned int a3,
981  unsigned int a4,
982  unsigned int a5,
983  unsigned int a6,
984  unsigned int a7);
985
990 static __forceinline__ __device__ unsigned int optixGetAttribute_0();
991 static __forceinline__ __device__ unsigned int optixGetAttribute_1();
992 static __forceinline__ __device__ unsigned int optixGetAttribute_2();
993 static __forceinline__ __device__ unsigned int optixGetAttribute_3();
994 static __forceinline__ __device__ unsigned int optixGetAttribute_4();
995 static __forceinline__ __device__ unsigned int optixGetAttribute_5();
996 static __forceinline__ __device__ unsigned int optixGetAttribute_6();
997 static __forceinline__ __device__ unsigned int optixGetAttribute_7();
998
999
1007 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_0();
1008 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_1();
1009 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_2();
1010 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_3();
1011 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_4();
1012 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_5();
1013 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_6();
1014 static __forceinline__ __device__ unsigned int optixHitObjectGetAttribute_7();
1015
1019 static __forceinline__ __device__ void optixTerminateRay();
1020
1025 static __forceinline__ __device__ void optixIgnoreIntersection();
1026
1027
1043 static __forceinline__ __device__ unsigned int optixGetPrimitiveIndex();
1044
1052 static __forceinline__ __device__ unsigned int optixHitObjectGetPrimitiveIndex();
1053
1064 static __forceinline__ __device__ unsigned int optixGetSbtGASIndex();
1065
1074 static __forceinline__ __device__ unsigned int optixHitObjectGetSbtGASIndex();
1075
1076
1089 static __forceinline__ __device__ unsigned int optixGetInstanceId();
1090
1099 static __forceinline__ __device__ unsigned int optixHitObjectGetInstanceId();

```



```

1100
1110 static __forceinline__ __device__ unsigned int optixGetInstanceIndex();
1111
1120 static __forceinline__ __device__ unsigned int optixHitObjectGetInstanceIndex();
1121
1129 static __forceinline__ __device__ unsigned int optixGetHitKind();
1130
1138 static __forceinline__ __device__ unsigned int optixHitObjectGetHitKind();
1139
1143 static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType(unsigned int hitKind);
1144
1148 static __forceinline__ __device__ bool optixIsFrontFaceHit(unsigned int hitKind);
1149
1153 static __forceinline__ __device__ bool optixIsBackFaceHit(unsigned int hitKind);
1154
1158 static __forceinline__ __device__ OptixPrimitiveType optixGetPrimitiveType();
1159
1163 static __forceinline__ __device__ bool optixIsFrontFaceHit();
1164
1168 static __forceinline__ __device__ bool optixIsBackFaceHit();
1169
1173 static __forceinline__ __device__ bool optixIsTriangleHit();
1174
1178 static __forceinline__ __device__ bool optixIsTriangleFrontFaceHit();
1179
1183 static __forceinline__ __device__ bool optixIsTriangleBackFaceHit();
1184
1188 static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleHit();
1189
1193 static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleFrontFaceHit();
1194
1198 static __forceinline__ __device__ bool optixIsDisplacedMicromeshTriangleBackFaceHit();
1199
1206 static __forceinline__ __device__ float2 optixGetTriangleBarycentrics();
1207
1212 static __forceinline__ __device__ float optixGetCurveParameter();
1213
1219 static __forceinline__ __device__ float2 optixGetRibbonParameters();
1220
1227 static __forceinline__ __device__ uint3 optixGetLaunchIndex();
1228
1233 static __forceinline__ __device__ uint3 optixGetLaunchDimensions();
1234
1239 static __forceinline__ __device__ CUdeviceptr optixGetSbtDataPointer();
1240
1247 static __forceinline__ __device__ CUdeviceptr optixHitObjectGetSbtDataPointer();
1248
1263 static __forceinline__ __device__ void optixThrowException(int exceptionCode);
1264
1270 static __forceinline__ __device__ void optixThrowException(int exceptionCode, unsigned int
exceptionDetail0);
1271
1277 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1278                                     unsigned int exceptionDetail0,
1279                                     unsigned int exceptionDetail1);
1280
1286 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1287                                     unsigned int exceptionDetail0,
1288                                     unsigned int exceptionDetail1,
1289                                     unsigned int exceptionDetail2);
1290
1296 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1297                                     unsigned int exceptionDetail0,
1298                                     unsigned int exceptionDetail1,
1299                                     unsigned int exceptionDetail2,
1300                                     unsigned int exceptionDetail3);
1301

```

```

1307 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1308   unsigned int exceptionDetail0,
1309   unsigned int exceptionDetail1,
1310   unsigned int exceptionDetail2,
1311   unsigned int exceptionDetail3,
1312   unsigned int exceptionDetail4);
1313
1319 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1320   unsigned int exceptionDetail0,
1321   unsigned int exceptionDetail1,
1322   unsigned int exceptionDetail2,
1323   unsigned int exceptionDetail3,
1324   unsigned int exceptionDetail4,
1325   unsigned int exceptionDetail5);
1326
1333 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1334   unsigned int exceptionDetail0,
1335   unsigned int exceptionDetail1,
1336   unsigned int exceptionDetail2,
1337   unsigned int exceptionDetail3,
1338   unsigned int exceptionDetail4,
1339   unsigned int exceptionDetail5,
1340   unsigned int exceptionDetail6);
1341
1347 static __forceinline__ __device__ void optixThrowException(int exceptionCode,
1348   unsigned int exceptionDetail0,
1349   unsigned int exceptionDetail1,
1350   unsigned int exceptionDetail2,
1351   unsigned int exceptionDetail3,
1352   unsigned int exceptionDetail4,
1353   unsigned int exceptionDetail5,
1354   unsigned int exceptionDetail6,
1355   unsigned int exceptionDetail7);
1356
1360 static __forceinline__ __device__ int optixGetExceptionCode();
1361
1368 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_0();
1369
1375 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_1();
1376
1382 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_2();
1383
1389 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_3();
1390
1396 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_4();
1397
1403 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_5();
1404
1410 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_6();
1411
1417 static __forceinline__ __device__ unsigned int optixGetExceptionDetail_7();
1418
1419
1432 static __forceinline__ __device__ char* optixGetExceptionLineInfo();
1433
1457 template <typename ReturnT, typename... ArgTypes>
1458 static __forceinline__ __device__ ReturnT optixDirectCall(unsigned int sbtIndex, ArgTypes... args);
1459
1460
1483 template <typename ReturnT, typename... ArgTypes>
1484 static __forceinline__ __device__ ReturnT optixContinuationCall(unsigned int sbtIndex, ArgTypes...
args);
1485
1486
1551 static __forceinline__ __device__ uint4 optixTexFootprint2D(unsigned long long tex, unsigned int
texInfo, float x, float y, unsigned int* singleMipLevel);
1552

```



```

1564 static __forceinline__ __device__ uint4
1565 optixTexFootprint2DLod(unsigned long long tex, unsigned int texInfo, float x, float y, float level, bool
coarse, unsigned int* singleMipLevel);
1566
1581 static __forceinline__ __device__ uint4 optixTexFootprint2DGrad(unsigned long long tex,
1582  unsigned int    texInfo,
1583  float          x,
1584  float          y,
1585  float          dPdx_x,
1586  float          dPdx_y,
1587  float          dPdy_x,
1588  float          dPdy_y,
1589  bool           coarse,
1590  unsigned int*  singleMipLevel);
1591 // end group optix_device_api
1593
1594 #define __OPTIX_INCLUDE_INTERNAL_HEADERS__
1595
1596 #include "internal/optix_device_impl.h"
1597
1598 #endif // OPTIX_OPTIX_DEVICE_H

```

## 8.13 optix\_function\_table.h File Reference

### Classes

- struct [OptixFunctionTable](#)

### Macros

- #define [OPTIX\\_ABI\\_VERSION](#) 87

### Typedefs

- typedef struct [OptixFunctionTable](#) [OptixFunctionTable](#)

#### 8.13.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

#### 8.13.2 Macro Definition Documentation

##### 8.13.2.1 OPTIX\_ABI\_VERSION

```
#define OPTIX_ABI_VERSION 87
```

The OptiX ABI version.

## 8.14 optix\_function\_table.h

[Go to the documentation of this file.](#)

```

1 /*
2 * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3 *
4 * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
5 * rights in and to this software, related documentation and any modifications thereto.
6 * Any use, reproduction, disclosure or distribution of this software and related
7 * documentation without an express license agreement from NVIDIA Corporation is strictly

```

```

8 * prohibited.
9 *
10 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
11 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
12 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A
13 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
14 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
15 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
16 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
17 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
18 * SUCH DAMAGES
19 */
20
21
22
23
24
25 #ifndef OPTIX_OPTIX_FUNCTION_TABLE_H
26 #define OPTIX_OPTIX_FUNCTION_TABLE_H
27
28
29 #define OPTIX_ABI_VERSION 87
30
31 #ifndef OPTIX_DEFINE_ABI_VERSION_ONLY
32
33 #include "optix_types.h"
34
35 #if !defined(OPTIX_DONT_INCLUDE_CUDA)
36 // If OPTIX_DONT_INCLUDE_CUDA is defined, cuda driver types must be defined through other
37 // means before including optix headers.
38 #include <cuda.h>
39 #endif
40
41 #ifdef __cplusplus
42 extern "C" {
43 #endif
44
45
46
47
48
49
50
51
52
53
54
55 typedef struct OptixFunctionTable
56 {
57     /*@ {
58
59
60
61     const char* (*optixGetErrorName)(OptixResult result);
62
63
64     const char* (*optixGetErrorString)(OptixResult result);
65
66     /*@ }
67     /*@ {
68
69
70
71     OptixResult (*optixDeviceContextCreate)(CUcontext fromContext, const OptixDeviceContextOptions*
options, OptixDeviceContext* context);
72
73
74     OptixResult (*optixDeviceContextDestroy)(OptixDeviceContext context);
75
76
77     OptixResult (*optixDeviceContextGetProperty)(OptixDeviceContext context, OptixDeviceProperty
property, void* value, size_t sizeInBytes);
78
79
80     OptixResult (*optixDeviceContextSetLogCallback)(OptixDeviceContext context,
81   OptixLogCallback callbackFunction,
82   void* callbackData,
83   unsigned int callbackLevel);
84
85
86     OptixResult (*optixDeviceContextSetCacheEnabled)(OptixDeviceContext context, int enabled);
87
88
89     OptixResult (*optixDeviceContextSetCacheLocation)(OptixDeviceContext context, const char* location);
90
91
92     OptixResult (*optixDeviceContextSetCacheDatabaseSizes)(OptixDeviceContext context, size_t
lowWaterMark, size_t highWaterMark);
93
94
95     OptixResult (*optixDeviceContextGetCacheEnabled)(OptixDeviceContext context, int* enabled);
96

```

```

98     OptixResult (*optixDeviceContextGetCacheLocation)(OptixDeviceContext context, char* location, size_t
locationSize);
99
101     OptixResult (*optixDeviceContextGetCacheDatabaseSizes)(OptixDeviceContext context, size_t*
lowWaterMark, size_t* highWaterMark);
102
103     //@ }
105     //@ {
106
108     OptixResult (*optixModuleCreate)(OptixDeviceContext          context,
109                                     const OptixModuleCompileOptions* moduleCompileOptions,
110                                     const OptixPipelineCompileOptions* pipelineCompileOptions,
111                                     const char*                        input,
112                                     size_t                            inputSize,
113                                     char*                            logString,
114                                     size_t*                          logStringSize,
115                                     OptixModule*                    module);
116
118     OptixResult (*optixModuleCreateWithTasks)(OptixDeviceContext          context,
119   const OptixModuleCompileOptions* moduleCompileOptions,
120   const OptixPipelineCompileOptions* pipelineCompileOptions,
121   const char*                        input,
122   size_t                            inputSize,
123   char*                            logString,
124   size_t*                          logStringSize,
125   OptixModule*                    module,
126   OptixTask*                    firstTask);
127
129     OptixResult (*optixModuleGetCompilationState)(OptixModule module, OptixModuleCompileState* state);
130
132     OptixResult (*optixModuleDestroy)(OptixModule module);
133
135     OptixResult(*optixBuiltinISModuleGet)(OptixDeviceContext          context,
136   const OptixModuleCompileOptions* moduleCompileOptions,
137   const OptixPipelineCompileOptions* pipelineCompileOptions,
138   const OptixBuiltinISOptions*    builtinISOptions,
139   OptixModule*                    builtinModule);
140
141     //@ }
143     //@ {
144
146     OptixResult (*optixTaskExecute)(OptixTask      task,
147                                     OptixTask*     additionalTasks,
148                                     unsigned int    maxNumAdditionalTasks,
149                                     unsigned int*   numAdditionalTasksCreated);
150
151     //@ }
152     //@ {
153
155     OptixResult (*optixProgramGroupCreate)(OptixDeviceContext          context,
156   const OptixProgramGroupDesc* programDescriptions,
157   unsigned int                numProgramGroups,
158   const OptixProgramGroupOptions* options,
159   char*                      logString,
160   size_t*                    logStringSize,
161   OptixProgramGroup*        programGroups);
162
164     OptixResult (*optixProgramGroupDestroy)(OptixProgramGroup programGroup);
165
167     OptixResult (*optixProgramGroupGetStackSize)(OptixProgramGroup programGroup, OptixStackSizes*
stackSizes, OptixPipeline pipeline);
168
169     //@ }
171     //@ {
172
174     OptixResult (*optixPipelineCreate)(OptixDeviceContext          context,
175                                       const OptixPipelineCompileOptions* pipelineCompileOptions,
176                                       const OptixPipelineLinkOptions*    pipelineLinkOptions,

```

```

177         const OptixProgramGroup*      programGroups,
178         unsigned int                  numProgramGroups,
179         char*                          logString,
180         size_t*                        logStringSize,
181         OptixPipeline*                 pipeline);
182
183 OptixResult (*optixPipelineDestroy)(OptixPipeline pipeline);
184
185 OptixResult (*optixPipelineSetStackSize)(OptixPipeline pipeline,
186         unsigned int directCallableStackSizeFromTraversal,
187         unsigned int directCallableStackSizeFromState,
188         unsigned int continuationStackSize,
189         unsigned int maxTraversableGraphDepth);
190
191 //@ }
192 //@ {
193
194 OptixResult (*optixAccelComputeMemoryUsage)(OptixDeviceContext context,
195         const OptixAccelBuildOptions* accelOptions,
196         const OptixBuildInput*        buildInputs,
197         unsigned int                  numBuildInputs,
198         OptixAccelBufferSizes*        bufferSizes);
199
200 OptixResult (*optixAccelBuild)(OptixDeviceContext context,
201         CUstream stream,
202         const OptixAccelBuildOptions* accelOptions,
203         const OptixBuildInput*        buildInputs,
204         unsigned int                  numBuildInputs,
205         CUdeviceptr tempBuffer,
206         size_t        tempBufferSizeInBytes,
207         CUdeviceptr outputBuffer,
208         size_t        outputBufferSizeInBytes,
209         OptixTraversableHandle* outputHandle,
210         const OptixAccelEmitDesc* emittedProperties,
211         unsigned int numEmittedProperties);
212
213 OptixResult (*optixAccelGetRelocationInfo)(OptixDeviceContext context, OptixTraversableHandle
214 handle, OptixRelocationInfo* info);
215
216 OptixResult (*optixCheckRelocationCompatibility)(OptixDeviceContext context,
217         const OptixRelocationInfo* info,
218         int* compatible);
219
220 OptixResult (*optixAccelRelocate)(OptixDeviceContext context,
221         CUstream stream,
222         const OptixRelocationInfo* info,
223         const OptixRelocateInput* relocateInputs,
224         size_t numRelocateInputs,
225         CUdeviceptr targetAccel,
226         size_t targetAccelSizeInBytes,
227         OptixTraversableHandle* targetHandle);
228
229 OptixResult (*optixAccelCompact)(OptixDeviceContext context,
230         CUstream stream,
231         OptixTraversableHandle inputHandle,
232         CUdeviceptr outputBuffer,
233         size_t outputBufferSizeInBytes,
234         OptixTraversableHandle* outputHandle);
235
236 OptixResult (*optixAccelEmitProperty)(OptixDeviceContext context,
237         CUstream stream,
238         OptixTraversableHandle handle,
239         const OptixAccelEmitDesc* emittedProperty);
240
241 OptixResult (*optixConvertPointerToTraversableHandle)(OptixDeviceContext onDevice,

```

```

253                                     CUdeviceptr      pointer,
254                                     OptixTraversableType traversableType,
255                                     OptixTraversableHandle* traversableHandle);
256
258     OptixResult (*optixOpacityMicromapArrayComputeMemoryUsage)(OptixDeviceContext
context,
259  const OptixOpacityMicromapArrayBuildInput*
buildInput,
260  OptixMicromapBufferSizes*
bufferSizes);
261
263     OptixResult (*optixOpacityMicromapArrayBuild)(OptixDeviceContext      context,
264  CUstream                      stream,
265  const OptixOpacityMicromapArrayBuildInput* buildInput,
266  const OptixMicromapBuffers*      buffers);
267
269     OptixResult (*optixOpacityMicromapArrayGetRelocationInfo)(OptixDeviceContext context,
270  CUdeviceptr      opacityMicromapArray,
271  OptixRelocationInfo* info);
272
274     OptixResult (*optixOpacityMicromapArrayRelocate)(OptixDeviceContext      context,
275   CUstream                      stream,
276   const OptixRelocationInfo* info,
277   CUdeviceptr      targetOpacityMicromapArray,
278   size_t
targetOpacityMicromapArraySizeInBytes);
279
281     OptixResult (*optixDisplacementMicromapArrayComputeMemoryUsage)(OptixDeviceContext context,
282  const
OptixDisplacementMicromapArrayBuildInput* buildInput,
283  OptixMicromapBufferSizes* bufferSizes);
284
286     OptixResult (*optixDisplacementMicromapArrayBuild)(OptixDeviceContext
context,
287   CUstream                      stream,
288   const OptixDisplacementMicromapArrayBuildInput*
buildInput,
289   const OptixMicromapBuffers*
buffers);
290
291     //@ }
293     //@ {
294
296     OptixResult (*optixSbtRecordPackHeader)(OptixProgramGroup programGroup, void*
sbtRecordHeaderHostPointer);
297
299     OptixResult (*optixLaunch)(OptixPipeline      pipeline,
300                                CUstream          stream,
301                                CUdeviceptr      pipelineParams,
302                                size_t            pipelineParamsSize,
303                                const OptixShaderBindingTable* sbt,
304                                unsigned int      width,
305                                unsigned int      height,
306                                unsigned int      depth);
307
308     //@ }
310     //@ {
311
313     OptixResult (*optixDenoiserCreate)(OptixDeviceContext context, OptixDenoiserModelKind modelKind,
const OptixDenoiserOptions* options, OptixDenoiser* returnHandle);
314
316     OptixResult (*optixDenoiserDestroy)(OptixDenoiser handle);
317
319     OptixResult (*optixDenoiserComputeMemoryResources)(const OptixDenoiser handle,
320   unsigned int      maximumInputWidth,
321   unsigned int      maximumInputHeight,
322   OptixDenoiserSizes* returnSizes);

```

```

323
325     OptixResult (*optixDenoiserSetup)(OptixDenoiser denoiser,
326                                     CUstream      stream,
327                                     unsigned int   inputWidth,
328                                     unsigned int   inputHeight,
329                                     CUdeviceptr    state,
330                                     size_t         stateSizeInBytes,
331                                     CUdeviceptr    scratch,
332                                     size_t         scratchSizeInBytes);
333
335     OptixResult (*optixDenoiserInvoke)(OptixDenoiser      denoiser,
336                                       CUstream          stream,
337                                       const OptixDenoiserParams* params,
338                                       CUdeviceptr        denoiserState,
339                                       size_t              denoiserStateSizeInBytes,
340                                       const OptixDenoiserGuideLayer * guideLayer,
341                                       const OptixDenoiserLayer *   layers,
342                                       unsigned int          numLayers,
343                                       unsigned int          inputOffsetX,
344                                       unsigned int          inputOffsetY,
345                                       CUdeviceptr          scratch,
346                                       size_t                scratchSizeInBytes);
347
349     OptixResult (*optixDenoiserComputeIntensity)(OptixDenoiser      handle,
350  CUstream          stream,
351  const OptixImage2D* inputImage,
352  CUdeviceptr        outputIntensity,
353  CUdeviceptr        scratch,
354  size_t              scratchSizeInBytes);
355
357     OptixResult (*optixDenoiserComputeAverageColor)(OptixDenoiser      handle,
358   CUstream          stream,
359   const OptixImage2D* inputImage,
360   CUdeviceptr        outputAverageColor,
361   CUdeviceptr        scratch,
362   size_t              scratchSizeInBytes);
363
365     OptixResult (*optixDenoiserCreateWithUserModel)(OptixDeviceContext context, const void * data, size_t
dataSizeInBytes, OptixDenoiser* returnHandle);
366     //@ }
367
368 } OptixFunctionTable;
369 // end group optix_function_table
371
372 #ifdef __cplusplus
373 }
374 #endif
375
376 #endif /* OPTIX_DEFINE_ABI_VERSION_ONLY */
377
378 #endif /* OPTIX_OPTIX_FUNCTION_TABLE_H */

```

## 8.15 optix\_function\_table\_definition.h File Reference

### Variables

- [OptixFunctionTable g\\_optixFunctionTable](#)

### 8.15.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

## 8.16 optix\_function\_table\_definition.h

[Go to the documentation of this file.](#)

```

1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * Redistribution and use in source and binary forms, with or without
5  * modification, are permitted provided that the following conditions
6  * are met:
7  * * Redistributions of source code must retain the above copyright
8  *   notice, this list of conditions and the following disclaimer.
9  * * Redistributions in binary form must reproduce the above copyright
10 *   notice, this list of conditions and the following disclaimer in the
11 *   documentation and/or other materials provided with the distribution.
12 * * Neither the name of NVIDIA CORPORATION nor the names of its
13 *   contributors may be used to endorse or promote products derived
14 *   from this software without specific prior written permission.
15 *
16 * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS "AS IS" AND ANY
17 * EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
18 * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
19 * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
20 * CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
21 * EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
22 * PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
23 * PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY
24 * OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
25 * (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
26 * OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
27 */
28
32
33 #ifndef OPTIX_OPTIX_FUNCTION_TABLE_DEFINITION_H
34 #define OPTIX_OPTIX_FUNCTION_TABLE_DEFINITION_H
35
36 #include "optix_function_table.h"
37
38 #ifdef __cplusplus
39 extern "C" {
40 #endif
41
42 OptixFunctionTable g_optixFunctionTable;
43 // end group optix_function_table
44
45 #ifdef __cplusplus
46 }
47 #endif
48 #endif // OPTIX_OPTIX_FUNCTION_TABLE_DEFINITION_H

```

## 8.17 optix\_host.h File Reference

### Functions

- `const char * optixGetErrorName (OptixResult result)`
- `const char * optixGetErrorString (OptixResult result)`
- `OptixResult optixDeviceContextCreate (CUcontext fromContext, const OptixDeviceContextOptions *options, OptixDeviceContext *context)`
- `OptixResult optixDeviceContextDestroy (OptixDeviceContext context)`



- `OptixResult optixDeviceContextGetProperty` (`OptixDeviceContext` context, `OptixDeviceProperty` property, `void *value`, `size_t sizeInBytes`)
- `OptixResult optixDeviceContextSetLogCallback` (`OptixDeviceContext` context, `OptixLogCallback` callbackFunction, `void *callbackData`, `unsigned int callbackLevel`)
- `OptixResult optixDeviceContextSetCacheEnabled` (`OptixDeviceContext` context, `int enabled`)
- `OptixResult optixDeviceContextSetCacheLocation` (`OptixDeviceContext` context, `const char *location`)
- `OptixResult optixDeviceContextSetCacheDatabaseSizes` (`OptixDeviceContext` context, `size_t lowWaterMark`, `size_t highWaterMark`)
- `OptixResult optixDeviceContextGetCacheEnabled` (`OptixDeviceContext` context, `int *enabled`)
- `OptixResult optixDeviceContextGetCacheLocation` (`OptixDeviceContext` context, `char *location`, `size_t locationSize`)
- `OptixResult optixDeviceContextGetCacheDatabaseSizes` (`OptixDeviceContext` context, `size_t *lowWaterMark`, `size_t *highWaterMark`)
- `OptixResult optixPipelineCreate` (`OptixDeviceContext` context, `const OptixPipelineCompileOptions *pipelineCompileOptions`, `const OptixPipelineLinkOptions *pipelineLinkOptions`, `const OptixProgramGroup *programGroups`, `unsigned int numProgramGroups`, `char *logString`, `size_t *logStringSize`, `OptixPipeline *pipeline`)
- `OptixResult optixPipelineDestroy` (`OptixPipeline` pipeline)
- `OptixResult optixPipelineSetStackSize` (`OptixPipeline` pipeline, `unsigned int directCallableStackSizeFromTraversal`, `unsigned int directCallableStackSizeFromState`, `unsigned int continuationStackSize`, `unsigned int maxTraversableGraphDepth`)
- `OptixResult optixModuleCreate` (`OptixDeviceContext` context, `const OptixModuleCompileOptions *moduleCompileOptions`, `const OptixPipelineCompileOptions *pipelineCompileOptions`, `const char *input`, `size_t inputSize`, `char *logString`, `size_t *logStringSize`, `OptixModule *module`)
- `OptixResult optixModuleCreateWithTasks` (`OptixDeviceContext` context, `const OptixModuleCompileOptions *moduleCompileOptions`, `const OptixPipelineCompileOptions *pipelineCompileOptions`, `const char *input`, `size_t inputSize`, `char *logString`, `size_t *logStringSize`, `OptixModule *module`, `OptixTask *firstTask`)
- `OptixResult optixModuleGetCompilationState` (`OptixModule` module, `OptixModuleCompileState *state`)
- `OptixResult optixModuleDestroy` (`OptixModule` module)
- `OptixResult optixBuiltinISModuleGet` (`OptixDeviceContext` context, `const OptixModuleCompileOptions *moduleCompileOptions`, `const OptixPipelineCompileOptions *pipelineCompileOptions`, `const OptixBuiltinISOOptions *builtinISOOptions`, `OptixModule *builtinModule`)
- `OptixResult optixTaskExecute` (`OptixTask` task, `OptixTask *additionalTasks`, `unsigned int maxNumAdditionalTasks`, `unsigned int *numAdditionalTasksCreated`)
- `OptixResult optixProgramGroupGetStackSize` (`OptixProgramGroup` programGroup, `OptixStackSizes *stackSizes`, `OptixPipeline` pipeline)
- `OptixResult optixProgramGroupCreate` (`OptixDeviceContext` context, `const OptixProgramGroupDesc *programDescriptions`, `unsigned int numProgramGroups`, `const OptixProgramGroupOptions *options`, `char *logString`, `size_t *logStringSize`, `OptixProgramGroup *programGroups`)
- `OptixResult optixProgramGroupDestroy` (`OptixProgramGroup` programGroup)
- `OptixResult optixLaunch` (`OptixPipeline` pipeline, `CUstream` stream, `CUdeviceptr` pipelineParams, `size_t pipelineParamsSize`, `const OptixShaderBindingTable *sbt`, `unsigned int width`, `unsigned int height`, `unsigned int depth`)
- `OptixResult optixSbtRecordPackHeader` (`OptixProgramGroup` programGroup, `void *sbtRecordHeaderHostPointer`)



- `OptixResult optixAccelComputeMemoryUsage` (`OptixDeviceContext` context, `const OptixAccelBuildOptions *accelOptions`, `const OptixBuildInput *buildInputs`, `unsigned int numBuildInputs`, `OptixAccelBufferSizes *bufferSizes`)
- `OptixResult optixAccelBuild` (`OptixDeviceContext` context, `CUstream` stream, `const OptixAccelBuildOptions *accelOptions`, `const OptixBuildInput *buildInputs`, `unsigned int numBuildInputs`, `CUdeviceptr` tempBuffer, `size_t` tempBufferSizeInBytes, `CUdeviceptr` outputBuffer, `size_t` outputBufferSizeInBytes, `OptixTraversableHandle *outputHandle`, `const OptixAccelEmitDesc *emittedProperties`, `unsigned int numEmittedProperties`)
- `OptixResult optixAccelGetRelocationInfo` (`OptixDeviceContext` context, `OptixTraversableHandle` handle, `OptixRelocationInfo *info`)
- `OptixResult optixCheckRelocationCompatibility` (`OptixDeviceContext` context, `const OptixRelocationInfo *info`, `int *compatible`)
- `OptixResult optixAccelRelocate` (`OptixDeviceContext` context, `CUstream` stream, `const OptixRelocationInfo *info`, `const OptixRelocateInput *relocateInputs`, `size_t` numRelocateInputs, `CUdeviceptr` targetAccel, `size_t` targetAccelSizeInBytes, `OptixTraversableHandle *targetHandle`)
- `OptixResult optixAccelCompact` (`OptixDeviceContext` context, `CUstream` stream, `OptixTraversableHandle` inputHandle, `CUdeviceptr` outputBuffer, `size_t` outputBufferSizeInBytes, `OptixTraversableHandle *outputHandle`)
- `OptixResult optixAccelEmitProperty` (`OptixDeviceContext` context, `CUstream` stream, `OptixTraversableHandle` handle, `const OptixAccelEmitDesc *emittedProperty`)
- `OptixResult optixConvertPointerToTraversableHandle` (`OptixDeviceContext` onDevice, `CUdeviceptr` pointer, `OptixTraversableType` traversableType, `OptixTraversableHandle *traversableHandle`)
- `OptixResult optixOpacityMicromapArrayComputeMemoryUsage` (`OptixDeviceContext` context, `const OptixOpacityMicromapArrayBuildInput *buildInput`, `OptixMicromapBufferSizes *bufferSizes`)
- `OptixResult optixOpacityMicromapArrayBuild` (`OptixDeviceContext` context, `CUstream` stream, `const OptixOpacityMicromapArrayBuildInput *buildInput`, `const OptixMicromapBuffers *buffers`)
- `OptixResult optixOpacityMicromapArrayGetRelocationInfo` (`OptixDeviceContext` context, `CUdeviceptr` opacityMicromapArray, `OptixRelocationInfo *info`)
- `OptixResult optixOpacityMicromapArrayRelocate` (`OptixDeviceContext` context, `CUstream` stream, `const OptixRelocationInfo *info`, `CUdeviceptr` targetOpacityMicromapArray, `size_t` targetOpacityMicromapArraySizeInBytes)
- `OptixResult optixDisplacementMicromapArrayComputeMemoryUsage` (`OptixDeviceContext` context, `const OptixDisplacementMicromapArrayBuildInput *buildInput`, `OptixMicromapBufferSizes *bufferSizes`)
- `OptixResult optixDisplacementMicromapArrayBuild` (`OptixDeviceContext` context, `CUstream` stream, `const OptixDisplacementMicromapArrayBuildInput *buildInput`, `const OptixMicromapBuffers *buffers`)
- `OptixResult optixDenoiserCreate` (`OptixDeviceContext` context, `OptixDenoiserModelKind` modelKind, `const OptixDenoiserOptions *options`, `OptixDenoiser *denoiser`)
- `OptixResult optixDenoiserCreateWithUserModel` (`OptixDeviceContext` context, `const void *userData`, `size_t` userDataSizeInBytes, `OptixDenoiser *denoiser`)
- `OptixResult optixDenoiserDestroy` (`OptixDenoiser` denoiser)
- `OptixResult optixDenoiserComputeMemoryResources` (`const OptixDenoiser` denoiser, `unsigned int` outputWidth, `unsigned int` outputHeight, `OptixDenoiserSizes *returnSizes`)
- `OptixResult optixDenoiserSetup` (`OptixDenoiser` denoiser, `CUstream` stream, `unsigned int` inputWidth, `unsigned int` inputHeight, `CUdeviceptr` denoiserState, `size_t` denoiserStateSizeInBytes, `CUdeviceptr` scratch, `size_t` scratchSizeInBytes)

- `OptixResult optixDenoiserInvoke` (`OptixDenoiser` denoiser, `CUstream` stream, const `OptixDenoiserParams` \*params, `CUdeviceptr` denoiserState, `size_t` denoiserStateSizeInBytes, const `OptixDenoiserGuideLayer` \*guideLayer, const `OptixDenoiserLayer` \*layers, unsigned int numLayers, unsigned int inputOffsetX, unsigned int inputOffsetY, `CUdeviceptr` scratch, `size_t` scratchSizeInBytes)
- `OptixResult optixDenoiserComputeIntensity` (`OptixDenoiser` denoiser, `CUstream` stream, const `OptixImage2D` \*inputImage, `CUdeviceptr` outputIntensity, `CUdeviceptr` scratch, `size_t` scratchSizeInBytes)
- `OptixResult optixDenoiserComputeAverageColor` (`OptixDenoiser` denoiser, `CUstream` stream, const `OptixImage2D` \*inputImage, `CUdeviceptr` outputAverageColor, `CUdeviceptr` scratch, `size_t` scratchSizeInBytes)

## 8.17.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

OptiX host include file – includes the host api if compiling host code. For the math library routines include `optix_math.h`

## 8.17.2 Function Documentation

### 8.17.2.1 optixAccelBuild()

```
OptixResult optixAccelBuild (
    OptixDeviceContext context,
    CUstream stream,
    const OptixAccelBuildOptions * accelOptions,
    const OptixBuildInput * buildInputs,
    unsigned int numBuildInputs,
    CUdeviceptr tempBuffer,
    size_t tempBufferSizeInBytes,
    CUdeviceptr outputBuffer,
    size_t outputBufferSizeInBytes,
    OptixTraversableHandle * outputHandle,
    const OptixAccelEmitDesc * emittedProperties,
    unsigned int numEmittedProperties )
```

Parameters

|    |                       |                                                                      |
|----|-----------------------|----------------------------------------------------------------------|
| in | <i>context</i>        |                                                                      |
| in | <i>stream</i>         |                                                                      |
| in | <i>accelOptions</i>   | accel options                                                        |
| in | <i>buildInputs</i>    | an array of <code>OptixBuildInput</code> objects                     |
| in | <i>numBuildInputs</i> | must be $\geq 1$ for GAS, and $= 1$ for IAS                          |
| in | <i>tempBuffer</i>     | must be a multiple of <code>OPTIX_ACCEL_BUFFER_BYTE_ALIGNMENT</code> |

## Parameters

|     |                                |                                                           |
|-----|--------------------------------|-----------------------------------------------------------|
| in  | <i>tempBufferSizeInBytes</i>   |                                                           |
| in  | <i>outputBuffer</i>            | must be a multiple of OPTIX_ACCEL_BUFFER_BYTE_ALIGNMENT   |
| in  | <i>outputBufferSizeInBytes</i> |                                                           |
| out | <i>outputHandle</i>            |                                                           |
| in  | <i>emittedProperties</i>       | types of requested properties and output buffers          |
| in  | <i>numEmittedProperties</i>    | number of post-build properties to populate (may be zero) |

## 8.17.2.2 optixAccelCompact()

```
OptixResult optixAccelCompact (
    OptixDeviceContext context,
    CUstream stream,
    OptixTraversableHandle inputHandle,
    CUdeviceptr outputBuffer,
    size_t outputBufferSizeInBytes,
    OptixTraversableHandle * outputHandle )
```

After building an acceleration structure, it can be copied in a compacted form to reduce memory. In order to be compacted, OPTIX\_BUILD\_FLAG\_ALLOW\_COMPACTION must be supplied in [OptixAccelBuildOptions::buildFlags](#) passed to [optixAccelBuild](#).

'outputBuffer' is the pointer to where the compacted acceleration structure will be written. This pointer must be a multiple of OPTIX\_ACCEL\_BUFFER\_BYTE\_ALIGNMENT.

The size of the memory specified in 'outputBufferSizeInBytes' should be at least the value computed using the OPTIX\_PROPERTY\_TYPE\_COMPACTED\_SIZE that was reported during [optixAccelBuild](#).

## Parameters

|     |                                |
|-----|--------------------------------|
| in  | <i>context</i>                 |
| in  | <i>stream</i>                  |
| in  | <i>inputHandle</i>             |
| in  | <i>outputBuffer</i>            |
| in  | <i>outputBufferSizeInBytes</i> |
| out | <i>outputHandle</i>            |

## 8.17.2.3 optixAccelComputeMemoryUsage()

```
OptixResult optixAccelComputeMemoryUsage (
    OptixDeviceContext context,
    const OptixAccelBuildOptions * accelOptions,
    const OptixBuildInput * buildInputs,
    unsigned int numBuildInputs,
    OptixAccelBufferSizes * bufferSizes )
```

## Parameters

|     |                       |                                                        |
|-----|-----------------------|--------------------------------------------------------|
| in  | <i>context</i>        |                                                        |
| in  | <i>accelOptions</i>   | options for the accel build                            |
| in  | <i>buildInputs</i>    | an array of <a href="#">OptixBuildInput</a> objects    |
| in  | <i>numBuildInputs</i> | number of elements in buildInputs (must be at least 1) |
| out | <i>bufferSizes</i>    | fills in buffer sizes                                  |

## 8.17.2.4 optixAccelEmitProperty()

```
OptixResult optixAccelEmitProperty (
    OptixDeviceContext context,
    CUstream stream,
    OptixTraversableHandle handle,
    const OptixAccelEmitDesc * emittedProperty )
```

Emit a single property after an acceleration structure was built. The result buffer of the 'emittedProperty' needs to be large enough to hold the requested property (.).

See also [OptixAccelPropertyType](#)).

## Parameters

|    |                        |                                              |
|----|------------------------|----------------------------------------------|
| in | <i>context</i>         |                                              |
| in | <i>stream</i>          |                                              |
| in | <i>handle</i>          |                                              |
| in | <i>emittedProperty</i> | type of requested property and output buffer |

## 8.17.2.5 optixAccelGetRelocationInfo()

```
OptixResult optixAccelGetRelocationInfo (
    OptixDeviceContext context,
    OptixTraversableHandle handle,
    OptixRelocationInfo * info )
```

Obtain relocation information, stored in [OptixRelocationInfo](#), for a given context and acceleration structure's traversable handle.

The relocation information can be passed to [optixCheckRelocationCompatibility](#) to determine if an acceleration structure, referenced by 'handle', can be relocated to a different device's memory space (see [optixCheckRelocationCompatibility](#)).

When used with [optixAccelRelocate](#), it provides data necessary for doing the relocation.

If the acceleration structure data associated with 'handle' is copied multiple times, the same [OptixRelocationInfo](#) can also be used on all copies.

## Parameters

|    |                |
|----|----------------|
| in | <i>context</i> |
| in | <i>handle</i>  |

## Parameters

|     |      |
|-----|------|
| out | info |
|-----|------|

## Returns

OPTIX\_ERROR\_INVALID\_VALUE will be returned for traversable handles that are not from acceleration structure builds.

## 8.17.2.6 optixAccelRelocate()

```
OptixResult optixAccelRelocate (
    OptixDeviceContext context,
    CUstream stream,
    const OptixRelocationInfo * info,
    const OptixRelocateInput * relocateInputs,
    size_t numRelocateInputs,
    CUdeviceptr targetAccel,
    size_t targetAccelSizeInBytes,
    OptixTraversableHandle * targetHandle )
```

optixAccelRelocate is called to update the acceleration structure after it has been relocated. Relocation is necessary when the acceleration structure's location in device memory has changed.

optixAccelRelocate does not copy the memory. This function only operates on the relocated memory whose new location is specified by 'targetAccel'. optixAccelRelocate also returns the new OptixTraversableHandle associated with 'targetAccel'. The original memory (source) is not required to be valid, only the [OptixRelocationInfo](#).

Before calling optixAccelRelocate, optixCheckRelocationCompatibility should be called to ensure the copy will be compatible with the destination device context.

The memory pointed to by 'targetAccel' should be allocated with the same size as the source acceleration. Similar to the 'outputBuffer' used in optixAccelBuild, this pointer must be a multiple of OPTIX\_ACCEL\_BUFFER\_BYTE\_ALIGNMENT.

The memory in 'targetAccel' must be allocated as long as the accel is in use.

The instance traversables referenced by an IAS and the micromaps referenced by a triangle GAS may themselves require relocation. 'relocateInputs' and 'numRelocateInputs' should be used to specify the relocated traversables and micromaps. After relocation, the relocated accel will reference these relocated traversables and micromaps instead of their sources. The number of relocate inputs 'numRelocateInputs' must match the number of build inputs 'numBuildInputs' used to build the source accel. Relocation inputs correspond with build inputs used to build the source accel and should appear in the same order (see [optixAccelBuild](#)). 'relocateInputs' and 'numRelocateInputs' may be zero, preserving any references to traversables and micromaps from the source accel.

## Parameters

|    |                |
|----|----------------|
| in | context        |
| in | stream         |
| in | info           |
| in | relocateInputs |

## Parameters

|     |                               |
|-----|-------------------------------|
| in  | <i>numRelocateInputs</i>      |
| in  | <i>targetAccel</i>            |
| in  | <i>targetAccelSizeInBytes</i> |
| out | <i>targetHandle</i>           |

## 8.17.2.7 optixBuiltinISModuleGet()

```
OptixResult optixBuiltinISModuleGet (
    OptixDeviceContext context,
    const OptixModuleCompileOptions * moduleCompileOptions,
    const OptixPipelineCompileOptions * pipelineCompileOptions,
    const OptixBuiltinISOptions * builtinISOptions,
    OptixModule * builtinModule )
```

Returns a module containing the intersection program for the built-in primitive type specified by the builtinISOptions. This module must be used as the moduleIS for the [OptixProgramGroupHitgroup](#) in any SBT record for that primitive type. (The entryFunctionNameIS should be null.)

## 8.17.2.8 optixCheckRelocationCompatibility()

```
OptixResult optixCheckRelocationCompatibility (
    OptixDeviceContext context,
    const OptixRelocationInfo * info,
    int * compatible )
```

Checks if an optix data structure built using another OptixDeviceContext (that was used to fill in 'info') is compatible with the OptixDeviceContext specified in the 'context' parameter.

Any device is always compatible with itself.

## Parameters

|     |                   |                                                                                                                                                                                                                                                                       |
|-----|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| in  | <i>context</i>    |                                                                                                                                                                                                                                                                       |
| in  | <i>info</i>       |                                                                                                                                                                                                                                                                       |
| out | <i>compatible</i> | <p>If OPTIX_SUCCESS is returned 'compatible' will have the value of either:</p> <ul style="list-style-type: none"> <li>• 0: This context is not compatible with the optix data structure associated with 'info'.</li> <li>• 1: This context is compatible.</li> </ul> |

## 8.17.2.9 optixConvertPointerToTraversableHandle()

```
OptixResult optixConvertPointerToTraversableHandle (
    OptixDeviceContext onDevice,
    CUdeviceptr pointer,
    OptixTraversableType traversableType,
    OptixTraversableHandle * traversableHandle )
```

## Parameters

|     |                          |                                                                                                                           |
|-----|--------------------------|---------------------------------------------------------------------------------------------------------------------------|
| in  | <i>onDevice</i>          |                                                                                                                           |
| in  | <i>pointer</i>           | pointer to traversable allocated in OptixDeviceContext. This pointer must be a multiple of OPTIX_TRANSFORM_BYTE_ALIGNMENT |
| in  | <i>traversableType</i>   | Type of OptixTraversableHandle to create                                                                                  |
| out | <i>traversableHandle</i> | traversable handle. traversableHandle must be in host memory                                                              |

## 8.17.2.10 optixDenoiserComputeAverageColor()

```
OptixResult optixDenoiserComputeAverageColor (
    OptixDenoiser denoiser,
    CUstream stream,
    const OptixImage2D * inputImage,
    CUdeviceptr outputAverageColor,
    CUdeviceptr scratch,
    size_t scratchSizeInBytes )
```

Compute average logarithmic for each of the first three channels for the given image. When denoising tiles the intensity of the entire image should be computed, i.e. not per tile to get consistent results.

The size of scratch memory required can be queried with [optixDenoiserComputeMemoryResources](#).

data type unsigned char is not supported for 'inputImage', it must be 3 or 4 component half/float.

## Parameters

|     |                           |              |
|-----|---------------------------|--------------|
| in  | <i>denoiser</i>           |              |
| in  | <i>stream</i>             |              |
| in  | <i>inputImage</i>         |              |
| out | <i>outputAverageColor</i> | three floats |
| in  | <i>scratch</i>            |              |
| in  | <i>scratchSizeInBytes</i> |              |

## 8.17.2.11 optixDenoiserComputeIntensity()

```
OptixResult optixDenoiserComputeIntensity (
    OptixDenoiser denoiser,
    CUstream stream,
    const OptixImage2D * inputImage,
    CUdeviceptr outputIntensity,
    CUdeviceptr scratch,
    size_t scratchSizeInBytes )
```

Computes the logarithmic average intensity of the given image. The returned value 'outputIntensity' is multiplied with the RGB values of the input image/tile in optixDenoiserInvoke if given in the parameter [OptixDenoiserParams::hdrIntensity](#) (otherwise 'hdrIntensity' must be a null pointer). This is useful for denoising HDR images which are very dark or bright. When denoising tiles the intensity of

the entire image should be computed, i.e. not per tile to get consistent results.

For each RGB pixel in the `inputImage` the intensity is calculated and summed if it is greater than  $1e-8f$ :  
 $intensity = \log(r * 0.212586f + g * 0.715170f + b * 0.072200f)$ . The function returns  $0.18 / \exp(\text{sum of intensities} / \text{number of summed pixels})$ . More details could be found in the Reinhard tonemapping paper: [http://www.cmap.polytechnique.fr/~peyre/cours/x2005signal/hdr\\_photographic.pdf](http://www.cmap.polytechnique.fr/~peyre/cours/x2005signal/hdr_photographic.pdf)

The size of scratch memory required can be queried with `optixDenoiserComputeMemoryResources`.  
 data type unsigned char is not supported for 'inputImage', it must be 3 or 4 component half/float.

#### Parameters

|     |                           |              |
|-----|---------------------------|--------------|
| in  | <i>denoiser</i>           |              |
| in  | <i>stream</i>             |              |
| in  | <i>inputImage</i>         |              |
| out | <i>outputIntensity</i>    | single float |
| in  | <i>scratch</i>            |              |
| in  | <i>scratchSizeInBytes</i> |              |

#### 8.17.2.12 optixDenoiserComputeMemoryResources()

```
OptixResult optixDenoiserComputeMemoryResources (
    const OptixDenoiser denoiser,
    unsigned int outputWidth,
    unsigned int outputHeight,
    OptixDenoiserSizes * returnSizes )
```

Computes the GPU memory resources required to execute the denoiser.

Memory for state and scratch buffers must be allocated with the sizes in 'returnSizes' and scratch memory passed to `optixDenoiserSetup`, `optixDenoiserInvoke`, `optixDenoiserComputeIntensity` and `optixDenoiserComputeAverageColor`. For tiled denoising an overlap area ('overlapWindowSizeInPixels') must be added to each tile on all sides which increases the amount of memory needed to denoise a tile. In case of tiling use `withOverlapScratchSizeInBytes` for scratch memory size. If only full resolution images are denoised, `withoutOverlapScratchSizeInBytes` can be used which is always smaller than `withOverlapScratchSizeInBytes`.

'outputWidth' and 'outputHeight' is the dimension of the image to be denoised (without overlap in case tiling is being used). 'outputWidth' and 'outputHeight' must be greater than or equal to the dimensions passed to `optixDenoiserSetup`.

#### Parameters

|     |                     |
|-----|---------------------|
| in  | <i>denoiser</i>     |
| in  | <i>outputWidth</i>  |
| in  | <i>outputHeight</i> |
| out | <i>returnSizes</i>  |



### 8.17.2.13 optixDenoiserCreate()

```
OptixResult optixDenoiserCreate (
    OptixDeviceContext context,
    OptixDenoiserModelKind modelKind,
    const OptixDenoiserOptions * options,
    OptixDenoiser * denoiser )
```

Creates a denoiser object with the given options, using built-in inference models.

'modelKind' selects the model used for inference. Inference for the built-in models can be guided (giving hints to improve image quality) with albedo and normal vector images in the guide layer (see 'optixDenoiserInvoke'). Use of these images must be enabled in 'OptixDenoiserOptions'.

Parameters

|     |                  |
|-----|------------------|
| in  | <i>context</i>   |
| in  | <i>modelKind</i> |
| in  | <i>options</i>   |
| out | <i>denoiser</i>  |

### 8.17.2.14 optixDenoiserCreateWithUserModel()

```
OptixResult optixDenoiserCreateWithUserModel (
    OptixDeviceContext context,
    const void * userData,
    size_t userDataSizeInBytes,
    OptixDenoiser * denoiser )
```

Creates a denoiser object with the given options, using a provided inference model.

'userData' and 'userDataSizeInBytes' provide a user model for inference. The memory passed in userData will be accessed only during the invocation of this function and can be freed after it returns. The user model must export only one weight set which determines both the model kind and the required set of guide images.

Parameters

|     |                            |
|-----|----------------------------|
| in  | <i>context</i>             |
| in  | <i>userData</i>            |
| in  | <i>userDataSizeInBytes</i> |
| out | <i>denoiser</i>            |

### 8.17.2.15 optixDenoiserDestroy()

```
OptixResult optixDenoiserDestroy (
    OptixDenoiser denoiser )
```

Destroys the denoiser object and any associated host resources.

### 8.17.2.16 optixDenoiserInvoke()

```
OptixResult optixDenoiserInvoke (
    OptixDenoiser denoiser,
    CUstream stream,
    const OptixDenoiserParams * params,
    CUdeviceptr denoiserState,
    size_t denoiserStateSizeInBytes,
    const OptixDenoiserGuideLayer * guideLayer,
    const OptixDenoiserLayer * layers,
    unsigned int numLayers,
    unsigned int inputOffsetX,
    unsigned int inputOffsetY,
    CUdeviceptr scratch,
    size_t scratchSizeInBytes )
```

Invokes denoiser on a set of input data and produces at least one output image. State memory must be available during the execution of the denoiser (or until `optixDenoiserSetup` is called with a new state memory pointer). Scratch memory passed is used only for the duration of this function. Scratch and state memory sizes must have a size greater than or equal to the sizes as returned by `optixDenoiserComputeMemoryResources`.

'inputOffsetX' and 'inputOffsetY' are pixel offsets in the 'inputLayers' image specifying the beginning of the image without overlap. When denoising an entire image without tiling there is no overlap and 'inputOffsetX' and 'inputOffsetY' must be zero. When denoising a tile which is adjacent to one of the four sides of the entire image the corresponding offsets must also be zero since there is no overlap at the side adjacent to the image border.

'guideLayer' provides additional information to the denoiser. When providing albedo and normal vector guide images, the corresponding fields in the '`OptixDenoiserOptions`' must be enabled, see `optixDenoiserCreate`. 'guideLayer' must not be null. If a guide image in '`OptixDenoiserOptions`' is not enabled, the corresponding image in '`OptixDenoiserGuideLayer`' is ignored.

If `OPTIX_DENOISER_MODEL_KIND_TEMPORAL` or `OPTIX_DENOISER_MODEL_KIND_TEMPORAL_AOV` is selected, a 2d flow image must be given in '`OptixDenoiserGuideLayer`'. It describes for each pixel the flow from the previous to the current frame (a 2d vector in pixel space). The denoised beauty/AOV of the previous frame must be given in 'previousOutput'. If this image is not available in the first frame of a sequence, the noisy beauty/AOV from the first frame and zero flow vectors could be given as a substitute. For non-temporal model kinds the flow image in '`OptixDenoiserGuideLayer`' is ignored. 'previousOutput' and 'output' may refer to the same buffer if tiling is not used, i.e. 'previousOutput' is first read by this function and later overwritten with the denoised result. 'output' can be passed as 'previousOutput' to the next frame. In other model kinds (not temporal) 'previousOutput' is ignored.

The beauty layer must be given as the first entry in 'layers'. In AOV type model kinds (`OPTIX_DENOISER_MODEL_KIND_AOV` or in user defined models implementing kernel-prediction) additional layers for the AOV images can be given. In each layer the noisy input image is given in 'input', the denoised output is written into the 'output' image. input and output images may refer to the same buffer, with the restriction that the pixel formats must be identical for input and output when the blend mode is selected (see `OptixDenoiserParams`).

If `OPTIX_DENOISER_MODEL_KIND_TEMPORAL` or `OPTIX_DENOISER_MODEL_KIND_TEMPORAL_AOV` is selected, the denoised image from the previous frame must be given in 'previousOutput' in the layer. 'previousOutput' and 'output' may refer to the same buffer if tiling is not

used, i.e. 'previousOutput' is first read by this function and later overwritten with the denoised result. 'output' can be passed as 'previousOutput' to the next frame. In addition, 'previousOutputInternalGuideLayer' and 'outputInternalGuideLayer' must both be allocated regardless of tiling mode. The pixel format must be OPTIX\_PIXEL\_FORMAT\_INTERNAL\_GUIDE\_LAYER and the dimension must be identical to the other input layers. In the first frame memory in 'previousOutputInternalGuideLayer' must either contain valid data from previous denoiser runs or set to zero. In other model kinds (not temporal) 'previousOutput' and the internal guide layers are ignored.

If OPTIX\_DENOISER\_MODEL\_KIND\_TEMPORAL or OPTIX\_DENOISER\_MODEL\_KIND\_TEMPORAL\_AOV is selected, the normal vector guide image must be given as 3d vectors in camera space. In the other models only the x and y channels are used and other channels are ignored.

#### Parameters

|    |                                 |
|----|---------------------------------|
| in | <i>denoiser</i>                 |
| in | <i>stream</i>                   |
| in | <i>params</i>                   |
| in | <i>denoiserState</i>            |
| in | <i>denoiserStateSizeInBytes</i> |
| in | <i>guideLayer</i>               |
| in | <i>layers</i>                   |
| in | <i>numLayers</i>                |
| in | <i>inputOffsetX</i>             |
| in | <i>inputOffsetY</i>             |
| in | <i>scratch</i>                  |
| in | <i>scratchSizeInBytes</i>       |

### 8.17.2.17 optixDenoiserSetup()

```
OptixResult optixDenoiserSetup (
    OptixDenoiser denoiser,
    CUstream stream,
    unsigned int inputWidth,
    unsigned int inputHeight,
    CUdeviceptr denoiserState,
    size_t denoiserStateSizeInBytes,
    CUdeviceptr scratch,
    size_t scratchSizeInBytes )
```

Initializes the state required by the denoiser.

'inputWidth' and 'inputHeight' must include overlap on both sides of the image if tiling is being used. The overlap is returned by [optixDenoiserComputeMemoryResources](#). For subsequent calls to [optixDenoiserInvoke](#) 'inputWidth' and 'inputHeight' are the maximum dimensions of the input layers. Dimensions of the input layers passed to [optixDenoiserInvoke](#) may be different in each invocation however they always must be smaller than 'inputWidth' and 'inputHeight' passed to [optixDenoiserSetup](#).

## Parameters

|    |                                 |
|----|---------------------------------|
| in | <i>denoiser</i>                 |
| in | <i>stream</i>                   |
| in | <i>inputWidth</i>               |
| in | <i>inputHeight</i>              |
| in | <i>denoiserState</i>            |
| in | <i>denoiserStateSizeInBytes</i> |
| in | <i>scratch</i>                  |
| in | <i>scratchSizeInBytes</i>       |

## 8.17.2.18 optixDeviceContextCreate()

```
OptixResult optixDeviceContextCreate (
    CUcontext fromContext,
    const OptixDeviceContextOptions * options,
    OptixDeviceContext * context )
```

Create a device context associated with the CUDA context specified with 'fromContext'.

If zero is specified for 'fromContext', OptiX will use the current CUDA context. The CUDA context should be initialized before calling optixDeviceContextCreate.

## Parameters

|     |                    |
|-----|--------------------|
| in  | <i>fromContext</i> |
| in  | <i>options</i>     |
| out | <i>context</i>     |

## Returns

- OPTIX\_ERROR\_CUDA\_NOT\_INITIALIZED If using zero for 'fromContext' and CUDA has not been initialized yet on the calling thread.
- OPTIX\_ERROR\_CUDA\_ERROR CUDA operation failed.
- OPTIX\_ERROR\_HOST\_OUT\_OF\_MEMORY Heap allocation failed.
- OPTIX\_ERROR\_INTERNAL\_ERROR Internal error

## 8.17.2.19 optixDeviceContextDestroy()

```
OptixResult optixDeviceContextDestroy (
    OptixDeviceContext context )
```

Destroys all CPU and GPU state associated with the device.

It will attempt to block on CUDA streams that have launch work outstanding.

Any API objects, such as OptixModule and OptixPipeline, not already destroyed will be destroyed.

Thread safety: A device context must not be destroyed while it is still in use by concurrent API calls in other threads.

## 8.17.2.20 optixDeviceContextGetCacheDatabaseSizes()

```
OptixResult optixDeviceContextGetCacheDatabaseSizes (
    OptixDeviceContext context,
    size_t * lowWaterMark,
    size_t * highWaterMark )
```

Returns the low and high water marks for disk cache garbage collection. If the cache has been disabled by setting the environment variable OPTIX\_CACHE\_MAXSIZE=0, this function will return 0 for the low and high water marks.

Parameters

|     |                      |                     |
|-----|----------------------|---------------------|
| in  | <i>context</i>       | the device context  |
| out | <i>lowWaterMark</i>  | the low water mark  |
| out | <i>highWaterMark</i> | the high water mark |

## 8.17.2.21 optixDeviceContextGetCacheEnabled()

```
OptixResult optixDeviceContextGetCacheEnabled (
    OptixDeviceContext context,
    int * enabled )
```

Indicates whether the disk cache is enabled or disabled.

Parameters

|     |                |                             |
|-----|----------------|-----------------------------|
| in  | <i>context</i> | the device context          |
| out | <i>enabled</i> | 1 if enabled, 0 if disabled |

## 8.17.2.22 optixDeviceContextGetCacheLocation()

```
OptixResult optixDeviceContextGetCacheLocation (
    OptixDeviceContext context,
    char * location,
    size_t locationSize )
```

Returns the location of the disk cache. If the cache has been disabled by setting the environment variable OPTIX\_CACHE\_MAXSIZE=0, this function will return an empty string.

Parameters

|     |                     |                                                              |
|-----|---------------------|--------------------------------------------------------------|
| in  | <i>context</i>      | the device context                                           |
| out | <i>location</i>     | directory of disk cache, null terminated if locationSize > 0 |
| in  | <i>locationSize</i> | locationSize                                                 |

## 8.17.2.23 optixDeviceContextGetProperty()

```
OptixResult optixDeviceContextGetProperty (
    OptixDeviceContext context,
```

```

    OptixDeviceProperty property,
    void * value,
    size_t sizeInBytes )

```

Query properties of a device context.

Parameters

|     |                    |                                              |
|-----|--------------------|----------------------------------------------|
| in  | <i>context</i>     | the device context to query the property for |
| in  | <i>property</i>    | the property to query                        |
| out | <i>value</i>       | pointer to the returned                      |
| in  | <i>sizeInBytes</i> | size of output                               |

### 8.17.2.24 optixDeviceContextSetCacheDatabaseSizes()

```

OptixResult optixDeviceContextSetCacheDatabaseSizes (
    OptixDeviceContext context,
    size_t lowWaterMark,
    size_t highWaterMark )

```

Sets the low and high water marks for disk cache garbage collection.

Garbage collection is triggered when a new entry is written to the cache and the current cache data size plus the size of the cache entry that is about to be inserted exceeds the high water mark. Garbage collection proceeds until the size reaches the low water mark. Garbage collection will always free enough space to insert the new entry without exceeding the low water mark. Setting either limit to zero will disable garbage collection. An error will be returned if both limits are non-zero and the high water mark is smaller than the low water mark.

Note that garbage collection is performed only on writes to the disk cache. No garbage collection is triggered on disk cache initialization or immediately when calling this function, but on subsequent inserting of data into the database.

If the size of a compiled module exceeds the value configured for the high water mark and garbage collection is enabled, the module will not be added to the cache and a warning will be added to the log.

The high water mark can be overridden with the environment variable OPTIX\_CACHE\_MAXSIZE. The environment variable takes precedence over the function parameters. The low water mark will be set to half the value of OPTIX\_CACHE\_MAXSIZE. Setting OPTIX\_CACHE\_MAXSIZE to 0 will disable the disk cache, but will not alter the contents of the cache. Negative and non-integer values will be ignored.

Parameters

|    |                      |                     |
|----|----------------------|---------------------|
| in | <i>context</i>       | the device context  |
| in | <i>lowWaterMark</i>  | the low water mark  |
| in | <i>highWaterMark</i> | the high water mark |

### 8.17.2.25 optixDeviceContextSetCacheEnabled()

```

OptixResult optixDeviceContextSetCacheEnabled (
    OptixDeviceContext context,

```

```
int enabled )
```

Enables or disables the disk cache.

If caching was previously disabled, enabling it will attempt to initialize the disk cache database using the currently configured cache location. An error will be returned if initialization fails.

Note that no in-memory cache is used, so no caching behavior will be observed if the disk cache is disabled.

The cache can be disabled by setting the environment variable OPTIX\_CACHE\_MAXSIZE=0. The environment variable takes precedence over this setting. See [optixDeviceContextSetCacheDatabaseSizes](#) for additional information.

Note that the disk cache can be disabled by the environment variable, but it cannot be enabled via the environment if it is disabled via the API.

Parameters

|    |                |                            |
|----|----------------|----------------------------|
| in | <i>context</i> | the device context         |
| in | <i>enabled</i> | 1 to enabled, 0 to disable |

#### 8.17.2.26 optixDeviceContextSetCacheLocation()

```
OptixResult optixDeviceContextSetCacheLocation (
    OptixDeviceContext context,
    const char * location )
```

Sets the location of the disk cache.

The location is specified by a directory. This directory should not be used for other purposes and will be created if it does not exist. An error will be returned if it is not possible to create the disk cache at the specified location for any reason (e.g., the path is invalid or the directory is not writable). Caching will be disabled if the disk cache cannot be initialized in the new location. If caching is disabled, no error will be returned until caching is enabled. If the disk cache is located on a network file share, behavior is undefined.

The location of the disk cache can be overridden with the environment variable OPTIX\_CACHE\_PATH. The environment variable takes precedence over this setting.

The default location depends on the operating system:

- Windows: LOCALAPPDATA%\NVIDIA\OptixCache
- Linux: /var/tmp/OptixCache\_<username> (or /tmp/OptixCache\_<username> if the first choice is not usable), the underscore and username suffix are omitted if the username cannot be obtained
- MacOS X: /Library/Application Support/NVIDIA/OptixCache

Parameters

|    |                 |                         |
|----|-----------------|-------------------------|
| in | <i>context</i>  | the device context      |
| in | <i>location</i> | directory of disk cache |

#### 8.17.2.27 optixDeviceContextSetLogCallback()

```
OptixResult optixDeviceContextSetLogCallback (
```

```

    OptixDeviceContext context,
    OptixLogCallback callbackFunction,
    void * callbackData,
    unsigned int callbackLevel )

```

Sets the current log callback method.

See [OptixLogCallback](#) for more details.

Thread safety: It is guaranteed that the callback itself (callbackFunction and callbackData) are updated atomically. It is not guaranteed that the callback itself (callbackFunction and callbackData) and the callbackLevel are updated atomically. It is unspecified when concurrent API calls using the same context start to make use of the new callback method.

#### Parameters

|    |                         |                                                               |
|----|-------------------------|---------------------------------------------------------------|
| in | <i>context</i>          | the device context                                            |
| in | <i>callbackFunction</i> | the callback function to call                                 |
| in | <i>callbackData</i>     | pointer to data passed to callback function while invoking it |
| in | <i>callbackLevel</i>    | callback level                                                |

### 8.17.2.28 optixDisplacementMicromapArrayBuild()

```

OptixResult optixDisplacementMicromapArrayBuild (
    OptixDeviceContext context,
    CUstream stream,
    const OptixDisplacementMicromapArrayBuildInput * buildInput,
    const OptixMicromapBuffers * buffers )

```

FIXME Construct an array of Displacement Micromap (DMMs).

Each triangle within a DMM GAS geometry references one DMM that specifies how to subdivide it into micro-triangles. A DMM gives a subdivision resolution into  $4^N$  micro-triangles, and displacement values for each of the vertices in the subdivided mesh. The values are combined with e.g. normal vectors, scale and bias given as AS build inputs, to get the final geometry. A DMM is encoded in one or more compressed blocks, each block having displacement values for a subtriangle of 64..1024 micro-triangles.

#### Parameters

|    |                   |                                                   |
|----|-------------------|---------------------------------------------------|
| in | <i>context</i>    |                                                   |
| in | <i>stream</i>     |                                                   |
| in | <i>buildInput</i> | a single build input object referencing many DMMs |
| in | <i>buffers</i>    | the buffers used for build                        |

### 8.17.2.29 optixDisplacementMicromapArrayComputeMemoryUsage()

```

OptixResult optixDisplacementMicromapArrayComputeMemoryUsage (
    OptixDeviceContext context,
    const OptixDisplacementMicromapArrayBuildInput * buildInput,
    OptixMicromapBufferSizes * bufferSizes )

```



Determine the amount of memory necessary for a Displacement Micromap Array build.

Parameters

|     |                    |
|-----|--------------------|
| in  | <i>context</i>     |
| in  | <i>buildInput</i>  |
| out | <i>bufferSizes</i> |

### 8.17.2.30 optixGetErrorName()

```
const char * optixGetErrorName (
    OptixResult result )
```

Returns a string containing the name of an error code in the enum.

Output is a string representation of the enum. For example "OPTIX\_SUCCESS" for OPTIX\_SUCCESS and "OPTIX\_ERROR\_INVALID\_VALUE" for OPTIX\_ERROR\_INVALID\_VALUE.

If the error code is not recognized, "Unrecognized OptixResult code" is returned.

Parameters

|    |               |                                              |
|----|---------------|----------------------------------------------|
| in | <i>result</i> | OptixResult enum to generate string name for |
|----|---------------|----------------------------------------------|

See also [optixGetErrorString](#)

### 8.17.2.31 optixGetErrorString()

```
const char * optixGetErrorString (
    OptixResult result )
```

Returns the description string for an error code.

Output is a string description of the enum. For example "Success" for OPTIX\_SUCCESS and "Invalid value" for OPTIX\_ERROR\_INVALID\_VALUE.

If the error code is not recognized, "Unrecognized OptixResult code" is returned.

Parameters

|    |               |                                                     |
|----|---------------|-----------------------------------------------------|
| in | <i>result</i> | OptixResult enum to generate string description for |
|----|---------------|-----------------------------------------------------|

See also [optixGetErrorName](#)

### 8.17.2.32 optixLaunch()

```
OptixResult optixLaunch (
    OptixPipeline pipeline,
    CUstream stream,
    CUdeviceptr pipelineParams,
    size_t pipelineParamsSize,
    const OptixShaderBindingTable * sbt,
    unsigned int width,
```

```
    unsigned int height,
    unsigned int depth )
```

Where the magic happens.

The stream and pipeline must belong to the same device context. Multiple launches may be issues in parallel from multiple threads to different streams.

pipelineParamsSize number of bytes are copied from the device memory pointed to by pipelineParams before launch. It is an error if pipelineParamsSize is greater than the size of the variable declared in modules and identified by `OptixPipelineCompileOptions::pipelineLaunchParamsVariableName`. If the launch params variable was optimized out or not found in the modules linked to the pipeline then the pipelineParams and pipelineParamsSize parameters are ignored.

sbt points to the shader binding table, which defines shader groupings and their resources. See the SBT spec.

#### Parameters

|    |                           |                               |
|----|---------------------------|-------------------------------|
| in | <i>pipeline</i>           |                               |
| in | <i>stream</i>             |                               |
| in | <i>pipelineParams</i>     |                               |
| in | <i>pipelineParamsSize</i> |                               |
| in | <i>sbt</i>                |                               |
| in | <i>width</i>              | number of elements to compute |
| in | <i>height</i>             | number of elements to compute |
| in | <i>depth</i>              | number of elements to compute |

Thread safety: In the current implementation concurrent launches to the same pipeline are not supported. Concurrent launches require separate OptixPipeline objects.

#### 8.17.2.33 optixModuleCreate()

```
OptixResult optixModuleCreate (
    OptixDeviceContext context,
    const OptixModuleCompileOptions * moduleCompileOptions,
    const OptixPipelineCompileOptions * pipelineCompileOptions,
    const char * input,
    size_t inputSize,
    char * logString,
    size_t * logStringSize,
    OptixModule * module )
```

Compiling programs into a module. These programs can be passed in as either PTX or OptiX-IR.

See the Programming Guide for details, as well as how to generate these encodings from CUDA sources.

logString is an optional buffer that contains compiler feedback and errors. This information is also passed to the context logger (if enabled), however it may be difficult to correlate output to the logger to specific API invocations when using multiple threads. The output to logString will only contain feedback for this specific invocation of this API call.

logStringSize as input should be a pointer to the number of bytes backing logString. Upon return it contains the length of the log message (including the null terminator) which may be greater than the input value. In this case, the log message will be truncated to fit into logString.

If logString or logStringSize are NULL, no output is written to logString. If logStringSize points to a value that is zero, no output is written. This does not affect output to the context logger if enabled.

#### Parameters

|         |                               |                                                                                                                      |
|---------|-------------------------------|----------------------------------------------------------------------------------------------------------------------|
| in      | <i>context</i>                |                                                                                                                      |
| in      | <i>moduleCompileOptions</i>   |                                                                                                                      |
| in      | <i>pipelineCompileOptions</i> | All modules in a pipeline need to use the same values for the pipeline compile options.                              |
| in      | <i>input</i>                  | Pointer to the input code.                                                                                           |
| in      | <i>inputSize</i>              | Parsing proceeds up to inputSize characters. Or, when reading PTX input, the first NUL byte, whichever occurs first. |
| out     | <i>logString</i>              | Information will be written to this string. If logStringSize > 0 logString will be null terminated.                  |
| in, out | <i>logStringSize</i>          |                                                                                                                      |
| out     | <i>module</i>                 |                                                                                                                      |

#### Returns

OPTIX\_ERROR\_INVALID\_VALUE - context is 0, moduleCompileOptions is 0, pipelineCompileOptions is 0, input is 0, module is 0.

### 8.17.2.34 optixModuleCreateWithTasks()

```
OptixResult optixModuleCreateWithTasks (
    OptixDeviceContext context,
    const OptixModuleCompileOptions * moduleCompileOptions,
    const OptixPipelineCompileOptions * pipelineCompileOptions,
    const char * input,
    size_t inputSize,
    char * logString,
    size_t * logStringSize,
    OptixModule * module,
    OptixTask * firstTask )
```

This function is designed to do just enough work to create the OptixTask return parameter and is expected to be fast enough run without needing parallel execution. A single thread could generate all the OptixTask objects for further processing in a work pool.

Options are similar to `optixModuleCreate()`, aside from the return parameter, firstTask.

The memory used to hold the input should be live until all tasks are finished.

It is illegal to call `optixModuleDestroy()` if any OptixTask objects are currently being executed. In that case OPTIX\_ERROR\_ILLEGAL\_DURING\_TASK\_EXECUTE will be returned.

If an invocation of `optixTaskExecute` fails, the OptixModule will be marked as OPTIX\_MODULE\_COMPILE\_STATE\_IMPEDING\_FAILURE if there are outstanding tasks or OPTIX\_MODULE\_

COMPILE\_STATE\_FAILURE if there are no outstanding tasks. Subsequent calls to `optixTaskExecute()` may execute additional work to collect compilation errors generated from the input. Currently executing tasks will not necessarily be terminated immediately but at the next opportunity. Logging will continue to be directed to the logger installed with the `OptixDeviceContext`. If `logString` is provided to `optixModuleCreateWithTasks()`, it will contain all the compiler feedback from all executed tasks. The lifetime of the memory pointed to by `logString` should extend from calling `optixModuleCreateWithTasks()` to when the compilation state is either `OPTIX_MODULE_COMPILE_STATE_FAILURE` or `OPTIX_MODULE_COMPILE_STATE_COMPLETED`. OptiX will not write to the `logString` outside of execution of `optixModuleCreateWithTasks()` or `optixTaskExecute()`. If the compilation state is `OPTIX_MODULE_COMPILE_STATE_IMENDING_FAILURE` and no further execution of `optixTaskExecute()` is performed the `logString` may be reclaimed by the application before calling `optixModuleDestroy()`. The contents of `logString` will contain output from currently completed tasks. All `OptixTask` objects associated with a given `OptixModule` will be cleaned up when `optixModuleDestroy()` is called regardless of whether the compilation was successful or not. If the compilation state is `OPTIX_MODULE_COMPILE_STATE_IMENDING_FAILURE`, any unstarted `OptixTask` objects do not need to be executed though there is no harm doing so.

See also `optixModuleCreate`

### 8.17.2.35 optixModuleDestroy()

```
OptixResult optixModuleDestroy (
    OptixModule module )
```

Call for `OptixModule` objects created with `optixModuleCreate` and `optixModuleDeserialize`.

Modules must not be destroyed while they are still used by any program group.

Thread safety: A module must not be destroyed while it is still in use by concurrent API calls in other threads.

### 8.17.2.36 optixModuleGetCompilationState()

```
OptixResult optixModuleGetCompilationState (
    OptixModule module,
    OptixModuleCompileState * state )
```

When creating a module with tasks, the current state of the module can be queried using this function.

Thread safety: Safe to call from any thread until `optixModuleDestroy` is called.

See also `optixModuleCreateWithTasks`

### 8.17.2.37 optixOpacityMicromapArrayBuild()

```
OptixResult optixOpacityMicromapArrayBuild (
    OptixDeviceContext context,
    CUstream stream,
    const OptixOpacityMicromapArrayBuildInput * buildInput,
    const OptixMicromapBuffers * buffers )
```

Construct an array of Opacity Micromaps.

Each triangle within an instance/GAS may reference one opacity micromap to give finer control over alpha behavior. An opacity micromap consists of a set of  $4^N$  micro-triangles in a triangular uniform barycentric grid. Multiple opacity micromaps are collected (built) into an opacity micromap array with this function. Each geometry in a GAS may bind a single opacity micromap array and can use opacity

micromaps from that array only.

Each micro-triangle within a opacity micromap can be in one of four states: Transparent, Opaque, Unknown-Transparent or Unknown-Opaque. During traversal, if a triangle with a opacity micromap attached is intersected, the opacity micromap is queried to categorize the hit as either opaque, unknown (alpha) or a miss. Geometry, ray or instance flags that modify the alpha/opaque behavior are applied *after* this opacity micromap query.

The opacity micromap query may operate in 2-state mode (alpha testing) or 4-state mode (AHS culling), depending on the opacity micromap type and ray/instance flags. When operating in 2-state mode, alpha hits will not be reported, and transparent and opaque hits must be accurate.

#### Parameters

|    |                   |                                                                |
|----|-------------------|----------------------------------------------------------------|
| in | <i>context</i>    |                                                                |
| in | <i>stream</i>     |                                                                |
| in | <i>buildInput</i> | a single build input object referencing many opacity micromaps |
| in | <i>buffers</i>    | the buffers used for build                                     |

### 8.17.2.38 optixOpacityMicromapArrayComputeMemoryUsage()

```
OptixResult optixOpacityMicromapArrayComputeMemoryUsage (
    OptixDeviceContext context,
    const OptixOpacityMicromapArrayBuildInput * buildInput,
    OptixMicromapBufferSizes * bufferSizes )
```

Determine the amount of memory necessary for a Opacity Micromap Array build.

#### Parameters

|     |                    |
|-----|--------------------|
| in  | <i>context</i>     |
| in  | <i>buildInput</i>  |
| out | <i>bufferSizes</i> |

### 8.17.2.39 optixOpacityMicromapArrayGetRelocationInfo()

```
OptixResult optixOpacityMicromapArrayGetRelocationInfo (
    OptixDeviceContext context,
    CUdeviceptr opacityMicromapArray,
    OptixRelocationInfo * info )
```

Obtain relocation information, stored in [OptixRelocationInfo](#), for a given context and opacity micromap array.

The relocation information can be passed to [optixCheckRelocationCompatibility](#) to determine if a opacity micromap array, referenced by buffers, can be relocated to a different device's memory space (see [optixCheckRelocationCompatibility](#)).

When used with [optixOpacityMicromapArrayRelocate](#), it provides data necessary for doing the relocation.

If the opacity micromap array data associated with 'opacityMicromapArray' is copied multiple times, the same [OptixRelocationInfo](#) can also be used on all copies.

## Parameters

|     |                             |
|-----|-----------------------------|
| in  | <i>context</i>              |
| in  | <i>opacityMicromapArray</i> |
| out | <i>info</i>                 |

## 8.17.2.40 optixOpacityMicromapArrayRelocate()

```
OptixResult optixOpacityMicromapArrayRelocate (
    OptixDeviceContext context,
    CUstream stream,
    const OptixRelocationInfo * info,
    CUdeviceptr targetOpacityMicromapArray,
    size_t targetOpacityMicromapArraySizeInBytes )
```

optixOpacityMicromapArrayRelocate is called to update the opacity micromap array after it has been relocated. Relocation is necessary when the opacity micromap array's location in device memory has changed. optixOpacityMicromapArrayRelocate does not copy the memory. This function only operates on the relocated memory whose new location is specified by 'targetOpacityMicromapArray'. The original memory (source) is not required to be valid, only the [OptixRelocationInfo](#).

Before calling optixOpacityMicromapArrayRelocate, optixCheckRelocationCompatibility should be called to ensure the copy will be compatible with the destination device context.

The memory pointed to by 'targetOpacityMicromapArray' should be allocated with the same size as the source opacity micromap array. Similar to the '[OptixMicromapBuffers::output](#)' used in optixOpacityMicromapArrayBuild, this pointer must be a multiple of OPTIX\_OPACITY\_MICROMAP\_ARRAY\_BUFFER\_BYTE\_ALIGNMENT.

The memory in 'targetOpacityMicromapArray' must be allocated as long as the opacity micromap array is in use.

Note that any Acceleration Structures build using the original memory (source) as input will still be associated with this original memory. To associate an existing (possibly relocated) Acceleration Structures with the relocated opacity micromap array, use optixAccelBuild to update the existing Acceleration Structures (See OPTIX\_BUILD\_OPERATION\_UPDATE)

## Parameters

|    |                                              |
|----|----------------------------------------------|
| in | <i>context</i>                               |
| in | <i>stream</i>                                |
| in | <i>info</i>                                  |
| in | <i>targetOpacityMicromapArray</i>            |
| in | <i>targetOpacityMicromapArraySizeInBytes</i> |

## 8.17.2.41 optixPipelineCreate()

```
OptixResult optixPipelineCreate (
    OptixDeviceContext context,
    const OptixPipelineCompileOptions * pipelineCompileOptions,
    const OptixPipelineLinkOptions * pipelineLinkOptions,
```

```

const OptixProgramGroup * programGroups,
unsigned int numProgramGroups,
char * logString,
size_t * logStringSize,
OptixPipeline * pipeline )

```

logString is an optional buffer that contains compiler feedback and errors. This information is also passed to the context logger (if enabled), however it may be difficult to correlate output to the logger to specific API invocations when using multiple threads. The output to logString will only contain feedback for this specific invocation of this API call.

logStringSize as input should be a pointer to the number of bytes backing logString. Upon return it contains the length of the log message (including the null terminator) which may be greater than the input value. In this case, the log message will be truncated to fit into logString.

If logString or logStringSize are NULL, no output is written to logString. If logStringSize points to a value that is zero, no output is written. This does not affect output to the context logger if enabled.

#### Parameters

|         |                               |                                                                                                     |
|---------|-------------------------------|-----------------------------------------------------------------------------------------------------|
| in      | <i>context</i>                |                                                                                                     |
| in      | <i>pipelineCompileOptions</i> |                                                                                                     |
| in      | <i>pipelineLinkOptions</i>    |                                                                                                     |
| in      | <i>programGroups</i>          | array of ProgramGroup objects                                                                       |
| in      | <i>numProgramGroups</i>       | number of ProgramGroup objects                                                                      |
| out     | <i>logString</i>              | Information will be written to this string. If logStringSize > 0 logString will be null terminated. |
| in, out | <i>logStringSize</i>          |                                                                                                     |
| out     | <i>pipeline</i>               |                                                                                                     |

#### 8.17.2.42 optixPipelineDestroy()

```

OptixResult optixPipelineDestroy (
    OptixPipeline pipeline )

```

Thread safety: A pipeline must not be destroyed while it is still in use by concurrent API calls in other threads.

#### 8.17.2.43 optixPipelineSetStackSize()

```

OptixResult optixPipelineSetStackSize (
    OptixPipeline pipeline,
    unsigned int directCallableStackSizeFromTraversal,
    unsigned int directCallableStackSizeFromState,
    unsigned int continuationStackSize,
    unsigned int maxTraversableGraphDepth )

```

Sets the stack sizes for a pipeline.

Users are encouraged to see the programming guide and the implementations of the helper functions to understand how to construct the stack sizes based on their particular needs.

If this method is not used, an internal default implementation is used. The default implementation is correct (but not necessarily optimal) as long as the maximum depth of call trees of CC programs is at most 2, and no DC programs or motion transforms are used.

The `maxTraversableGraphDepth` responds to the maximal number of traversables visited when calling trace. Every acceleration structure and motion transform count as one level of traversal. E.g., for a simple IAS (instance acceleration structure) -> GAS (geometry acceleration structure) traversal graph, the `maxTraversableGraphDepth` is two. For IAS -> MT (motion transform) -> GAS, the `maxTraversableGraphDepth` is three. Note that it does not matter whether a IAS or GAS has motion or not, it always counts as one. Launching optix with exceptions turned on (see `OPTIX_EXCEPTION_FLAG_TRACE_DEPTH`) will throw an exception if the specified `maxTraversableGraphDepth` is too small.

#### Parameters

|    |                                             |                                                                                    |
|----|---------------------------------------------|------------------------------------------------------------------------------------|
| in | <i>pipeline</i>                             | The pipeline to configure the stack size for.                                      |
| in | <i>directCallableStackSizeFromTraversal</i> | The direct stack size requirement for direct callables invoked from IS or AH.      |
| in | <i>directCallableStackSizeFromState</i>     | The direct stack size requirement for direct callables invoked from RG, MS, or CH. |
| in | <i>continuationStackSize</i>                | The continuation stack requirement.                                                |
| in | <i>maxTraversableGraphDepth</i>             | The maximum depth of a traversable graph passed to trace.                          |

#### 8.17.2.44 optixProgramGroupCreate()

```
OptixResult optixProgramGroupCreate (
    OptixDeviceContext context,
    const OptixProgramGroupDesc * programDescriptions,
    unsigned int numProgramGroups,
    const OptixProgramGroupOptions * options,
    char * logString,
    size_t * logStringSize,
    OptixProgramGroup * programGroups )
```

`logString` is an optional buffer that contains compiler feedback and errors. This information is also passed to the context logger (if enabled), however it may be difficult to correlate output to the logger to specific API invocations when using multiple threads. The output to `logString` will only contain feedback for this specific invocation of this API call.

`logStringSize` as input should be a pointer to the number of bytes backing `logString`. Upon return it contains the length of the log message (including the null terminator) which may be greater than the input value. In this case, the log message will be truncated to fit into `logString`.

If `logString` or `logStringSize` are NULL, no output is written to `logString`. If `logStringSize` points to a value that is zero, no output is written. This does not affect output to the context logger if enabled.

Creates `numProgramGroups` `OptixProgramGroup` objects from the specified `OptixProgramGroupDesc` array. The size of the arrays must match.

#### Parameters

|    |                |  |
|----|----------------|--|
| in | <i>context</i> |  |
|----|----------------|--|



## Parameters

|         |                            |                                                                                                     |
|---------|----------------------------|-----------------------------------------------------------------------------------------------------|
| in      | <i>programDescriptions</i> | N * <a href="#">OptixProgramGroupDesc</a>                                                           |
| in      | <i>numProgramGroups</i>    | N                                                                                                   |
| in      | <i>options</i>             |                                                                                                     |
| out     | <i>logString</i>           | Information will be written to this string. If logStringSize > 0 logString will be null terminated. |
| in, out | <i>logStringSize</i>       |                                                                                                     |
| out     | <i>programGroups</i>       |                                                                                                     |

## 8.17.2.45 optixProgramGroupDestroy()

```
OptixResult optixProgramGroupDestroy (
    OptixProgramGroup programGroup )
```

Thread safety: A program group must not be destroyed while it is still in use by concurrent API calls in other threads.

## 8.17.2.46 optixProgramGroupGetStackSize()

```
OptixResult optixProgramGroupGetStackSize (
    OptixProgramGroup programGroup,
    OptixStackSizes * stackSizes,
    OptixPipeline pipeline )
```

Returns the stack sizes for the given program group. When programs in this `programGroup` are relying on external functions, the corresponding stack sizes can only be correctly retrieved when all functions are known after linking, i.e. when a pipeline has been created. When `pipeline` is set to NULL, the stack size will be calculated excluding external functions. In this case a warning will be issued if external functions are referenced by the `OptixModule`.

## Parameters

|     |                     |                                                                      |
|-----|---------------------|----------------------------------------------------------------------|
| in  | <i>programGroup</i> | the program group                                                    |
| out | <i>stackSizes</i>   | the corresponding stack sizes                                        |
| in  | <i>pipeline</i>     | considering the program group within the given pipeline, can be NULL |

## 8.17.2.47 optixSbtRecordPackHeader()

```
OptixResult optixSbtRecordPackHeader (
    OptixProgramGroup programGroup,
    void * sbtRecordHeaderHostPointer )
```

## Parameters

|     |                                   |                                             |
|-----|-----------------------------------|---------------------------------------------|
| in  | <i>programGroup</i>               | the program group containing the program(s) |
| out | <i>sbtRecordHeaderHostPointer</i> | the result sbt record header                |

### 8.17.2.48 optixTaskExecute()

```
OptixResult optixTaskExecute (
    OptixTask task,
    OptixTask * additionalTasks,
    unsigned int maxNumAdditionalTasks,
    unsigned int * numAdditionalTasksCreated )
```

Each OptixTask should be executed with `optixTaskExecute()`. If additional parallel work is found, new OptixTask objects will be returned in `additionalTasks` along with the number of additional tasks in `numAdditionalTasksCreated`. The parameter `additionalTasks` should point to a user allocated array of minimum size `maxNumAdditionalTasks`. OptiX can generate upto `maxNumAdditionalTasks` additional tasks.

Each task can be executed in parallel and in any order.

Thread safety: Safe to call from any thread until `optixModuleDestroy()` is called for any associated task.

See also `optixModuleCreateWithTasks`

#### Parameters

|     |                                  |                                                                                            |
|-----|----------------------------------|--------------------------------------------------------------------------------------------|
| in  | <i>task</i>                      | the OptixTask to execute                                                                   |
| in  | <i>additionalTasks</i>           | pointer to array of OptixTask objects to be filled in                                      |
| in  | <i>maxNumAdditionalTasks</i>     | maximum number of additional OptixTask objects                                             |
| out | <i>numAdditionalTasksCreated</i> | number of OptixTask objects created by OptiX and written into <code>additionalTasks</code> |

## 8.18 optix\_host.h

[Go to the documentation of this file.](#)

```
1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
5  * rights in and to this software, related documentation and any modifications thereto.
6  * Any use, reproduction, disclosure or distribution of this software and related
7  * documentation without an express license agreement from NVIDIA Corporation is strictly
8  * prohibited.
9  *
10 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
11 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
12 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A
13 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
14 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
15 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
16 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
17 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
18 * SUCH DAMAGES
19 */
20
21
22
23
24
25
26
27
28 #ifndef OPTIX_OPTIX_HOST_H
29 #define OPTIX_OPTIX_HOST_H
30
31 #include "optix_types.h"
32 #if !defined(OPTIX_DONT_INCLUDE_CUDA)
33 // If OPTIX_DONT_INCLUDE_CUDA is defined, cuda driver types must be defined through other
34 // means before including optix headers.
35 #include <cuda.h>
```

```

36 #endif
37
38 #ifdef NV_MODULE_OPTIX
39 // This is a mechanism to include <g_nvconfig.h> in driver builds only and translate any nvconfig macro to
40 // a custom OPTIX-specific macro, that can also be used in SDK builds/installs
41 #include <exp/misc/optix_nvconfig_translate.h> // includes <g_nvconfig.h>
42 #endif // NV_MODULE_OPTIX
43
44 #ifdef __cplusplus
45 extern "C" {
46 #endif
47
48
49
50
51
52
53
54
55
56
57
58
59
60
61
62
63
64
65 const char* optixGetErrorName(OptixResult result);
66
67 const char* optixGetErrorString(OptixResult result);
68
69
70
71
72
73
74
75
76
77
78
79
80
81
82
83
84
85
86
87
88
89
90
91
92
93
94
95
96
97
98
99
100
101
102 OptixResult optixDeviceContextCreate(CUcontext fromContext, const OptixDeviceContextOptions* options,
103 OptixDeviceContext* context);
104
105
106
107
108
109
110
111
112 OptixResult optixDeviceContextDestroy(OptixDeviceContext context);
113
114
115
116
117
118
119
120 OptixResult optixDeviceContextGetProperty(OptixDeviceContext context, OptixDeviceProperty property,
121 void* value, size_t sizeInBytes);
122
123
124
125
126
127
128
129
130
131
132
133
134
135 OptixResult optixDeviceContextSetLogCallback(OptixDeviceContext context,
136 OptixLogCallback callbackFunction,
137 void* callbackData,
138 unsigned int callbackLevel);
139
140
141
142
143
144
145
146
147
148
149
150
151
152
153
154
155
156
157
158 OptixResult optixDeviceContextSetCacheEnabled(OptixDeviceContext context,
159 int enabled);
160
161
162
163
164
165
166
167
168
169
170
171
172
173
174
175
176
177
178
179
180
181 OptixResult optixDeviceContextSetCacheLocation(OptixDeviceContext context, const char* location);
182
183
184
185
186
187
188
189
190
191
192
193
194
195
196
197
198
199
200
201
202
203
204
205
206
207
208
209
210 OptixResult optixDeviceContextSetCacheDatabaseSizes(OptixDeviceContext context, size_t lowWaterMark,
211 size_t highWaterMark);
212
213
214
215
216 OptixResult optixDeviceContextGetCacheEnabled(OptixDeviceContext context, int* enabled);
217
218
219
220
221
222
223 OptixResult optixDeviceContextGetCacheLocation(OptixDeviceContext context, char* location, size_t
224 locationSize);
225
226
227
228
229
230
231
232 OptixResult optixDeviceContextGetCacheDatabaseSizes(OptixDeviceContext context, size_t* lowWaterMark,
233 size_t* highWaterMark);
234
235
236
237
238
239
240
241
242
243
244
245
246
247
248
249
250
251
252
253
254
255
256
257
258
259
260
261
262 OptixResult optixPipelineCreate(OptixDeviceContext context,
263 const OptixPipelineCompileOptions* pipelineCompileOptions,
264 const OptixPipelineLinkOptions* pipelineLinkOptions,
265 const OptixProgramGroup* programGroups,
266 unsigned int numProgramGroups,
267 char* logString,
268 size_t* logStringSize,
269 OptixPipeline* pipeline);
270
271
272 OptixResult optixPipelineDestroy(OptixPipeline pipeline);
273
274
275
276 OptixResult optixPipelineSetStackSize(OptixPipeline pipeline,
277 unsigned int directCallableStackSizeFromTraversal,

```

```

298         unsigned int    directCallableStackSizeFromState,
299         unsigned int    continuationStackSize,
300         unsigned int    maxTraversableGraphDepth);
301
302
303
304
305
306
336 OptixResult optixModuleCreate(OptixDeviceContext context,
337                               const OptixModuleCompileOptions* moduleCompileOptions,
338                               const OptixPipelineCompileOptions* pipelineCompileOptions,
339                               const char* input,
340                               size_t inputSize,
341                               char* logString,
342                               size_t* logStringSize,
343                               OptixModule* module);
344
345
346
347
385 OptixResult optixModuleCreateWithTasks(OptixDeviceContext context,
386   const OptixModuleCompileOptions* moduleCompileOptions,
387   const OptixPipelineCompileOptions* pipelineCompileOptions,
388   const char* input,
389   size_t inputSize,
390   char* logString,
391   size_t* logStringSize,
392   OptixModule* module,
393   OptixTask* firstTask);
394
401 OptixResult optixModuleGetCompilationState(OptixModule module, OptixModuleCompileState* state);
402
408 OptixResult optixModuleDestroy(OptixModule module);
409
413 OptixResult optixBuiltinISModuleGet(OptixDeviceContext context,
414                                     const OptixModuleCompileOptions* moduleCompileOptions,
415                                     const OptixPipelineCompileOptions* pipelineCompileOptions,
416                                     const OptixBuiltinISOOptions* builtinISOOptions,
417                                     OptixModule* builtinModule);
418
419
420
421
422
423
441 OptixResult optixTaskExecute(OptixTask task, OptixTask* additionalTasks, unsigned int
maxNumAdditionalTasks, unsigned int* numAdditionalTasksCreated);
442
443
444
445
446
447
456 OptixResult optixProgramGroupGetStackSize(OptixProgramGroup programGroup, OptixStackSizes* stackSizes,
OptixPipeline pipeline);
457
483 OptixResult optixProgramGroupCreate(OptixDeviceContext context,
484                                     const OptixProgramGroupDesc* programDescriptions,
485                                     unsigned int numProgramGroups,
486                                     const OptixProgramGroupOptions* options,
487                                     char* logString,
488                                     size_t* logStringSize,
489                                     OptixProgramGroup* programGroups);
490
492 OptixResult optixProgramGroupDestroy(OptixProgramGroup programGroup);
493
494
495
496
497
498
525 OptixResult optixLaunch(OptixPipeline pipeline,
526                          CUstream stream,
527                          CUdeviceptr pipelineParams,
528                          size_t pipelineParamsSize,

```

```

529         const OptixShaderBindingTable* sbt,
530         unsigned int width,
531         unsigned int height,
532         unsigned int depth);
533
536 OptixResult optixSbtRecordPackHeader(OptixProgramGroup programGroup, void* sbtRecordHeaderHostPointer);
537
539
541
542
548 OptixResult optixAccelComputeMemoryUsage(OptixDeviceContext context,
549         const OptixAccelBuildOptions* accelOptions,
550         const OptixBuildInput* buildInputs,
551         unsigned int numBuildInputs,
552         OptixAccelBufferSizes* bufferSizes);
553
556 OptixResult optixAccelBuild(OptixDeviceContext context,
557         CUstream stream,
558         const OptixAccelBuildOptions* accelOptions,
559         const OptixBuildInput* buildInputs,
560         unsigned int numBuildInputs,
561         CUdeviceptr tempBuffer,
562         size_t tempBufferSizeInBytes,
563         CUdeviceptr outputBuffer,
564         size_t outputBufferSizeInBytes,
565         OptixTraversableHandle* outputHandle,
566         const OptixAccelEmitDesc* emittedProperties,
567         unsigned int numEmittedProperties);
568
596 OptixResult optixAccelGetRelocationInfo(OptixDeviceContext context, OptixTraversableHandle handle,
OptixRelocationInfo* info);
597
609 OptixResult optixCheckRelocationCompatibility(OptixDeviceContext context, const OptixRelocationInfo*
info, int* compatible);
610
648 OptixResult optixAccelRelocate(OptixDeviceContext context,
649         CUstream stream,
650         const OptixRelocationInfo* info,
651         const OptixRelocateInput* relocateInputs,
652         size_t numRelocateInputs,
653         CUdeviceptr targetAccel,
654         size_t targetAccelSizeInBytes,
655         OptixTraversableHandle* targetHandle);
656
674 OptixResult optixAccelCompact(OptixDeviceContext context,
675         CUstream stream,
676         OptixTraversableHandle inputHandle,
677         CUdeviceptr outputBuffer,
678         size_t outputBufferSizeInBytes,
679         OptixTraversableHandle* outputHandle);
680
689 OptixResult optixAccelEmitProperty(OptixDeviceContext context,
690         CUstream stream,
691         OptixTraversableHandle handle,
692         const OptixAccelEmitDesc* emittedProperty);
693
698 OptixResult optixConvertPointerToTraversableHandle(OptixDeviceContext onDevice,
699         CUdeviceptr pointer,
700         OptixTraversableType traversableType,
701         OptixTraversableHandle* traversableHandle);
702
703
709 OptixResult optixOpacityMicromapArrayComputeMemoryUsage(OptixDeviceContext context,
710         const OptixOpacityMicromapArrayBuildInput* buildInput,
711         OptixMicromapBufferSizes* bufferSizes);
712
735 OptixResult optixOpacityMicromapArrayBuild(OptixDeviceContext context,

```

```

736                                     CUstream          stream,
737                                     const OptixOpacityMicromapArrayBuildInput* buildInput,
738                                     const OptixMicromapBuffers*          buffers);
739
755 OptixResult optixOpacityMicromapArrayGetRelocationInfo(OptixDeviceContext context, CUdeviceptr
opacityMicromapArray, OptixRelocationInfo* info);
756
783 OptixResult optixOpacityMicromapArrayRelocate(OptixDeviceContext context,
784   CUstream          stream,
785   const OptixRelocationInfo* info,
786   CUdeviceptr          targetOpacityMicromapArray,
787   size_t
targetOpacityMicromapArraySizeInBytes);
788
794 OptixResult optixDisplacementMicromapArrayComputeMemoryUsage(OptixDeviceContext
context,
795   const
OptixDisplacementMicromapArrayBuildInput* buildInput,
796   OptixMicromapBufferSizes* bufferSizes);
797
811 OptixResult optixDisplacementMicromapArrayBuild(OptixDeviceContext          context,
812   CUstream          stream,
813   const OptixDisplacementMicromapArrayBuildInput* buildInput,
814   const OptixMicromapBuffers*          buffers);
815
816
818
820
821
833 OptixResult optixDenoiserCreate(OptixDeviceContext context,
834                                 OptixDenoiserModelKind modelKind,
835                                 const OptixDenoiserOptions* options,
836                                 OptixDenoiser* denoiser);
837
850 OptixResult optixDenoiserCreateWithUserModel(OptixDeviceContext context,
851   const void* userData, size_t userDataSizeInBytes,
OptixDenoiser* denoiser);
852
854 OptixResult optixDenoiserDestroy(OptixDenoiser denoiser);
855
875 OptixResult optixDenoiserComputeMemoryResources(const OptixDenoiser denoiser,
876  unsigned int      outputWidth,
877  unsigned int      outputHeight,
878  OptixDenoiserSizes* returnSizes);
879
896 OptixResult optixDenoiserSetup(OptixDenoiser denoiser,
897                                CUstream      stream,
898                                unsigned int   inputWidth,
899                                unsigned int   inputHeight,
900                                CUdeviceptr    denoiserState,
901                                size_t         denoiserStateSizeInBytes,
902                                CUdeviceptr    scratch,
903                                size_t         scratchSizeInBytes);
904
970 OptixResult optixDenoiserInvoke(OptixDenoiser          denoiser,
971                                CUstream          stream,
972                                const OptixDenoiserParams* params,
973                                CUdeviceptr          denoiserState,
974                                size_t               denoiserStateSizeInBytes,
975                                const OptixDenoiserGuideLayer* guideLayer,
976                                const OptixDenoiserLayer*    layers,
977                                unsigned int             numLayers,
978                                unsigned int             inputOffsetX,
979                                unsigned int             inputOffsetY,
980                                CUdeviceptr             scratch,
981                                size_t                   scratchSizeInBytes);
982

```

```

1006 OptixResult optixDenoiserComputeIntensity(OptixDenoiser    denoiser,
1007   CUstream        stream,
1008   const OptixImage2D* inputImage,
1009   CUdeviceptr      outputIntensity,
1010   CUdeviceptr      scratch,
1011   size_t           scratchSizeInBytes);
1012
1027 OptixResult optixDenoiserComputeAverageColor(OptixDenoiser    denoiser,
1028   CUstream        stream,
1029   const OptixImage2D* inputImage,
1030   CUdeviceptr      outputAverageColor,
1031   CUdeviceptr      scratch,
1032   size_t           scratchSizeInBytes);
1033
1035
1036 #ifdef __cplusplus
1037 }
1038 #endif
1039
1040 #include "optix_function_table.h"
1041
1042 #endif // OPTIX_OPTIX_HOST_H

```

## 8.19 optix\_micromap.h File Reference

### Functions

- [OPTIX\\_MICROMAP\\_INLINE\\_FUNC](#) void `optixMicromapIndexToBaseBarycentrics` (unsigned int `micromapTriangleIndex`, unsigned int `subdivisionLevel`, float2 &`baseBarycentrics0`, float2 &`baseBarycentrics1`, float2 &`baseBarycentrics2`)
- [OPTIX\\_MICROMAP\\_INLINE\\_FUNC](#) float2 `optixBaseBarycentricsToMicroBarycentrics` (float2 `baseBarycentrics`, float2 `microVertexBaseBarycentrics[3]`)

### 8.19.1 Detailed Description

OptiX micromap helper functions.

Author

NVIDIA Corporation

OptiX micromap helper functions. Useable on either host or device.

### 8.19.2 Function Documentation

#### 8.19.2.1 `optixBaseBarycentricsToMicroBarycentrics()`

```

OPTIX_MICROMAP_INLINE_FUNC float2 optixBaseBarycentricsToMicroBarycentrics (
    float2 baseBarycentrics,
    float2 microVertexBaseBarycentrics[3] )

```

Maps barycentrics in the space of the base triangle to barycentrics of a micro triangle. The vertices of the micro triangle are defined by its barycentrics in the space of the base triangle. These can be queried for a DMM hit by using `optixGetMicroTriangleBarycentricsData()`.

#### 8.19.2.2 `optixMicromapIndexToBaseBarycentrics()`

```

OPTIX_MICROMAP_INLINE_FUNC void optixMicromapIndexToBaseBarycentrics (
    unsigned int micromapTriangleIndex,

```

```

    unsigned int subdivisionLevel,
    float2 & baseBarycentrics0,
    float2 & baseBarycentrics1,
    float2 & baseBarycentrics2 )

```

Converts a micromap triangle index to the three base-triangle barycentric coordinates of the micro-triangle vertices in the base triangle. The base triangle is the triangle that the micromap is applied to. Note that for displaced micro-meshes this function can be used to compute a UV mapping from sub triangle to base triangle.

#### Parameters

|     |                              |                                                                                                                    |
|-----|------------------------------|--------------------------------------------------------------------------------------------------------------------|
| in  | <i>micromapTriangleIndex</i> | Index of a micro- or sub triangle within a micromap.                                                               |
| in  | <i>subdivisionLevel</i>      | Number of subdivision levels of the micromap or number of subdivision levels being considered (for sub triangles). |
| out | <i>baseBarycentrics0</i>     | Barycentric coordinates in the space of the base triangle of vertex 0 of the micromap triangle.                    |
| out | <i>baseBarycentrics1</i>     | Barycentric coordinates in the space of the base triangle of vertex 1 of the micromap triangle.                    |
| out | <i>baseBarycentrics2</i>     | Barycentric coordinates in the space of the base triangle of vertex 2 of the micromap triangle.                    |

## 8.20 optix\_micromap.h

[Go to the documentation of this file.](#)

```

1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * Redistribution and use in source and binary forms, with or without
5  * modification, are permitted provided that the following conditions
6  * are met:
7  * * Redistributions of source code must retain the above copyright
8  *   notice, this list of conditions and the following disclaimer.
9  * * Redistributions in binary form must reproduce the above copyright
10 *   notice, this list of conditions and the following disclaimer in the
11 *   documentation and/or other materials provided with the distribution.
12 * * Neither the name of NVIDIA CORPORATION nor the names of its
13 *   contributors may be used to endorse or promote products derived
14 *   from this software without specific prior written permission.
15 *
16 * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS "AS IS" AND ANY
17 * EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
18 * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
19 * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
20 * CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
21 * EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
22 * PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
23 * PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY
24 * OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
25 * (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
26 * OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
27 */
28
29 #ifndef OPTIX_OPTIX_MICROMAP_H
30 #define OPTIX_OPTIX_MICROMAP_H
31
32 #if !defined(OPTIX_DONT_INCLUDE_CUDA)
33 // If OPTIX_DONT_INCLUDE_CUDA is defined, cuda driver type float2 must be defined through other

```



```

42 // means before including optix headers.
43 #include <vector_types.h>
44 #endif
45 #include "internal/optix_micromap_impl.h"
46
47 OPTIX_MICROMAP_INLINE_FUNC void optixMicromapIndexToBaseBarycentrics(unsigned int micromapTriangleIndex,
48  unsigned int subdivisionLevel,
49  float2& baseBarycentrics0,
50  float2& baseBarycentrics1,
51  float2& baseBarycentrics2)
52 {
53     optix_impl::micro2bary(micromapTriangleIndex, subdivisionLevel, baseBarycentrics0, baseBarycentrics1,
54                             baseBarycentrics2);
55 }
56
57 OPTIX_MICROMAP_INLINE_FUNC float2 optixBaseBarycentricsToMicroBarycentrics(float2 baseBarycentrics,
58  float2 microVertexBaseBarycentrics[3])
59 {
60     return optix_impl::base2micro(baseBarycentrics, microVertexBaseBarycentrics);
61 }
62
63 #endif // OPTIX_OPTIX_MICROMAP_H

```

## 8.21 optix\_stack\_size.h File Reference

### Functions

- [OptixResult optixUtilAccumulateStackSizes](#) ([OptixProgramGroup](#) programGroup, [OptixStackSizes](#) \*stackSizes, [OptixPipeline](#) pipeline)
- [OptixResult optixUtilComputeStackSizes](#) (const [OptixStackSizes](#) \*stackSizes, unsigned int maxTraceDepth, unsigned int maxCCDepth, unsigned int maxDCDepth, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize)
- [OptixResult optixUtilComputeStackSizesDCSplit](#) (const [OptixStackSizes](#) \*stackSizes, unsigned int dssDCFromTraversal, unsigned int dssDCFromState, unsigned int maxTraceDepth, unsigned int maxCCDepth, unsigned int maxDCDepthFromTraversal, unsigned int maxDCDepthFromState, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize)
- [OptixResult optixUtilComputeStackSizesCssCCTree](#) (const [OptixStackSizes](#) \*stackSizes, unsigned int cssCCTree, unsigned int maxTraceDepth, unsigned int maxDCDepth, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize)
- [OptixResult optixUtilComputeStackSizesSimplePathTracer](#) ([OptixProgramGroup](#) programGroupRG, [OptixProgramGroup](#) programGroupMS1, const [OptixProgramGroup](#) \*programGroupCH1, unsigned int programGroupCH1Count, [OptixProgramGroup](#) programGroupMS2, const [OptixProgramGroup](#) \*programGroupCH2, unsigned int programGroupCH2Count, unsigned int \*directCallableStackSizeFromTraversal, unsigned int \*directCallableStackSizeFromState, unsigned int \*continuationStackSize, [OptixPipeline](#) pipeline)

### 8.21.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

## 8.22 optix\_stack\_size.h

[Go to the documentation of this file.](#)

```

1 /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * Redistribution and use in source and binary forms, with or without
5  * modification, are permitted provided that the following conditions
6  * are met:
7  * * Redistributions of source code must retain the above copyright
8  *   notice, this list of conditions and the following disclaimer.
9  * * Redistributions in binary form must reproduce the above copyright
10 *   notice, this list of conditions and the following disclaimer in the
11 *   documentation and/or other materials provided with the distribution.
12 * * Neither the name of NVIDIA CORPORATION nor the names of its
13 *   contributors may be used to endorse or promote products derived
14 *   from this software without specific prior written permission.
15 *
16 * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS "AS IS" AND ANY
17 * EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
18 * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
19 * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
20 * CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
21 * EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
22 * PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
23 * PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY
24 * OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
25 * (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
26 * OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
27 */
28
29
30
31
32
33 #ifndef OPTIX_OPTIX_STACK_SIZE_H
34 #define OPTIX_OPTIX_STACK_SIZE_H
35
36 #include "optix.h"
37
38 #include <algorithm>
39 #include <cstring>
40
41 #ifdef __cplusplus
42 extern "C" {
43 #endif
44
45 inline OptixResult optixUtilAccumulateStackSizes(OptixProgramGroup programGroup, OptixStackSizes*
stackSizes, OptixPipeline pipeline)
46 {
47     if(!stackSizes)
48         return OPTIX_ERROR_INVALID_VALUE;
49
50     OptixStackSizes localStackSizes;
51     OptixResult result = optixProgramGroupGetStackSize(programGroup, &localStackSizes, pipeline);
52     if(result != OPTIX_SUCCESS)
53         return result;
54
55     stackSizes->cssRG = std::max(stackSizes->cssRG, localStackSizes.cssRG);
56     stackSizes->cssMS = std::max(stackSizes->cssMS, localStackSizes.cssMS);
57     stackSizes->cssCH = std::max(stackSizes->cssCH, localStackSizes.cssCH);
58     stackSizes->cssAH = std::max(stackSizes->cssAH, localStackSizes.cssAH);
59     stackSizes->cssIS = std::max(stackSizes->cssIS, localStackSizes.cssIS);
60     stackSizes->cssCC = std::max(stackSizes->cssCC, localStackSizes.cssCC);
61     stackSizes->dssDC = std::max(stackSizes->dssDC, localStackSizes.dssDC);
62 }

```

```

71
72     return OPTIX_SUCCESS;
73 }
74
75 inline OptixResult optixUtilComputeStackSizes(const OptixStackSizes* stackSizes,
76   unsigned int      maxTraceDepth,
77   unsigned int      maxCCDepth,
78   unsigned int      maxDCDepth,
79   unsigned int*      directCallableStackSizeFromTraversal,
80   unsigned int*      directCallableStackSizeFromState,
81   unsigned int*      continuationStackSize)
82 {
83     if(!stackSizes)
84         return OPTIX_ERROR_INVALID_VALUE;
85
86     const unsigned int cssRG = stackSizes->cssRG;
87     const unsigned int cssMS = stackSizes->cssMS;
88     const unsigned int cssCH = stackSizes->cssCH;
89     const unsigned int cssAH = stackSizes->cssAH;
90     const unsigned int cssIS = stackSizes->cssIS;
91     const unsigned int cssCC = stackSizes->cssCC;
92     const unsigned int dssDC = stackSizes->dssDC;
93
94     if(directCallableStackSizeFromTraversal)
95         *directCallableStackSizeFromTraversal = maxDCDepth * dssDC;
96     if(directCallableStackSizeFromState)
97         *directCallableStackSizeFromState = maxDCDepth * dssDC;
98
99     // upper bound on continuation stack used by call trees of continuation callables
100     unsigned int cssCCTree = maxCCDepth * cssCC;
101
102     // upper bound on continuation stack used by CH or MS programs including the call tree of
103     // continuation callables
104     unsigned int cssCHOrMSPlusCCTree = std::max(cssCH, cssMS) + cssCCTree;
105
106     // clang-format off
107     if(continuationStackSize)
108         *continuationStackSize
109             = cssRG + cssCCTree
110             + (std::max(maxTraceDepth, 1u) - 1) * cssCHOrMSPlusCCTree
111             + std::min(maxTraceDepth, 1u) * std::max(cssCHOrMSPlusCCTree, cssIS + cssAH);
112     // clang-format on
113
114     return OPTIX_SUCCESS;
115 }
116
117 inline OptixResult optixUtilComputeStackSizesDCSplit(const OptixStackSizes* stackSizes,
118   unsigned int      dssDCFromTraversal,
119   unsigned int      dssDCFromState,
120   unsigned int      maxTraceDepth,
121   unsigned int      maxCCDepth,
122   unsigned int      maxDCDepthFromTraversal,
123   unsigned int      maxDCDepthFromState,
124   unsigned int*      directCallableStackSizeFromTraversal,
125   unsigned int*      directCallableStackSizeFromState,
126   unsigned int*      continuationStackSize)
127 {
128     if(!stackSizes)
129         return OPTIX_ERROR_INVALID_VALUE;
130
131     const unsigned int cssRG = stackSizes->cssRG;
132     const unsigned int cssMS = stackSizes->cssMS;
133     const unsigned int cssCH = stackSizes->cssCH;
134     const unsigned int cssAH = stackSizes->cssAH;
135     const unsigned int cssIS = stackSizes->cssIS;
136     const unsigned int cssCC = stackSizes->cssCC;

```

```

173 // use dssDCFromTraversal and dssDCFromState instead of stackSizes->dssDC
174
175 if(directCallableStackSizeFromTraversal)
176     *directCallableStackSizeFromTraversal = maxDCDepthFromTraversal * dssDCFromTraversal;
177 if(directCallableStackSizeFromState)
178     *directCallableStackSizeFromState = maxDCDepthFromState * dssDCFromState;
179
180 // upper bound on continuation stack used by call trees of continuation callables
181 unsigned int cssCCTree = maxCCDepth * cssCC;
182
183 // upper bound on continuation stack used by CH or MS programs including the call tree of
184 // continuation callables
185 unsigned int cssCHorMSPlusCCTree = std::max(cssCH, cssMS) + cssCCTree;
186
187 // clang-format off
188 if(continuationStackSize)
189     *continuationStackSize
190     = cssRG + cssCCTree
191     + (std::max(maxTraceDepth, 1u) - 1) * cssCHorMSPlusCCTree
192     + std::min(maxTraceDepth, 1u) * std::max(cssCHorMSPlusCCTree, cssIS + cssAH);
193 // clang-format on
194
195 return OPTIX_SUCCESS;
196 }
197
214 inline OptixResult optixUtilComputeStackSizesCssCCTree(const OptixStackSizes* stackSizes,
215   unsigned int      cssCCTree,
216   unsigned int      maxTraceDepth,
217   unsigned int      maxDCDepth,
218   unsigned int*
219   directCallableStackSizeFromTraversal,
220   unsigned int*      directCallableStackSizeFromState,
221   unsigned int*      continuationStackSize)
222 {
223     if(!stackSizes)
224         return OPTIX_ERROR_INVALID_VALUE;
225
226     const unsigned int cssRG = stackSizes->cssRG;
227     const unsigned int cssMS = stackSizes->cssMS;
228     const unsigned int cssCH = stackSizes->cssCH;
229     const unsigned int cssAH = stackSizes->cssAH;
230     const unsigned int cssIS = stackSizes->cssIS;
231     // use cssCCTree instead of stackSizes->cssCC and maxCCDepth
232     const unsigned int dssDC = stackSizes->dssDC;
233
234     if(directCallableStackSizeFromTraversal)
235         *directCallableStackSizeFromTraversal = maxDCDepth * dssDC;
236     if(directCallableStackSizeFromState)
237         *directCallableStackSizeFromState = maxDCDepth * dssDC;
238
239     // upper bound on continuation stack used by CH or MS programs including the call tree of
240     // continuation callables
241     unsigned int cssCHorMSPlusCCTree = std::max(cssCH, cssMS) + cssCCTree;
242
243     // clang-format off
244     if(continuationStackSize)
245         *continuationStackSize
246         = cssRG + cssCCTree
247         + (std::max(maxTraceDepth, 1u) - 1) * cssCHorMSPlusCCTree
248         + std::min(maxTraceDepth, 1u) * std::max(cssCHorMSPlusCCTree, cssIS + cssAH);
249     // clang-format on
250
251     return OPTIX_SUCCESS;
252 }
253
268 inline OptixResult optixUtilComputeStackSizesSimplePathTracer(OptixProgramGroup      programGroupRG,
269   OptixProgramGroup      programGroupMS1,

```

```

270                                     const OptixProgramGroup* programGroupCH1,
271                                     unsigned int                programGroupCH1Count,
272                                     OptixProgramGroup           programGroupMS2,
273                                     const OptixProgramGroup* programGroupCH2,
274                                     unsigned int                programGroupCH2Count,
275                                     unsigned int*
directCallableStackSizeFromTraversal,
276                                     unsigned int* directCallableStackSizeFromState,
277                                     unsigned int* continuationStackSize,
278                                     OptixPipeline pipeline)
279 {
280     if(!programGroupCH1 && (programGroupCH1Count > 0))
281         return OPTIX_ERROR_INVALID_VALUE;
282     if(!programGroupCH2 && (programGroupCH2Count > 0))
283         return OPTIX_ERROR_INVALID_VALUE;
284
285     OptixResult result;
286
287     OptixStackSizes stackSizesRG = {};
288     result                = optixProgramGroupGetStackSize(programGroupRG, &stackSizesRG, pipeline);
289     if(result != OPTIX_SUCCESS)
290         return result;
291
292     OptixStackSizes stackSizesMS1 = {};
293     result                = optixProgramGroupGetStackSize(programGroupMS1, &stackSizesMS1,
pipeline);
294     if(result != OPTIX_SUCCESS)
295         return result;
296
297     OptixStackSizes stackSizesCH1 = {};
298     for(unsigned int i = 0; i < programGroupCH1Count; ++i)
299     {
300         result = optixUtilAccumulateStackSizes(programGroupCH1[i], &stackSizesCH1, pipeline);
301         if(result != OPTIX_SUCCESS)
302             return result;
303     }
304
305     OptixStackSizes stackSizesMS2 = {};
306     result                = optixProgramGroupGetStackSize(programGroupMS2, &stackSizesMS2,
pipeline);
307     if(result != OPTIX_SUCCESS)
308         return result;
309
310     OptixStackSizes stackSizesCH2 = {};
311     memset(&stackSizesCH2, 0, sizeof(OptixStackSizes));
312     for(unsigned int i = 0; i < programGroupCH2Count; ++i)
313     {
314         result = optixUtilAccumulateStackSizes(programGroupCH2[i], &stackSizesCH2, pipeline);
315         if(result != OPTIX_SUCCESS)
316             return result;
317     }
318
319     const unsigned int cssRG  = stackSizesRG.cssRG;
320     const unsigned int cssMS1 = stackSizesMS1.cssMS;
321     const unsigned int cssCH1 = stackSizesCH1.cssCH;
322     const unsigned int cssMS2 = stackSizesMS2.cssMS;
323     const unsigned int cssCH2 = stackSizesCH2.cssCH;
324     // no AH, IS, CC, or DC programs
325
326     if(directCallableStackSizeFromTraversal)
327         *directCallableStackSizeFromTraversal = 0;
328     if(directCallableStackSizeFromState)
329         *directCallableStackSizeFromState = 0;
330
331     if(continuationStackSize)
332         *continuationStackSize = cssRG + std::max(cssMS1, cssCH1 + std::max(cssMS2, cssCH2));
333

```

```

334     return OPTIX_SUCCESS;
335 }
336 // end group optix_utilities
337
338
339 #ifdef __cplusplus
340 }
341 #endif
342
343 #endif // OPTIX_OPTIX_STACK_SIZE_H

```

## 8.23 optix\_stubs.h File Reference

### Macros

- `#define WIN32_LEAN_AND_MEAN 1`

### Functions

- `static void * optixLoadWindowsDllFromName (const char *optixDllName)`
- `static void * optixLoadWindowsDll ()`
- `OptixResult optixInitWithHandle (void **handlePtr)`
- `OptixResult optixInit (void)`
- `OptixResult optixUninitWithHandle (void *handle)`

### Variables

- `OptixFunctionTable g_optixFunctionTable`

#### 8.23.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

#### 8.23.2 Macro Definition Documentation

##### 8.23.2.1 WIN32\_LEAN\_AND\_MEAN

```
#define WIN32_LEAN_AND_MEAN 1
```

#### 8.23.3 Function Documentation

##### 8.23.3.1 optixLoadWindowsDll()

```
static void * optixLoadWindowsDll ( ) [static]
```

##### 8.23.3.2 optixLoadWindowsDllFromName()

```
static void * optixLoadWindowsDllFromName (
    const char * optixDllName ) [static]
```

## 8.24 optix\_stubs.h

[Go to the documentation of this file.](#)

```

1  /*
2  * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
3  *
4  * Redistribution and use in source and binary forms, with or without
5  * modification, are permitted provided that the following conditions
6  * are met:
7  * * Redistributions of source code must retain the above copyright
8  *   notice, this list of conditions and the following disclaimer.
9  * * Redistributions in binary form must reproduce the above copyright
10 *   notice, this list of conditions and the following disclaimer in the
11 *   documentation and/or other materials provided with the distribution.
12 * * Neither the name of NVIDIA CORPORATION nor the names of its
13 *   contributors may be used to endorse or promote products derived
14 *   from this software without specific prior written permission.
15 *
16 * THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS "AS IS" AND ANY
17 * EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE
18 * IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR
19 * PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
20 * CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
21 * EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
22 * PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
23 * PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY
24 * OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
25 * (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE
26 * OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
27 */
28
29
30
31
32
33 #ifndef OPTIX_OPTIX_STUBS_H
34 #define OPTIX_OPTIX_STUBS_H
35
36 #include "optix_function_table.h"
37
38 #ifdef _WIN32
39 #ifndef WIN32_LEAN_AND_MEAN
40 #define WIN32_LEAN_AND_MEAN 1
41 #endif
42 #include <windows.h>
43 // The cfgmgr32 header is necessary for interrogating driver information in the registry.
44 // For convenience the library is also linked in automatically using the #pragma command.
45 #include <cfgmgr32.h>
46 #pragma comment(lib, "Cfgmgr32.lib")
47 #include <string.h>
48 #else
49 #include <dlfcn.h>
50 #endif
51
52 #ifdef __cplusplus
53 extern "C" {
54 #endif
55
56 // The function table needs to be defined in exactly one translation unit. This can be
57 // achieved by including optix_function_table_definition.h in that translation unit.
58 extern OptixFunctionTable g_optixFunctionTable;
59
60 #ifdef _WIN32
61 #if defined(_MSC_VER)
62 // Visual Studio produces warnings suggesting strcpy and friends being replaced with _s
63 // variants. All the string lengths and allocation sizes have been calculated and should
64 // be safe, so we are disabling this warning to increase compatibility.
65 #pragma warning(push)
66 #pragma warning(disable : 4996)
67 #endif
68 static void* optixLoadWindowsDllFromName(const char* optixDllName)
69 {
70     void* handle = NULL;

```

```

71
72 // Try the bare dll name first. This picks it up in the local path, followed by
73 // standard Windows paths.
74 handle = LoadLibraryA((LPSTR)optixDllName);
75 if(handle)
76     return handle;
77 // If we don't find it in the default dll search path, try the system paths
78
79 // Get the size of the path first, then allocate
80 unsigned int size = GetSystemDirectoryA(NULL, 0);
81 if(size == 0)
82 {
83     // Couldn't get the system path size, so bail
84     return NULL;
85 }
86 size_t pathSize = size + 1 + strlen(optixDllName);
87 char* systemPath = (char*)malloc(pathSize);
88 if(systemPath == NULL)
89     return NULL;
90 if(GetSystemDirectoryA(systemPath, size) != size - 1)
91 {
92     // Something went wrong
93     free(systemPath);
94     return NULL;
95 }
96 strcat(systemPath, "\\");
97 strcat(systemPath, optixDllName);
98 handle = LoadLibraryA(systemPath);
99 free(systemPath);
100 if(handle)
101     return handle;
102
103 // If we didn't find it, go looking in the register store. Since nvoptix.dll doesn't
104 // have its own registry entry, we are going to look for the opengl driver which lives
105 // next to nvoptix.dll. 0 (null) will be returned if any errors occurred.
106
107 static const char* deviceInstanceIdentifiersGUID = "{4d36e968-e325-11ce-bfc1-08002be10318}";
108 const ULONG flags = CM_GETIDLIST_FILTER_CLASS |
CM_GETIDLIST_FILTER_PRESENT;
109 ULONG deviceListSize = 0;
110 if(CM_Get_Device_ID_List_SizeA(&deviceListSize, deviceInstanceIdentifiersGUID, flags) != CR_SUCCESS)
111 {
112     return NULL;
113 }
114 char* deviceNames = (char*)malloc(deviceListSize);
115 if(deviceNames == NULL)
116     return NULL;
117 if(CM_Get_Device_ID_ListA(deviceInstanceIdentifiersGUID, deviceNames, deviceListSize, flags))
118 {
119     free(deviceNames);
120     return NULL;
121 }
122 DEVINST devID = 0;
123 char* dllPath = NULL;
124
125 // Continue to the next device if errors are encountered.
126 for(char* deviceName = deviceNames; *deviceName; deviceName += strlen(deviceName) + 1)
127 {
128     if(CM_Locate_DevNodeA(&devID, deviceName, CM_LOCATE_DEVNODE_NORMAL) != CR_SUCCESS)
129     {
130         continue;
131     }
132     HKEY regKey = 0;
133     if(CM_Open_DevNode_Key(devID, KEY_QUERY_VALUE, 0, RegDisposition_OpenExisting, &regKey,
CM_REGISTRY_SOFTWARE) != CR_SUCCESS)
134     {
135         continue;

```



```

136     }
137     const char* valueName = "OpenGLDriverName";
138     DWORD      valueSize = 0;
139     LSTATUS     ret      = RegQueryValueExA(regKey, valueName, NULL, NULL, NULL, &valueSize);
140     if(ret != ERROR_SUCCESS)
141     {
142         RegCloseKey(regKey);
143         continue;
144     }
145     char* regValue = (char*)malloc(valueSize);
146     if(regValue == NULL)
147     {
148         RegCloseKey(regKey);
149         continue;
150     }
151     ret      = RegQueryValueExA(regKey, valueName, NULL, NULL, (LPBYTE)regValue, &valueSize);
152     if(ret != ERROR_SUCCESS)
153     {
154         free(regValue);
155         RegCloseKey(regKey);
156         continue;
157     }
158     // Strip the opengl driver dll name from the string then create a new string with
159     // the path and the nvoptix.dll name
160     for(int i = (int) valueSize - 1; i >= 0 && regValue[i] != '\\'; --i)
161         regValue[i] = '\\0';
162     size_t newPathSize = strlen(regValue) + strlen(optixDllName) + 1;
163     dllPath             = (char*)malloc(newPathSize);
164     if(dllPath == NULL)
165     {
166         free(regValue);
167         RegCloseKey(regKey);
168         continue;
169     }
170     strcpy(dllPath, regValue);
171     strcat(dllPath, optixDllName);
172     free(regValue);
173     RegCloseKey(regKey);
174     handle = LoadLibraryA((LPCSTR)dllPath);
175     free(dllPath);
176     if(handle)
177         break;
178     }
179     free(deviceNames);
180     return handle;
181 }
182 #if defined(_MSC_VER)
183 #    pragma warning(pop)
184 #endif
185
186 static void* optixLoadWindowsDll( )
187 {
188     return optixLoadWindowsDllFromName("nvoptix.dll");
189 }
190 #endif
191
192
193
194
195 inline OptixResult optixInitWithHandle(void** handlePtr)
196 {
197     // Make sure these functions get initialized to zero in case the DLL and function
198     // table can't be loaded
199     g_optixFunctionTable.optixGetErrorName      = 0;
200     g_optixFunctionTable.optixGetErrorString    = 0;
201
202     if(!handlePtr)
203         return OPTIX_ERROR_INVALID_VALUE;
204 }

```

```

214 #ifdef _WIN32
215     *handlePtr = optixLoadWindowsDll();
216     if(!*handlePtr)
217         return OPTIX_ERROR_LIBRARY_NOT_FOUND;
218
219     void* symbol = GetProcAddress((HMODULE)*handlePtr, "optixQueryFunctionTable");
220     if(!symbol)
221         return OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND;
222 #else
223     *handlePtr = dlopen("libnvoptix.so.1", RTLD_NOW);
224     if(!*handlePtr)
225         return OPTIX_ERROR_LIBRARY_NOT_FOUND;
226
227     void* symbol = dlsym(*handlePtr, "optixQueryFunctionTable");
228     if(!symbol)
229         return OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND;
230 #endif
231
232     OptixQueryFunctionTable_t* optixQueryFunctionTable = (OptixQueryFunctionTable_t*)symbol;
233
234     return optixQueryFunctionTable(OPTIX_ABI_VERSION, 0, 0, 0, &g_optixFunctionTable,
235 sizeof(g_optixFunctionTable));
236 }
237
238 inline OptixResult optixInit(void)
239 {
240     void* handle;
241     return optixInitWithHandle(&handle);
242 }
243
244 inline OptixResult optixUninitWithHandle(void* handle)
245 {
246     if(!handle)
247         return OPTIX_ERROR_INVALID_VALUE;
248 #ifdef _WIN32
249     if(!FreeLibrary((HMODULE)handle))
250         return OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE;
251 #else
252     if(dlclose(handle))
253         return OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE;
254 #endif
255
256     OptixFunctionTable empty = { 0 };
257     g_optixFunctionTable = empty;
258     return OPTIX_SUCCESS;
259 }
260
261 // end group optix_utilities
262
263 #ifndef OPTIX_DOXYGEN_SHOULD_SKIP_THIS
264 // Stub functions that forward calls to the corresponding function pointer in the function table.
265
266 inline const char* optixGetErrorName(OptixResult result)
267 {
268     if(g_optixFunctionTable.optixGetErrorName)
269         return g_optixFunctionTable.optixGetErrorName(result);
270
271     // If the DLL and symbol table couldn't be loaded, provide a set of error strings
272     // suitable for processing errors related to the DLL loading.
273     switch(result)
274     {
275     case OPTIX_SUCCESS:
276         return "OPTIX_SUCCESS";
277     case OPTIX_ERROR_INVALID_VALUE:
278         return "OPTIX_ERROR_INVALID_VALUE";
279     case OPTIX_ERROR_UNSUPPORTED_ABI_VERSION:
280         return "OPTIX_ERROR_UNSUPPORTED_ABI_VERSION";
281     }

```

```

289         case OPTIX_ERROR_FUNCTION_TABLE_SIZE_MISMATCH:
290             return "OPTIX_ERROR_FUNCTION_TABLE_SIZE_MISMATCH";
291         case OPTIX_ERROR_INVALID_ENTRY_FUNCTION_OPTIONS:
292             return "OPTIX_ERROR_INVALID_ENTRY_FUNCTION_OPTIONS";
293         case OPTIX_ERROR_LIBRARY_NOT_FOUND:
294             return "OPTIX_ERROR_LIBRARY_NOT_FOUND";
295         case OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND:
296             return "OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND";
297         case OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE:
298             return "OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE";
299         default:
300             return "Unknown OptixResult code";
301     }
302 }
303
304 inline const char* optixGetErrorString(OptixResult result)
305 {
306     if(g_optixFunctionTable.optixGetErrorString)
307         return g_optixFunctionTable.optixGetErrorString(result);
308
309     // If the DLL and symbol table couldn't be loaded, provide a set of error strings
310     // suitable for processing errors related to the DLL loading.
311     switch(result)
312     {
313         case OPTIX_SUCCESS:
314             return "Success";
315         case OPTIX_ERROR_INVALID_VALUE:
316             return "Invalid value";
317         case OPTIX_ERROR_UNSUPPORTED_ABI_VERSION:
318             return "Unsupported ABI version";
319         case OPTIX_ERROR_FUNCTION_TABLE_SIZE_MISMATCH:
320             return "Function table size mismatch";
321         case OPTIX_ERROR_INVALID_ENTRY_FUNCTION_OPTIONS:
322             return "Invalid options to entry function";
323         case OPTIX_ERROR_LIBRARY_NOT_FOUND:
324             return "Library not found";
325         case OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND:
326             return "Entry symbol not found";
327         case OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE:
328             return "Library could not be unloaded";
329         default:
330             return "Unknown OptixResult code";
331     }
332 }
333
334 inline OptixResult optixDeviceContextCreate(CUcontext fromContext, const OptixDeviceContextOptions*
options, OptixDeviceContext* context)
335 {
336     return g_optixFunctionTable.optixDeviceContextCreate(fromContext, options, context);
337 }
338
339 inline OptixResult optixDeviceContextDestroy(OptixDeviceContext context)
340 {
341     return g_optixFunctionTable.optixDeviceContextDestroy(context);
342 }
343
344 inline OptixResult optixDeviceContextGetProperty(OptixDeviceContext context, OptixDeviceProperty
property, void* value, size_t sizeInBytes)
345 {
346     return g_optixFunctionTable.optixDeviceContextGetProperty(context, property, value, sizeInBytes);
347 }
348
349 inline OptixResult optixDeviceContextSetLogCallback(OptixDeviceContext context,
350   OptixLogCallback callbackFunction,
351   void* callbackData,
352   unsigned int callbackLevel)
353 {

```

```

354     return g_optixFunctionTable.optixDeviceContextSetLogCallback(context, callbackFunction,
355 callbackData, callbackLevel);
356 }
357 inline OptixResult optixDeviceContextSetCacheEnabled(OptixDeviceContext context, int enabled)
358 {
359     return g_optixFunctionTable.optixDeviceContextSetCacheEnabled(context, enabled);
360 }
361
362 inline OptixResult optixDeviceContextSetCacheLocation(OptixDeviceContext context, const char* location)
363 {
364     return g_optixFunctionTable.optixDeviceContextSetCacheLocation(context, location);
365 }
366
367 inline OptixResult optixDeviceContextSetCacheDatabaseSizes(OptixDeviceContext context, size_t
lowWaterMark, size_t highWaterMark)
368 {
369     return g_optixFunctionTable.optixDeviceContextSetCacheDatabaseSizes(context, lowWaterMark,
highWaterMark);
370 }
371
372 inline OptixResult optixDeviceContextGetCacheEnabled(OptixDeviceContext context, int* enabled)
373 {
374     return g_optixFunctionTable.optixDeviceContextGetCacheEnabled(context, enabled);
375 }
376
377 inline OptixResult optixDeviceContextGetCacheLocation(OptixDeviceContext context, char* location, size_t
locationSize)
378 {
379     return g_optixFunctionTable.optixDeviceContextGetCacheLocation(context, location, locationSize);
380 }
381
382 inline OptixResult optixDeviceContextGetCacheDatabaseSizes(OptixDeviceContext context, size_t*
lowWaterMark, size_t* highWaterMark)
383 {
384     return g_optixFunctionTable.optixDeviceContextGetCacheDatabaseSizes(context, lowWaterMark,
highWaterMark);
385 }
386
387 inline OptixResult optixModuleCreate(OptixDeviceContext context,
388                                     const OptixModuleCompileOptions* moduleCompileOptions,
389                                     const OptixPipelineCompileOptions* pipelineCompileOptions,
390                                     const char* input,
391                                     size_t inputSize,
392                                     char* logString,
393                                     size_t* logStringSize,
394                                     OptixModule* module)
395 {
396     return g_optixFunctionTable.optixModuleCreate(context, moduleCompileOptions, pipelineCompileOptions,
input, inputSize,
397 logString, logStringSize, module);
398 }
399
400 inline OptixResult optixModuleCreateWithTasks(OptixDeviceContext context,
401   const OptixModuleCompileOptions* moduleCompileOptions,
402   const OptixPipelineCompileOptions* pipelineCompileOptions,
403   const char* input,
404   size_t inputSize,
405   char* logString,
406   size_t* logStringSize,
407   OptixModule* module,
408   OptixTask* firstTask)
409 {
410     return g_optixFunctionTable.optixModuleCreateWithTasks(context, moduleCompileOptions,
pipelineCompileOptions, input,
411 inputSize, logString, logStringSize, module,
firstTask);

```

```

412 }
413
414 inline OptixResult optixModuleGetCompilationState(OptixModule module, OptixModuleCompileState* state)
415 {
416     return g_optixFunctionTable.optixModuleGetCompilationState(module, state);
417 }
418
419 inline OptixResult optixModuleDestroy(OptixModule module)
420 {
421     return g_optixFunctionTable.optixModuleDestroy(module);
422 }
423
424 inline OptixResult optixBuiltinISModuleGet(OptixDeviceContext context,
425   const OptixModuleCompileOptions* moduleCompileOptions,
426   const OptixPipelineCompileOptions* pipelineCompileOptions,
427   const OptixBuiltinISOptions* builtinISOptions,
428   OptixModule* builtinModule)
429 {
430     return g_optixFunctionTable.optixBuiltinISModuleGet(context, moduleCompileOptions,
431 pipelineCompileOptions,
432   builtinISOptions, builtinModule);
433 }
434
435 inline OptixResult optixTaskExecute(OptixTask task, OptixTask* additionalTasks, unsigned int
436 maxNumAdditionalTasks, unsigned int* numAdditionalTasksCreated)
437 {
438     return g_optixFunctionTable.optixTaskExecute(task, additionalTasks, maxNumAdditionalTasks,
439 numAdditionalTasksCreated);
440 }
441
442 inline OptixResult optixProgramGroupCreate(OptixDeviceContext context,
443   const OptixProgramGroupDesc* programDescriptions,
444   unsigned int numProgramGroups,
445   const OptixProgramGroupOptions* options,
446   char* logString,
447   size_t* logStringSize,
448   OptixProgramGroup* programGroups)
449 {
450     return g_optixFunctionTable.optixProgramGroupCreate(context, programDescriptions, numProgramGroups,
451 options,
452   logString, logStringSize, programGroups);
453 }
454
455 inline OptixResult optixProgramGroupDestroy(OptixProgramGroup programGroup)
456 {
457     return g_optixFunctionTable.optixProgramGroupDestroy(programGroup);
458 }
459
460 inline OptixResult optixProgramGroupGetStackSize(OptixProgramGroup programGroup, OptixStackSizes*
461 stackSizes, OptixPipeline pipeline)
462 {
463     return g_optixFunctionTable.optixProgramGroupGetStackSize(programGroup, stackSizes, pipeline);
464 }
465
466 inline OptixResult optixPipelineCreate(OptixDeviceContext context,
467   const OptixPipelineCompileOptions* pipelineCompileOptions,
468   const OptixPipelineLinkOptions* pipelineLinkOptions,
469   const OptixProgramGroup* programGroups,
470   unsigned int numProgramGroups,
471   char* logString,
472   size_t* logStringSize,
473   OptixPipeline* pipeline)
474 {
475     return g_optixFunctionTable.optixPipelineCreate(context, pipelineCompileOptions,
476 pipelineLinkOptions, programGroups,
477   numProgramGroups, logString, logStringSize, pipeline);
478 }

```

```

473
474 inline OptixResult optixPipelineDestroy(OptixPipeline pipeline)
475 {
476     return g_optixFunctionTable.optixPipelineDestroy(pipeline);
477 }
478
479 inline OptixResult optixPipelineSetStackSize(OptixPipeline pipeline,
480   unsigned int directCallableStackSizeFromTraversal,
481   unsigned int directCallableStackSizeFromState,
482   unsigned int continuationStackSize,
483   unsigned int maxTraversableGraphDepth)
484 {
485     return g_optixFunctionTable.optixPipelineSetStackSize(pipeline,
486 directCallableStackSizeFromTraversal, directCallableStackSizeFromState,
487   continuationStackSize, maxTraversableGraphDepth);
488 }
489
490 inline OptixResult optixAccelComputeMemoryUsage(OptixDeviceContext context,
491   const OptixAccelBuildOptions* accelOptions,
492   const OptixBuildInput* buildInputs,
493   unsigned int numBuildInputs,
494   OptixAccelBufferSizes* bufferSizes)
495 {
496     return g_optixFunctionTable.optixAccelComputeMemoryUsage(context, accelOptions, buildInputs,
497 numBuildInputs, bufferSizes);
498 }
499
500 inline OptixResult optixAccelBuild(OptixDeviceContext context,
501                                   CUstream stream,
502                                   const OptixAccelBuildOptions* accelOptions,
503                                   const OptixBuildInput* buildInputs,
504                                   unsigned int numBuildInputs,
505                                   CUdeviceptr tempBuffer,
506                                   size_t tempBufferSizeInBytes,
507                                   CUdeviceptr outputBuffer,
508                                   size_t outputBufferSizeInBytes,
509                                   OptixTraversableHandle* outputHandle,
510                                   const OptixAccelEmitDesc* emittedProperties,
511                                   unsigned int numEmittedProperties)
512 {
513     return g_optixFunctionTable.optixAccelBuild(context, stream, accelOptions, buildInputs,
514 numBuildInputs, tempBuffer,
515 tempBufferSizeInBytes, outputBuffer, outputBufferSizeInBytes,
516 outputHandle, emittedProperties, numEmittedProperties);
517 }
518
519 inline OptixResult optixAccelGetRelocationInfo(OptixDeviceContext context, OptixTraversableHandle
520 handle, OptixRelocationInfo* info)
521 {
522     return g_optixFunctionTable.optixAccelGetRelocationInfo(context, handle, info);
523 }
524
525 inline OptixResult optixCheckRelocationCompatibility(OptixDeviceContext context, const
526 OptixRelocationInfo* info, int* compatible)
527 {
528     return g_optixFunctionTable.optixCheckRelocationCompatibility(context, info, compatible);
529 }
530
531 inline OptixResult optixAccelRelocate(OptixDeviceContext context,
532                                       CUstream stream,
533                                       const OptixRelocationInfo* info,
534                                       const OptixRelocateInput* relocateInputs,
535                                       size_t numRelocateInputs,
536                                       CUdeviceptr targetAccel,
537                                       size_t targetAccelSizeInBytes,

```

```

535                                     OptixTraversableHandle*      targetHandle)
536 {
537     return g_optixFunctionTable.optixAccelRelocate(context, stream, info, relocateInputs,
538 numRelocateInputs,
539                                     targetAccel, targetAccelSizeInBytes, targetHandle);
540 }
541 inline OptixResult optixAccelCompact(OptixDeviceContext      context,
542                                     CUstream                stream,
543                                     OptixTraversableHandle   inputHandle,
544                                     CUdeviceptr              outputBuffer,
545                                     size_t                   outputBufferSizeInBytes,
546                                     OptixTraversableHandle*   outputHandle)
547 {
548     return g_optixFunctionTable.optixAccelCompact(context, stream, inputHandle, outputBuffer,
549 outputBufferSizeInBytes, outputHandle);
550 }
551 inline OptixResult optixAccelEmitProperty(OptixDeviceContext      context,
552                                     CUstream                stream,
553                                     OptixTraversableHandle   handle,
554                                     const OptixAccelEmitDesc* emittedProperty)
555 {
556     return g_optixFunctionTable.optixAccelEmitProperty(context, stream, handle, emittedProperty);
557 }
558
559 inline OptixResult optixConvertPointerToTraversableHandle(OptixDeviceContext      onDevice,
560                                     CUdeviceptr                pointer,
561                                     OptixTraversableType         traversableType,
562                                     OptixTraversableHandle*      traversableHandle)
563 {
564     return g_optixFunctionTable.optixConvertPointerToTraversableHandle(onDevice, pointer,
565 traversableType, traversableHandle);
566 }
567 inline OptixResult optixOpacityMicromapArrayComputeMemoryUsage(OptixDeviceContext
568 context,
569                                     const OptixOpacityMicromapArrayBuildInput*
570 buildInput,
571                                     OptixMicromapBufferSizes*
572 bufferSizes)
573 {
574     return g_optixFunctionTable.optixOpacityMicromapArrayComputeMemoryUsage(context, buildInput,
575 bufferSizes);
576 }
577
578 inline OptixResult optixOpacityMicromapArrayBuild(OptixDeviceContext      context,
579                                     CUstream                stream,
580                                     const OptixOpacityMicromapArrayBuildInput* buildInput,
581                                     const OptixMicromapBuffers*           buffers)
582 {
583     return g_optixFunctionTable.optixOpacityMicromapArrayBuild(context, stream, buildInput, buffers);
584 }
585
586 inline OptixResult optixOpacityMicromapArrayGetRelocationInfo(OptixDeviceContext      context,
587                                     CUdeviceptr                opacityMicromapArray,
588                                     OptixRelocationInfo*        info)
589 {
590     return g_optixFunctionTable.optixOpacityMicromapArrayGetRelocationInfo(context,
591 opacityMicromapArray, info);
592 }
593
594 inline OptixResult optixOpacityMicromapArrayRelocate(OptixDeviceContext      context,
595                                     CUstream                stream,
596                                     const OptixRelocationInfo* info,
597                                     CUdeviceptr              targetOpacityMicromapArray,
598                                     size_t

```



```

targetOpacityMicromapArraySizeInBytes)
594 {
595     return g_optixFunctionTable.optixOpacityMicromapArrayRelocate(context, stream, info,
targetOpacityMicromapArray, targetOpacityMicromapArraySizeInBytes);
596 }
597
598 inline OptixResult optixDisplacementMicromapArrayComputeMemoryUsage(OptixDeviceContext context,
599  const
OptixDisplacementMicromapArrayBuildInput* buildInput,
  OptixMicromapBufferSizes* bufferSizes)
600 {
601     return g_optixFunctionTable.optixDisplacementMicromapArrayComputeMemoryUsage(context, buildInput,
bufferSizes);
602 }
603 }
604
605 inline OptixResult optixDisplacementMicromapArrayBuild(OptixDeviceContext
context,
  CUstream stream,
  const OptixDisplacementMicromapArrayBuildInput*
buildInput,
  const OptixMicromapBuffers* buffers)
606 {
607     return g_optixFunctionTable.optixDisplacementMicromapArrayBuild(context, stream, buildInput,
buffers);
608 }
609 }
610
611 inline OptixResult optixSbtRecordPackHeader(OptixProgramGroup programGroup, void*
sbtRecordHeaderHostPointer)
612 {
613     return g_optixFunctionTable.optixSbtRecordPackHeader(programGroup, sbtRecordHeaderHostPointer);
614 }
615 }
616
617 inline OptixResult optixLaunch(OptixPipeline pipeline,
  CUstream stream,
  CUdeviceptr pipelineParams,
  size_t pipelineParamsSize,
  const OptixShaderBindingTable* sbt,
  unsigned int width,
  unsigned int height,
  unsigned int depth)
618 {
619     return g_optixFunctionTable.optixLaunch(pipeline, stream, pipelineParams, pipelineParamsSize, sbt,
width, height, depth);
620 }
621 }
622
623 inline OptixResult optixDenoiserCreate(OptixDeviceContext context, OptixDenoiserModelKind modelKind,
const OptixDenoiserOptions* options, OptixDenoiser* returnHandle)
624 {
625     return g_optixFunctionTable.optixDenoiserCreate(context, modelKind, options, returnHandle);
626 }
627 }
628
629 inline OptixResult optixDenoiserCreateWithUserModel(OptixDeviceContext context, const void* data, size_t
dataSizeInBytes, OptixDenoiser* returnHandle)
630 {
631     return g_optixFunctionTable.optixDenoiserCreateWithUserModel(context, data, dataSizeInBytes,
returnHandle);
632 }
633 }
634
635 inline OptixResult optixDenoiserDestroy(OptixDenoiser handle)
636 {
637     return g_optixFunctionTable.optixDenoiserDestroy(handle);
638 }
639 }
640
641 inline OptixResult optixDenoiserComputeMemoryResources(const OptixDenoiser handle,
  unsigned int maximumInputWidth,
  unsigned int maximumInputHeight,
  OptixDenoiserSizes* returnSizes)
642 {
643     return g_optixFunctionTable.optixDenoiserComputeMemoryResources(handle, maximumInputWidth,
maximumInputHeight, returnSizes);
644 }
645 }
646
647
648

```



```

649 {
650     return g_optixFunctionTable.optixDenoiserComputeMemoryResources(handle, maximumInputWidth,
651         maximumInputHeight, returnSizes);
652 }
653 inline OptixResult optixDenoiserSetup(OptixDenoiser denoiser,
654     CUstream stream,
655     unsigned int inputWidth,
656     unsigned int inputHeight,
657     CUdeviceptr denoiserState,
658     size_t denoiserStateSizeInBytes,
659     CUdeviceptr scratch,
660     size_t scratchSizeInBytes)
661 {
662     return g_optixFunctionTable.optixDenoiserSetup(denoiser, stream, inputWidth, inputHeight,
663         denoiserState,
664         denoiserStateSizeInBytes, scratch, scratchSizeInBytes);
665 }
666 inline OptixResult optixDenoiserInvoke(OptixDenoiser handle,
667     CUstream stream,
668     const OptixDenoiserParams* params,
669     CUdeviceptr denoiserData,
670     size_t denoiserDataSize,
671     const OptixDenoiserGuideLayer* guideLayer,
672     const OptixDenoiserLayer* layers,
673     unsigned int numLayers,
674     unsigned int inputOffsetX,
675     unsigned int inputOffsetY,
676     CUdeviceptr scratch,
677     size_t scratchSizeInBytes)
678 {
679     return g_optixFunctionTable.optixDenoiserInvoke(handle, stream, params, denoiserData,
680         denoiserDataSize,
681         guideLayer, layers, numLayers,
682         inputOffsetX, inputOffsetY, scratch, scratchSizeInBytes);
683 }
684 inline OptixResult optixDenoiserComputeIntensity(OptixDenoiser handle,
685     CUstream stream,
686     const OptixImage2D* inputImage,
687     CUdeviceptr outputIntensity,
688     CUdeviceptr scratch,
689     size_t scratchSizeInBytes)
690 {
691     return g_optixFunctionTable.optixDenoiserComputeIntensity(handle, stream, inputImage,
692         outputIntensity, scratch, scratchSizeInBytes);
693 }
694 inline OptixResult optixDenoiserComputeAverageColor(OptixDenoiser handle,
695     CUstream stream,
696     const OptixImage2D* inputImage,
697     CUdeviceptr outputAverageColor,
698     CUdeviceptr scratch,
699     size_t scratchSizeInBytes)
700 {
701     return g_optixFunctionTable.optixDenoiserComputeAverageColor(handle, stream, inputImage,
702         outputAverageColor, scratch, scratchSizeInBytes);
703 }
704 #endif // OPTIX_DOXYGEN_SHOULD_SKIP_THIS
705
706 #ifdef __cplusplus
707 }
708 #endif
709
710 #endif // OPTIX_OPTIX_STUBS_H

```

## 8.25 optix\_types.h File Reference

### Classes

- struct OptixDeviceContextOptions
- struct OptixOpacityMicromapUsageCount
- struct OptixBuildInputOpacityMicromap
- struct OptixRelocateInputOpacityMicromap
- struct OptixDisplacementMicromapDesc
- struct OptixDisplacementMicromapHistogramEntry
- struct OptixDisplacementMicromapArrayBuildInput
- struct OptixDisplacementMicromapUsageCount
- struct OptixBuildInputDisplacementMicromap
- struct OptixBuildInputTriangleArray
- struct OptixRelocateInputTriangleArray
- struct OptixBuildInputCurveArray
- struct OptixBuildInputSphereArray
- struct OptixAabb
- struct OptixBuildInputCustomPrimitiveArray
- struct OptixBuildInputInstanceArray
- struct OptixRelocateInputInstanceArray
- struct OptixBuildInput
- struct OptixRelocateInput
- struct OptixInstance
- struct OptixOpacityMicromapDesc
- struct OptixOpacityMicromapHistogramEntry
- struct OptixOpacityMicromapArrayBuildInput
- struct OptixMicromapBufferSizes
- struct OptixMicromapBuffers
- struct OptixMotionOptions
- struct OptixAccelBuildOptions
- struct OptixAccelBufferSizes
- struct OptixAccelEmitDesc
- struct OptixRelocationInfo
- struct OptixStaticTransform
- struct OptixMatrixMotionTransform
- struct OptixSRTData
- struct OptixSRTMotionTransform
- struct OptixImage2D
- struct OptixDenoiserOptions
- struct OptixDenoiserGuideLayer
- struct OptixDenoiserLayer
- struct OptixDenoiserParams
- struct OptixDenoiserSizes
- struct OptixModuleCompileBoundValueEntry
- struct OptixPayloadType
- struct OptixModuleCompileOptions
- struct OptixProgramGroupSingleModule
- struct OptixProgramGroupHitgroup
- struct OptixProgramGroupCallables
- struct OptixProgramGroupDesc

- struct `OptixProgramGroupOptions`
- struct `OptixPipelineCompileOptions`
- struct `OptixPipelineLinkOptions`
- struct `OptixShaderBindingTable`
- struct `OptixStackSizes`
- struct `OptixBuiltinISOOptions`

## Macros

- `#define OPTIX_SBT_RECORD_HEADER_SIZE ((size_t)32)`
- `#define OPTIX_SBT_RECORD_ALIGNMENT 16ull`
- `#define OPTIX_ACCEL_BUFFER_BYTE_ALIGNMENT 128ull`
- `#define OPTIX_INSTANCE_BYTE_ALIGNMENT 16ull`
- `#define OPTIX_AABB_BUFFER_BYTE_ALIGNMENT 8ull`
- `#define OPTIX_GEOMETRY_TRANSFORM_BYTE_ALIGNMENT 16ull`
- `#define OPTIX_TRANSFORM_BYTE_ALIGNMENT 64ull`
- `#define OPTIX_OPACITY_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT 8ull`
- `#define OPTIX_COMPILE_DEFAULT_MAX_REGISTER_COUNT 0`
- `#define OPTIX_COMPILE_DEFAULT_MAX_PAYLOAD_TYPE_COUNT 8`
- `#define OPTIX_COMPILE_DEFAULT_MAX_PAYLOAD_VALUE_COUNT 32`
- `#define OPTIX_OPACITY_MICROMAP_STATE_TRANSPARENT (0)`
- `#define OPTIX_OPACITY_MICROMAP_STATE_OPAQUE (1)`
- `#define OPTIX_OPACITY_MICROMAP_STATE_UNKNOWN_TRANSPARENT (2)`
- `#define OPTIX_OPACITY_MICROMAP_STATE_UNKNOWN_OPAQUE (3)`
- `#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_TRANSPARENT (-1)`
- `#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_OPAQUE (-2)`
- `#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_TRANSPARENT (-3)`
- `#define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_OPAQUE (-4)`
- `#define OPTIX_OPACITY_MICROMAP_ARRAY_BUFFER_BYTE_ALIGNMENT 128ull`
- `#define OPTIX_OPACITY_MICROMAP_MAX_SUBDIVISION_LEVEL 12`
- `#define OPTIX_DISPLACEMENT_MICROMAP_MAX_SUBDIVISION_LEVEL 5`
- `#define OPTIX_DISPLACEMENT_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT 8ull`
- `#define OPTIX_DISPLACEMENT_MICROMAP_ARRAY_BUFFER_BYTE_ALIGNMENT 128ull`

## Typedefs

- `typedef unsigned long long CUdeviceptr`
- `typedef struct OptixDeviceContext_t * OptixDeviceContext`
- `typedef struct OptixModule_t * OptixModule`
- `typedef struct OptixProgramGroup_t * OptixProgramGroup`
- `typedef struct OptixPipeline_t * OptixPipeline`
- `typedef struct OptixDenoiser_t * OptixDenoiser`
- `typedef struct OptixTask_t * OptixTask`
- `typedef unsigned long long OptixTraversableHandle`
- `typedef unsigned int OptixVisibilityMask`
- `typedef enum OptixResult OptixResult`
- `typedef enum OptixDeviceProperty OptixDeviceProperty`
- `typedef void(* OptixLogCallback) (unsigned int level, const char *tag, const char *message, void *cbdata)`

- typedef enum OptixDeviceContextValidationMode OptixDeviceContextValidationMode
- typedef struct OptixDeviceContextOptions OptixDeviceContextOptions
- typedef enum OptixDevicePropertyShaderExecutionReorderingFlags OptixDevicePropertyShaderExecutionReorderingFlags
- typedef enum OptixGeometryFlags OptixGeometryFlags
- typedef enum OptixHitKind OptixHitKind
- typedef enum OptixIndicesFormat OptixIndicesFormat
- typedef enum OptixVertexFormat OptixVertexFormat
- typedef enum OptixTransformFormat OptixTransformFormat
- typedef enum OptixDisplacementMicromapBiasAndScaleFormat OptixDisplacementMicromapBiasAndScaleFormat
- typedef enum OptixDisplacementMicromapDirectionFormat OptixDisplacementMicromapDirectionFormat
- typedef enum OptixOpacityMicromapFormat OptixOpacityMicromapFormat
- typedef enum OptixOpacityMicromapArrayIndexingMode OptixOpacityMicromapArrayIndexingMode
- typedef struct OptixOpacityMicromapUsageCount OptixOpacityMicromapUsageCount
- typedef struct OptixBuildInputOpacityMicromap OptixBuildInputOpacityMicromap
- typedef struct OptixRelocateInputOpacityMicromap OptixRelocateInputOpacityMicromap
- typedef enum OptixDisplacementMicromapFormat OptixDisplacementMicromapFormat
- typedef enum OptixDisplacementMicromapFlags OptixDisplacementMicromapFlags
- typedef enum OptixDisplacementMicromapTriangleFlags OptixDisplacementMicromapTriangleFlags
- typedef struct OptixDisplacementMicromapDesc OptixDisplacementMicromapDesc
- typedef struct OptixDisplacementMicromapHistogramEntry OptixDisplacementMicromapHistogramEntry
- typedef struct OptixDisplacementMicromapArrayBuildInput OptixDisplacementMicromapArrayBuildInput
- typedef struct OptixDisplacementMicromapUsageCount OptixDisplacementMicromapUsageCount
- typedef enum OptixDisplacementMicromapArrayIndexingMode OptixDisplacementMicromapArrayIndexingMode
- typedef struct OptixBuildInputDisplacementMicromap OptixBuildInputDisplacementMicromap
- typedef struct OptixBuildInputTriangleArray OptixBuildInputTriangleArray
- typedef struct OptixRelocateInputTriangleArray OptixRelocateInputTriangleArray
- typedef enum OptixPrimitiveType OptixPrimitiveType
- typedef enum OptixPrimitiveTypeFlags OptixPrimitiveTypeFlags
- typedef enum OptixCurveEndcapFlags OptixCurveEndcapFlags
- typedef struct OptixBuildInputCurveArray OptixBuildInputCurveArray
- typedef struct OptixBuildInputSphereArray OptixBuildInputSphereArray
- typedef struct OptixAabb OptixAabb
- typedef struct OptixBuildInputCustomPrimitiveArray OptixBuildInputCustomPrimitiveArray
- typedef struct OptixBuildInputInstanceArray OptixBuildInputInstanceArray
- typedef struct OptixRelocateInputInstanceArray OptixRelocateInputInstanceArray
- typedef enum OptixBuildInputType OptixBuildInputType
- typedef struct OptixBuildInput OptixBuildInput
- typedef struct OptixRelocateInput OptixRelocateInput
- typedef enum OptixInstanceFlags OptixInstanceFlags
- typedef struct OptixInstance OptixInstance
- typedef enum OptixBuildFlags OptixBuildFlags

- typedef enum OptixOpacityMicromapFlags OptixOpacityMicromapFlags
- typedef struct OptixOpacityMicromapDesc OptixOpacityMicromapDesc
- typedef struct OptixOpacityMicromapHistogramEntry OptixOpacityMicromapHistogramEntry
- typedef struct OptixOpacityMicromapArrayBuildInput OptixOpacityMicromapArrayBuildInput
- typedef struct OptixMicromapBufferSizes OptixMicromapBufferSizes
- typedef struct OptixMicromapBuffers OptixMicromapBuffers
- typedef enum OptixBuildOperation OptixBuildOperation
- typedef enum OptixMotionFlags OptixMotionFlags
- typedef struct OptixMotionOptions OptixMotionOptions
- typedef struct OptixAccelBuildOptions OptixAccelBuildOptions
- typedef struct OptixAccelBufferSizes OptixAccelBufferSizes
- typedef enum OptixAccelPropertyType OptixAccelPropertyType
- typedef struct OptixAccelEmitDesc OptixAccelEmitDesc
- typedef struct OptixRelocationInfo OptixRelocationInfo
- typedef struct OptixStaticTransform OptixStaticTransform
- typedef struct OptixMatrixMotionTransform OptixMatrixMotionTransform
- typedef struct OptixSRTData OptixSRTData
- typedef struct OptixSRTMotionTransform OptixSRTMotionTransform
- typedef enum OptixTraversableType OptixTraversableType
- typedef enum OptixPixelFormat OptixPixelFormat
- typedef struct OptixImage2D OptixImage2D
- typedef enum OptixDenoiserModelKind OptixDenoiserModelKind
- typedef enum OptixDenoiserAlphaMode OptixDenoiserAlphaMode
- typedef struct OptixDenoiserOptions OptixDenoiserOptions
- typedef struct OptixDenoiserGuideLayer OptixDenoiserGuideLayer
- typedef enum OptixDenoiserAOVType OptixDenoiserAOVType
- typedef struct OptixDenoiserLayer OptixDenoiserLayer
- typedef struct OptixDenoiserParams OptixDenoiserParams
- typedef struct OptixDenoiserSizes OptixDenoiserSizes
- typedef enum OptixRayFlags OptixRayFlags
- typedef enum OptixTransformType OptixTransformType
- typedef enum OptixTraversableGraphFlags OptixTraversableGraphFlags
- typedef enum OptixCompileOptimizationLevel OptixCompileOptimizationLevel
- typedef enum OptixCompileDebugLevel OptixCompileDebugLevel
- typedef enum OptixModuleCompileState OptixModuleCompileState
- typedef struct OptixModuleCompileBoundValueEntry OptixModuleCompileBoundValueEntry
- typedef enum OptixPayloadTypeID OptixPayloadTypeID
- typedef enum OptixPayloadSemantics OptixPayloadSemantics
- typedef struct OptixPayloadType OptixPayloadType
- typedef struct OptixModuleCompileOptions OptixModuleCompileOptions
- typedef enum OptixProgramGroupKind OptixProgramGroupKind
- typedef enum OptixProgramGroupFlags OptixProgramGroupFlags
- typedef struct OptixProgramGroupSingleModule OptixProgramGroupSingleModule
- typedef struct OptixProgramGroupHitgroup OptixProgramGroupHitgroup
- typedef struct OptixProgramGroupCallables OptixProgramGroupCallables
- typedef struct OptixProgramGroupDesc OptixProgramGroupDesc
- typedef struct OptixProgramGroupOptions OptixProgramGroupOptions
- typedef enum OptixExceptionCodes OptixExceptionCodes
- typedef enum OptixExceptionFlags OptixExceptionFlags
- typedef struct OptixPipelineCompileOptions OptixPipelineCompileOptions

- typedef struct OptixPipelineLinkOptions OptixPipelineLinkOptions
- typedef struct OptixShaderBindingTable OptixShaderBindingTable
- typedef struct OptixStackSizes OptixStackSizes
- typedef enum OptixQueryFunctionTableOptions OptixQueryFunctionTableOptions
- typedef OptixResult() OptixQueryFunctionTable\_t(int abiId, unsigned int numOptions, OptixQueryFunctionTableOptions \*, const void \*\*, void \*functionTable, size\_t sizeOfTable)
- typedef struct OptixBuiltinISOOptions OptixBuiltinISOOptions

## Enumerations

- enum OptixResult {  
OPTIX\_SUCCESS = 0 ,  
OPTIX\_ERROR\_INVALID\_VALUE = 7001 ,  
OPTIX\_ERROR\_HOST\_OUT\_OF\_MEMORY = 7002 ,  
OPTIX\_ERROR\_INVALID\_OPERATION = 7003 ,  
OPTIX\_ERROR\_FILE\_IO\_ERROR = 7004 ,  
OPTIX\_ERROR\_INVALID\_FILE\_FORMAT = 7005 ,  
OPTIX\_ERROR\_DISK\_CACHE\_INVALID\_PATH = 7010 ,  
OPTIX\_ERROR\_DISK\_CACHE\_PERMISSION\_ERROR = 7011 ,  
OPTIX\_ERROR\_DISK\_CACHE\_DATABASE\_ERROR = 7012 ,  
OPTIX\_ERROR\_DISK\_CACHE\_INVALID\_DATA = 7013 ,  
OPTIX\_ERROR\_LAUNCH\_FAILURE = 7050 ,  
OPTIX\_ERROR\_INVALID\_DEVICE\_CONTEXT = 7051 ,  
OPTIX\_ERROR\_CUDA\_NOT\_INITIALIZED = 7052 ,  
OPTIX\_ERROR\_VALIDATION\_FAILURE = 7053 ,  
OPTIX\_ERROR\_INVALID\_INPUT = 7200 ,  
OPTIX\_ERROR\_INVALID\_LAUNCH\_PARAMETER = 7201 ,  
OPTIX\_ERROR\_INVALID\_PAYLOAD\_ACCESS = 7202 ,  
OPTIX\_ERROR\_INVALID\_ATTRIBUTE\_ACCESS = 7203 ,  
OPTIX\_ERROR\_INVALID\_FUNCTION\_USE = 7204 ,  
OPTIX\_ERROR\_INVALID\_FUNCTION\_ARGUMENTS = 7205 ,  
OPTIX\_ERROR\_PIPELINE\_OUT\_OF\_CONSTANT\_MEMORY = 7250 ,  
OPTIX\_ERROR\_PIPELINE\_LINK\_ERROR = 7251 ,  
OPTIX\_ERROR\_ILLEGAL\_DURING\_TASK\_EXECUTE = 7270 ,  
OPTIX\_ERROR\_INTERNAL\_COMPILER\_ERROR = 7299 ,  
OPTIX\_ERROR\_DENOISER\_MODEL\_NOT\_SET = 7300 ,  
OPTIX\_ERROR\_DENOISER\_NOT\_INITIALIZED = 7301 ,  
OPTIX\_ERROR\_NOT\_COMPATIBLE = 7400 ,  
OPTIX\_ERROR\_PAYLOAD\_TYPE\_MISMATCH = 7500 ,  
OPTIX\_ERROR\_PAYLOAD\_TYPE\_RESOLUTION\_FAILED = 7501 ,  
OPTIX\_ERROR\_PAYLOAD\_TYPE\_ID\_INVALID = 7502 ,  
OPTIX\_ERROR\_NOT\_SUPPORTED = 7800 ,  
OPTIX\_ERROR\_UNSUPPORTED\_ABI\_VERSION = 7801 ,  
OPTIX\_ERROR\_FUNCTION\_TABLE\_SIZE\_MISMATCH = 7802 ,  
OPTIX\_ERROR\_INVALID\_ENTRY\_FUNCTION\_OPTIONS = 7803 ,  
OPTIX\_ERROR\_LIBRARY\_NOT\_FOUND = 7804 ,  
OPTIX\_ERROR\_ENTRY\_SYMBOL\_NOT\_FOUND = 7805 ,  
OPTIX\_ERROR\_LIBRARY\_UNLOAD\_FAILURE = 7806 ,  
OPTIX\_ERROR\_DEVICE\_OUT\_OF\_MEMORY = 7807 ,  
OPTIX\_ERROR\_CUDA\_ERROR = 7900 ,  
OPTIX\_ERROR\_INTERNAL\_ERROR = 7990 ,  
OPTIX\_ERROR\_UNKNOWN = 7999 }
- enum OptixDeviceProperty {  
OPTIX\_DEVICE\_PROPERTY\_LIMIT\_MAX\_TRACE\_DEPTH = 0x2001 ,



```

OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRAVERSABLE_GRAPH_DEPTH = 0x2002 ,
OPTIX_DEVICE_PROPERTY_LIMIT_MAX_PRIMITIVES_PER_GAS = 0x2003 ,
OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCES_PER_IAS = 0x2004 ,
OPTIX_DEVICE_PROPERTY_RTCORE_VERSION = 0x2005 ,
OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCE_ID = 0x2006 ,
OPTIX_DEVICE_PROPERTY_LIMIT_NUM_BITS_INSTANCE_VISIBILITY_MASK = 0x2007 ,
OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_RECORDS_PER_GAS = 0x2008 ,
OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_OFFSET = 0x2009 ,
OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING = 0x200A }
• enum OptixDeviceContextValidationMode {
    OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_OFF = 0 ,
    OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_ALL = 0xFFFFFFFF }
• enum OptixDevicePropertyShaderExecutionReorderingFlags {
    OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_NONE = 0 ,
    OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_STANDARD = 1
    << 0 }
• enum OptixGeometryFlags {
    OPTIX_GEOMETRY_FLAG_NONE = 0 ,
    OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT = 1u << 0 ,
    OPTIX_GEOMETRY_FLAG_REQUIRE_SINGLE_ANYHIT_CALL = 1u << 1 ,
    OPTIX_GEOMETRY_FLAG_DISABLE_TRIANGLE_FACE_CULLING = 1u << 2 }
• enum OptixHitKind {
    OPTIX_HIT_KIND_TRIANGLE_FRONT_FACE = 0xFE ,
    OPTIX_HIT_KIND_TRIANGLE_BACK_FACE = 0xFF }
• enum OptixIndicesFormat {
    OPTIX_INDICES_FORMAT_NONE = 0 ,
    OPTIX_INDICES_FORMAT_UNSIGNED_SHORT3 = 0x2102 ,
    OPTIX_INDICES_FORMAT_UNSIGNED_INT3 = 0x2103 }
• enum OptixVertexFormat {
    OPTIX_VERTEX_FORMAT_NONE = 0 ,
    OPTIX_VERTEX_FORMAT_FLOAT3 = 0x2121 ,
    OPTIX_VERTEX_FORMAT_FLOAT2 = 0x2122 ,
    OPTIX_VERTEX_FORMAT_HALF3 = 0x2123 ,
    OPTIX_VERTEX_FORMAT_HALF2 = 0x2124 ,
    OPTIX_VERTEX_FORMAT_SNORM16_3 = 0x2125 ,
    OPTIX_VERTEX_FORMAT_SNORM16_2 = 0x2126 }
• enum OptixTransformFormat {
    OPTIX_TRANSFORM_FORMAT_NONE = 0 ,
    OPTIX_TRANSFORM_FORMAT_MATRIX_FLOAT12 = 0x21E1 }
• enum OptixDisplacementMicromapBiasAndScaleFormat {
    OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_NONE = 0 ,
    OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_FLOAT2 = 0x2241 ,
    OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_HALF2 = 0x2242 }
• enum OptixDisplacementMicromapDirectionFormat {
    OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_NONE = 0 ,
    OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_FLOAT3 = 0x2261 ,
    OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_HALF3 = 0x2262 }
• enum OptixOpacityMicromapFormat {
    OPTIX_OPACITY_MICROMAP_FORMAT_NONE = 0 ,
    OPTIX_OPACITY_MICROMAP_FORMAT_2_STATE = 1 ,
    OPTIX_OPACITY_MICROMAP_FORMAT_4_STATE = 2 }
• enum OptixOpacityMicromapArrayIndexingMode {
    OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_NONE = 0 ,

```

- ```

OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_LINEAR = 1 ,
OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_INDEXED = 2 }

```
- enum OptixDisplacementMicromapFormat {

```

OPTIX_DISPLACEMENT_MICROMAP_FORMAT_NONE = 0 ,
OPTIX_DISPLACEMENT_MICROMAP_FORMAT_64_MICRO_TRIS_64_BYTES = 1 ,
OPTIX_DISPLACEMENT_MICROMAP_FORMAT_256_MICRO_TRIS_128_BYTES = 2 ,
OPTIX_DISPLACEMENT_MICROMAP_FORMAT_1024_MICRO_TRIS_128_BYTES = 3 }

```
  - enum OptixDisplacementMicromapFlags {

```

OPTIX_DISPLACEMENT_MICROMAP_FLAG_NONE = 0 ,
OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_TRACE = 1 << 0 ,
OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_BUILD = 1 << 1 }

```
  - enum OptixDisplacementMicromapTriangleFlags {

```

OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_NONE = 0 ,
OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_01 = 1 << 0 ,
OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_12 = 1 << 1 ,
OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_20 = 1 << 2 }

```
  - enum OptixDisplacementMicromapArrayIndexingMode {

```

OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_NONE = 0 ,
OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_LINEAR = 1 ,
OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_INDEXED = 2 }

```
  - enum OptixPrimitiveType {

```

OPTIX_PRIMITIVE_TYPE_CUSTOM = 0x2500 ,
OPTIX_PRIMITIVE_TYPE_ROUND_QUADRATIC_BSPLINE = 0x2501 ,
OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BSPLINE = 0x2502 ,
OPTIX_PRIMITIVE_TYPE_ROUND_LINEAR = 0x2503 ,
OPTIX_PRIMITIVE_TYPE_ROUND_CATMULLROM = 0x2504 ,
OPTIX_PRIMITIVE_TYPE_FLAT_QUADRATIC_BSPLINE = 0x2505 ,
OPTIX_PRIMITIVE_TYPE_SPHERE = 0x2506 ,
OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BEZIER = 0x2507 ,
OPTIX_PRIMITIVE_TYPE_TRIANGLE = 0x2531 ,
OPTIX_PRIMITIVE_TYPE_DISPLACED_MICROMESH_TRIANGLE = 0x2532 }

```
  - enum OptixPrimitiveTypeFlags {

```

OPTIX_PRIMITIVE_TYPE_FLAGS_CUSTOM = 1 << 0 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_QUADRATIC_BSPLINE = 1 << 1 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BSPLINE = 1 << 2 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_LINEAR = 1 << 3 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CATMULLROM = 1 << 4 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_FLAT_QUADRATIC_BSPLINE = 1 << 5 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_SPHERE = 1 << 6 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BEZIER = 1 << 7 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_TRIANGLE = 1 << 31 ,
OPTIX_PRIMITIVE_TYPE_FLAGS_DISPLACED_MICROMESH_TRIANGLE = 1 << 30 }

```
  - enum OptixCurveEndcapFlags {

```

OPTIX_CURVE_ENDCAP_DEFAULT = 0 ,
OPTIX_CURVE_ENDCAP_ON = 1 << 0 }

```
  - enum OptixBuildInputType {

```

OPTIX_BUILD_INPUT_TYPE_TRIANGLES = 0x2141 ,
OPTIX_BUILD_INPUT_TYPE_CUSTOM_PRIMITIVES = 0x2142 ,
OPTIX_BUILD_INPUT_TYPE_INSTANCES = 0x2143 ,
OPTIX_BUILD_INPUT_TYPE_INSTANCE_POINTERS = 0x2144 ,
OPTIX_BUILD_INPUT_TYPE_CURVES = 0x2145 ,
OPTIX_BUILD_INPUT_TYPE_SPHERES = 0x2146 }

```



- enum OptixInstanceFlags {  
OPTIX\_INSTANCE\_FLAG\_NONE = 0 ,  
OPTIX\_INSTANCE\_FLAG\_DISABLE\_TRIANGLE\_FACE\_CULLING = 1u << 0 ,  
OPTIX\_INSTANCE\_FLAG\_FLIP\_TRIANGLE\_FACING = 1u << 1 ,  
OPTIX\_INSTANCE\_FLAG\_DISABLE\_ANYHIT = 1u << 2 ,  
OPTIX\_INSTANCE\_FLAG\_ENFORCE\_ANYHIT = 1u << 3 ,  
OPTIX\_INSTANCE\_FLAG\_FORCE\_OPACITY\_MICROMAP\_2\_STATE = 1u << 4 ,  
OPTIX\_INSTANCE\_FLAG\_DISABLE\_OPACITY\_MICROMAPS = 1u << 5 }
- enum OptixBuildFlags {  
OPTIX\_BUILD\_FLAG\_NONE = 0 ,  
OPTIX\_BUILD\_FLAG\_ALLOW\_UPDATE = 1u << 0 ,  
OPTIX\_BUILD\_FLAG\_ALLOW\_COMPACTION = 1u << 1 ,  
OPTIX\_BUILD\_FLAG\_PREFER\_FAST\_TRACE = 1u << 2 ,  
OPTIX\_BUILD\_FLAG\_PREFER\_FAST\_BUILD = 1u << 3 ,  
OPTIX\_BUILD\_FLAG\_ALLOW\_RANDOM\_VERTEX\_ACCESS = 1u << 4 ,  
OPTIX\_BUILD\_FLAG\_ALLOW\_RANDOM\_INSTANCE\_ACCESS = 1u << 5 ,  
OPTIX\_BUILD\_FLAG\_ALLOW\_OPACITY\_MICROMAP\_UPDATE = 1u << 6 ,  
OPTIX\_BUILD\_FLAG\_ALLOW\_DISABLE\_OPACITY\_MICROMAPS = 1u << 7 }
- enum OptixOpacityMicromapFlags {  
OPTIX\_OPACITY\_MICROMAP\_FLAG\_NONE = 0 ,  
OPTIX\_OPACITY\_MICROMAP\_FLAG\_PREFER\_FAST\_TRACE = 1 << 0 ,  
OPTIX\_OPACITY\_MICROMAP\_FLAG\_PREFER\_FAST\_BUILD = 1 << 1 }
- enum OptixBuildOperation {  
OPTIX\_BUILD\_OPERATION\_BUILD = 0x2161 ,  
OPTIX\_BUILD\_OPERATION\_UPDATE = 0x2162 }
- enum OptixMotionFlags {  
OPTIX\_MOTION\_FLAG\_NONE = 0 ,  
OPTIX\_MOTION\_FLAG\_START\_VANISH = 1u << 0 ,  
OPTIX\_MOTION\_FLAG\_END\_VANISH = 1u << 1 }
- enum OptixAccelPropertyType {  
OPTIX\_PROPERTY\_TYPE\_COMPACTED\_SIZE = 0x2181 ,  
OPTIX\_PROPERTY\_TYPE\_AABBS = 0x2182 }
- enum OptixTraversableType {  
OPTIX\_TRAVERSABLE\_TYPE\_STATIC\_TRANSFORM = 0x21C1 ,  
OPTIX\_TRAVERSABLE\_TYPE\_MATRIX\_MOTION\_TRANSFORM = 0x21C2 ,  
OPTIX\_TRAVERSABLE\_TYPE\_SRT\_MOTION\_TRANSFORM = 0x21C3 }
- enum OptixPixelFormat {  
OPTIX\_PIXEL\_FORMAT\_HALF1 = 0x220a ,  
OPTIX\_PIXEL\_FORMAT\_HALF2 = 0x2207 ,  
OPTIX\_PIXEL\_FORMAT\_HALF3 = 0x2201 ,  
OPTIX\_PIXEL\_FORMAT\_HALF4 = 0x2202 ,  
OPTIX\_PIXEL\_FORMAT\_FLOAT1 = 0x220b ,  
OPTIX\_PIXEL\_FORMAT\_FLOAT2 = 0x2208 ,  
OPTIX\_PIXEL\_FORMAT\_FLOAT3 = 0x2203 ,  
OPTIX\_PIXEL\_FORMAT\_FLOAT4 = 0x2204 ,  
OPTIX\_PIXEL\_FORMAT\_UCHAR3 = 0x2205 ,  
OPTIX\_PIXEL\_FORMAT\_UCHAR4 = 0x2206 ,  
OPTIX\_PIXEL\_FORMAT\_INTERNAL\_GUIDE\_LAYER = 0x2209 }
- enum OptixDenoiserModelKind {  
OPTIX\_DENOISER\_MODEL\_KIND\_LDR = 0x2322 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_HDR = 0x2323 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_AOV = 0x2324 ,  
OPTIX\_DENOISER\_MODEL\_KIND\_TEMPORAL = 0x2325 ,

```

OPTIX_DENOISER_MODEL_KIND_TEMPORAL_AOV = 0x2326 ,
OPTIX_DENOISER_MODEL_KIND_UPSCALE2X = 0x2327 ,
OPTIX_DENOISER_MODEL_KIND_TEMPORAL_UPSCALE2X = 0x2328 }
• enum OptixDenoiserAlphaMode {
    OPTIX_DENOISER_ALPHA_MODE_COPY = 0 ,
    OPTIX_DENOISER_ALPHA_MODE_DENOISE = 1 }
• enum OptixDenoiserAOVType {
    OPTIX_DENOISER_AOV_TYPE_NONE = 0 ,
    OPTIX_DENOISER_AOV_TYPE_BEAUTY = 0x7000 ,
    OPTIX_DENOISER_AOV_TYPE_SPECULAR = 0x7001 ,
    OPTIX_DENOISER_AOV_TYPE_REFLECTION = 0x7002 ,
    OPTIX_DENOISER_AOV_TYPE_REFRACTION = 0x7003 ,
    OPTIX_DENOISER_AOV_TYPE_DIFFUSE = 0x7004 }
• enum OptixRayFlags {
    OPTIX_RAY_FLAG_NONE = 0u ,
    OPTIX_RAY_FLAG_DISABLE_ANYHIT = 1u << 0 ,
    OPTIX_RAY_FLAG_ENFORCE_ANYHIT = 1u << 1 ,
    OPTIX_RAY_FLAG_TERMINATE_ON_FIRST_HIT = 1u << 2 ,
    OPTIX_RAY_FLAG_DISABLE_CLOSESTHIT = 1u << 3 ,
    OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES = 1u << 4 ,
    OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES = 1u << 5 ,
    OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT = 1u << 6 ,
    OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT = 1u << 7 ,
    OPTIX_RAY_FLAG_FORCE_OPACITY_MICROMAP_2_STATE = 1u << 10 }
• enum OptixTransformType {
    OPTIX_TRANSFORM_TYPE_NONE = 0 ,
    OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM = 1 ,
    OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM = 2 ,
    OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM = 3 ,
    OPTIX_TRANSFORM_TYPE_INSTANCE = 4 }
• enum OptixTraversableGraphFlags {
    OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_ANY = 0 ,
    OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_GAS = 1u << 0 ,
    OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_LEVEL_INSTANCING = 1u << 1 }
• enum OptixCompileOptimizationLevel {
    OPTIX_COMPILE_OPTIMIZATION_DEFAULT = 0 ,
    OPTIX_COMPILE_OPTIMIZATION_LEVEL_0 = 0x2340 ,
    OPTIX_COMPILE_OPTIMIZATION_LEVEL_1 = 0x2341 ,
    OPTIX_COMPILE_OPTIMIZATION_LEVEL_2 = 0x2342 ,
    OPTIX_COMPILE_OPTIMIZATION_LEVEL_3 = 0x2343 }
• enum OptixCompileDebugLevel {
    OPTIX_COMPILE_DEBUG_LEVEL_DEFAULT = 0 ,
    OPTIX_COMPILE_DEBUG_LEVEL_NONE = 0x2350 ,
    OPTIX_COMPILE_DEBUG_LEVEL_MINIMAL = 0x2351 ,
    OPTIX_COMPILE_DEBUG_LEVEL_MODERATE = 0x2353 ,
    OPTIX_COMPILE_DEBUG_LEVEL_FULL = 0x2352 }
• enum OptixModuleCompileState {
    OPTIX_MODULE_COMPILE_STATE_NOT_STARTED = 0x2360 ,
    OPTIX_MODULE_COMPILE_STATE_STARTED = 0x2361 ,
    OPTIX_MODULE_COMPILE_STATE_IMPENDING_FAILURE = 0x2362 ,
    OPTIX_MODULE_COMPILE_STATE_FAILED = 0x2363 ,
    OPTIX_MODULE_COMPILE_STATE_COMPLETED = 0x2364 }

```

- enum OptixPayloadTypeID {  
OPTIX\_PAYLOAD\_TYPE\_DEFAULT = 0 ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_0 = (1 << 0u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_1 = (1 << 1u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_2 = (1 << 2u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_3 = (1 << 3u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_4 = (1 << 4u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_5 = (1 << 5u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_6 = (1 << 6u) ,  
OPTIX\_PAYLOAD\_TYPE\_ID\_7 = (1 << 7u) }
- enum OptixPayloadSemantics {  
OPTIX\_PAYLOAD\_SEMANTICS\_TRACE\_CALLER\_NONE = 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_TRACE\_CALLER\_READ = 1u << 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_TRACE\_CALLER\_WRITE = 2u << 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_TRACE\_CALLER\_READ\_WRITE = 3u << 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_CH\_NONE = 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_CH\_READ = 1u << 2 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_CH\_WRITE = 2u << 2 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_CH\_READ\_WRITE = 3u << 2 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_MS\_NONE = 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_MS\_READ = 1u << 4 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_MS\_WRITE = 2u << 4 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_MS\_READ\_WRITE = 3u << 4 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_AH\_NONE = 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_AH\_READ = 1u << 6 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_AH\_WRITE = 2u << 6 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_AH\_READ\_WRITE = 3u << 6 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_IS\_NONE = 0 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_IS\_READ = 1u << 8 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_IS\_WRITE = 2u << 8 ,  
OPTIX\_PAYLOAD\_SEMANTICS\_IS\_READ\_WRITE = 3u << 8 }
- enum OptixProgramGroupKind {  
OPTIX\_PROGRAM\_GROUP\_KIND\_RAYGEN = 0x2421 ,  
OPTIX\_PROGRAM\_GROUP\_KIND\_MISS = 0x2422 ,  
OPTIX\_PROGRAM\_GROUP\_KIND\_EXCEPTION = 0x2423 ,  
OPTIX\_PROGRAM\_GROUP\_KIND\_HITGROUP = 0x2424 ,  
OPTIX\_PROGRAM\_GROUP\_KIND\_CALLABLES = 0x2425 }
- enum OptixProgramGroupFlags { OPTIX\_PROGRAM\_GROUP\_FLAGS\_NONE = 0 }
- enum OptixExceptionCodes {  
OPTIX\_EXCEPTION\_CODE\_STACK\_OVERFLOW = -1 ,  
OPTIX\_EXCEPTION\_CODE\_TRACE\_DEPTH\_EXCEEDED = -2 }
- enum OptixExceptionFlags {  
OPTIX\_EXCEPTION\_FLAG\_NONE = 0 ,  
OPTIX\_EXCEPTION\_FLAG\_STACK\_OVERFLOW = 1u << 0 ,  
OPTIX\_EXCEPTION\_FLAG\_TRACE\_DEPTH = 1u << 1 ,  
OPTIX\_EXCEPTION\_FLAG\_USER = 1u << 2 }
- enum OptixQueryFunctionTableOptions { OPTIX\_QUERY\_FUNCTION\_TABLE\_OPTION\_DUMMY = 0 }

### 8.25.1 Detailed Description

OptiX public API header.

Author

NVIDIA Corporation

OptiX types include file – defines types and enums used by the API. For the math library routines include `optix_math.h`

## 8.26 optix\_types.h

[Go to the documentation of this file.](#)

```

1
2 /*
3 * Copyright (c) 2023 NVIDIA Corporation. All rights reserved.
4 *
5 * NVIDIA Corporation and its licensors retain all intellectual property and proprietary
6 * rights in and to this software, related documentation and any modifications thereto.
7 * Any use, reproduction, disclosure or distribution of this software and related
8 * documentation without an express license agreement from NVIDIA Corporation is strictly
9 * prohibited.
10 *
11 * TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, THIS SOFTWARE IS PROVIDED *AS IS*
12 * AND NVIDIA AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, EITHER EXPRESS OR IMPLIED,
13 * INCLUDING, BUT NOT LIMITED TO, IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A
14 * PARTICULAR PURPOSE. IN NO EVENT SHALL NVIDIA OR ITS SUPPLIERS BE LIABLE FOR ANY
15 * SPECIAL, INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT
16 * LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF
17 * BUSINESS INFORMATION, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR
18 * INABILITY TO USE THIS SOFTWARE, EVEN IF NVIDIA HAS BEEN ADVISED OF THE POSSIBILITY OF
19 * SUCH DAMAGES
20 */
21
28
29 #ifndef OPTIX_OPTIX_TYPES_H
30 #define OPTIX_OPTIX_TYPES_H
31
32 #if !defined(__CUDACC_RTC__)
33 #include <stddef.h> /* for size_t */
34 #endif
35
36 #ifdef NV_MODULE_OPTIX
37 // This is a mechanism to include <g_nvconfig.h> in driver builds only and translate any nvconfig macro to
38 // a custom OPTIX-specific macro, that can also be used in SDK builds/installs
39 #include <exp/misc/optix_nvconfig_translate.h> // includes <g_nvconfig.h>
40 #endif // NV_MODULE_OPTIX
41
44
49 // This typedef should match the one in cuda.h in order to avoid compilation errors.
50 #if defined(_WIN64) || defined(__LP64__)
52 typedef unsigned long long CUdeviceptr;
53 #else
55 typedef unsigned int CUdeviceptr;
56 #endif
57
59 typedef struct OptixDeviceContext_t* OptixDeviceContext;
60
62 typedef struct OptixModule_t* OptixModule;
63
65 typedef struct OptixProgramGroup_t* OptixProgramGroup;
66
68 typedef struct OptixPipeline_t* OptixPipeline;
69
71 typedef struct OptixDenoiser_t* OptixDenoiser;
72
74 typedef struct OptixTask_t* OptixTask;
75

```

```

77 typedef unsigned long long OptixTraversableHandle;
78
79 typedef unsigned int OptixVisibilityMask;
80
81
82 #define OPTIX_SBT_RECORD_HEADER_SIZE ((size_t)32)
83
84 #define OPTIX_SBT_RECORD_ALIGNMENT 16ull
85
86 #define OPTIX_ACCEL_BUFFER_BYTE_ALIGNMENT 128ull
87
88 #define OPTIX_INSTANCE_BYTE_ALIGNMENT 16ull
89
90 #define OPTIX_AABB_BUFFER_BYTE_ALIGNMENT 8ull
91
92 #define OPTIX_GEOMETRY_TRANSFORM_BYTE_ALIGNMENT 16ull
93
94 #define OPTIX_TRANSFORM_BYTE_ALIGNMENT 64ull
95
96 #define OPTIX_OPACITY_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT 8ull
97
98 #define OPTIX_COMPILE_DEFAULT_MAX_REGISTER_COUNT 0
99
100 #define OPTIX_COMPILE_DEFAULT_MAX_PAYLOAD_TYPE_COUNT 8
101
102 #define OPTIX_COMPILE_DEFAULT_MAX_PAYLOAD_VALUE_COUNT 32
103
104 #define OPTIX_OPACITY_MICROMAP_STATE_TRANSPARENT (0)
105 #define OPTIX_OPACITY_MICROMAP_STATE_OPAQUE (1)
106 #define OPTIX_OPACITY_MICROMAP_STATE_UNKNOWN_TRANSPARENT (2)
107 #define OPTIX_OPACITY_MICROMAP_STATE_UNKNOWN_OPAQUE (3)
108
109 #define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_TRANSPARENT (-1)
110 #define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_OPAQUE (-2)
111 #define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_TRANSPARENT (-3)
112 #define OPTIX_OPACITY_MICROMAP_PREDEFINED_INDEX_FULLY_UNKNOWN_OPAQUE (-4)
113
114 #define OPTIX_OPACITY_MICROMAP_ARRAY_BUFFER_BYTE_ALIGNMENT 128ull
115
116 #define OPTIX_OPACITY_MICROMAP_MAX_SUBDIVISION_LEVEL 12
117
118 #define OPTIX_DISPLACEMENT_MICROMAP_MAX_SUBDIVISION_LEVEL 5
119
120 #define OPTIX_DISPLACEMENT_MICROMAP_DESC_BUFFER_BYTE_ALIGNMENT 8ull
121
122 #define OPTIX_DISPLACEMENT_MICROMAP_ARRAY_BUFFER_BYTE_ALIGNMENT 128ull
123
124 typedef enum OptixResult
125 {
126     OPTIX_SUCCESS = 0,
127     OPTIX_ERROR_INVALID_VALUE = 7001,
128     OPTIX_ERROR_HOST_OUT_OF_MEMORY = 7002,
129     OPTIX_ERROR_INVALID_OPERATION = 7003,
130     OPTIX_ERROR_FILE_IO_ERROR = 7004,
131     OPTIX_ERROR_INVALID_FILE_FORMAT = 7005,
132     OPTIX_ERROR_DISK_CACHE_INVALID_PATH = 7010,
133     OPTIX_ERROR_DISK_CACHE_PERMISSION_ERROR = 7011,
134     OPTIX_ERROR_DISK_CACHE_DATABASE_ERROR = 7012,
135     OPTIX_ERROR_DISK_CACHE_INVALID_DATA = 7013,
136     OPTIX_ERROR_LAUNCH_FAILURE = 7050,
137     OPTIX_ERROR_INVALID_DEVICE_CONTEXT = 7051,
138     OPTIX_ERROR_CUDA_NOT_INITIALIZED = 7052,
139     OPTIX_ERROR_VALIDATION_FAILURE = 7053,
140     OPTIX_ERROR_INVALID_INPUT = 7200,
141     OPTIX_ERROR_INVALID_LAUNCH_PARAMETER = 7201,
142     OPTIX_ERROR_INVALID_PAYLOAD_ACCESS = 7202,
143     OPTIX_ERROR_INVALID_ATTRIBUTE_ACCESS = 7203,
144     OPTIX_ERROR_INVALID_FUNCTION_USE = 7204,

```

```

172     OPTIX_ERROR_INVALID_FUNCTION_ARGUMENTS           = 7205,
173     OPTIX_ERROR_PIPELINE_OUT_OF_CONSTANT_MEMORY      = 7250,
174     OPTIX_ERROR_PIPELINE_LINK_ERROR                  = 7251,
175     OPTIX_ERROR_ILLEGAL_DURING_TASK_EXECUTE          = 7270,
176     OPTIX_ERROR_INTERNAL_COMPILER_ERROR              = 7299,
177     OPTIX_ERROR_DENOISER_MODEL_NOT_SET                = 7300,
178     OPTIX_ERROR_DENOISER_NOT_INITIALIZED              = 7301,
179     OPTIX_ERROR_NOT_COMPATIBLE                        = 7400,
180     OPTIX_ERROR_PAYLOAD_TYPE_MISMATCH                = 7500,
181     OPTIX_ERROR_PAYLOAD_TYPE_RESOLUTION_FAILED        = 7501,
182     OPTIX_ERROR_PAYLOAD_TYPE_ID_INVALID               = 7502,
183     OPTIX_ERROR_NOT_SUPPORTED                         = 7800,
184     OPTIX_ERROR_UNSUPPORTED_ABI_VERSION               = 7801,
185     OPTIX_ERROR_FUNCTION_TABLE_SIZE_MISMATCH          = 7802,
186     OPTIX_ERROR_INVALID_ENTRY_FUNCTION_OPTIONS        = 7803,
187     OPTIX_ERROR_LIBRARY_NOT_FOUND                     = 7804,
188     OPTIX_ERROR_ENTRY_SYMBOL_NOT_FOUND                = 7805,
189     OPTIX_ERROR_LIBRARY_UNLOAD_FAILURE                = 7806,
190     OPTIX_ERROR_DEVICE_OUT_OF_MEMORY                 = 7807,
191     OPTIX_ERROR_CUDA_ERROR                           = 7900,
192     OPTIX_ERROR_INTERNAL_ERROR                        = 7990,
193     OPTIX_ERROR_UNKNOWN                              = 7999,
194 } OptixResult;
195
196 #typedef enum OptixDeviceProperty
197 {
198     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRACE_DEPTH = 0x2001,
199
200     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_TRAVERSABLE_GRAPH_DEPTH = 0x2002,
201
202     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_PRIMITIVES_PER_GAS = 0x2003,
203
204     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCES_PER_IAS = 0x2004,
205
206     OPTIX_DEVICE_PROPERTY_RTCORE_VERSION = 0x2005,
207
208     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_INSTANCE_ID = 0x2006,
209
210     OPTIX_DEVICE_PROPERTY_LIMIT_NUM_BITS_INSTANCE_VISIBILITY_MASK = 0x2007,
211
212     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_RECORDS_PER_GAS = 0x2008,
213
214     OPTIX_DEVICE_PROPERTY_LIMIT_MAX_SBT_OFFSET = 0x2009,
215
216     OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING = 0x200A,
217 } OptixDeviceProperty;
218
219 #typedef void (*OptixLogCallback)(unsigned int level, const char* tag, const char* message, void* cbdata);
220
221 #typedef enum OptixDeviceContextValidationMode
222 {
223     OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_OFF = 0,
224     OPTIX_DEVICE_CONTEXT_VALIDATION_MODE_ALL = 0xFFFFFFFF
225 } OptixDeviceContextValidationMode;
226
227 #typedef struct OptixDeviceContextOptions
228 {
229     OptixLogCallback logCallbackFunction;
230     void* logCallbackData;
231     int logCallbackLevel;
232     OptixDeviceContextValidationMode validationMode;
233 } OptixDeviceContextOptions;
234
235 #typedef enum OptixDevicePropertyShaderExecutionReorderingFlags
236 {
237     OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_NONE = 0,
238
239
240
241
242
243
244
245
246
247
248
249
250
251
252
253
254
255
256
257
258
259
260
261
262
263
264
265
266
267
268
269
270
271
272
273
274
275
276
277
278
279
280
281
282
283
284
285
286
287
288
289
290
291
292
293
294
295
296
297
298
299
300
301
302
303
304
305

```

```

306     // Standard thread reordering is supported
307     OPTIX_DEVICE_PROPERTY_SHADER_EXECUTION_REORDERING_FLAG_STANDARD = 1 « 0,
308 } OptixDevicePropertyShaderExecutionReorderingFlags;
309
312 typedef enum OptixGeometryFlags
313 {
314     OPTIX_GEOMETRY_FLAG_NONE = 0,
315
316     OPTIX_GEOMETRY_FLAG_DISABLE_ANYHIT = 1u « 0,
317
318     OPTIX_GEOMETRY_FLAG_REQUIRE_SINGLE_ANYHIT_CALL = 1u « 1,
319
320     OPTIX_GEOMETRY_FLAG_DISABLE_TRIANGLE_FACE_CULLING = 1u « 2,
321 } OptixGeometryFlags;
322
323 typedef enum OptixHitKind
324 {
325     OPTIX_HIT_KIND_TRIANGLE_FRONT_FACE = 0xFE,
326     OPTIX_HIT_KIND_TRIANGLE_BACK_FACE = 0xFF
327 } OptixHitKind;
328
329 typedef enum OptixIndicesFormat
330 {
331     OPTIX_INDICES_FORMAT_NONE = 0,
332     OPTIX_INDICES_FORMAT_UNSIGNED_SHORT3 = 0x2102,
333     OPTIX_INDICES_FORMAT_UNSIGNED_INT3 = 0x2103
334 } OptixIndicesFormat;
335
336 typedef enum OptixVertexFormat
337 {
338     OPTIX_VERTEX_FORMAT_NONE = 0,
339     OPTIX_VERTEX_FORMAT_FLOAT3 = 0x2121,
340     OPTIX_VERTEX_FORMAT_FLOAT2 = 0x2122,
341     OPTIX_VERTEX_FORMAT_HALF3 = 0x2123,
342     OPTIX_VERTEX_FORMAT_HALF2 = 0x2124,
343     OPTIX_VERTEX_FORMAT_SNORM16_3 = 0x2125,
344     OPTIX_VERTEX_FORMAT_SNORM16_2 = 0x2126
345 } OptixVertexFormat;
346
347 typedef enum OptixTransformFormat
348 {
349     OPTIX_TRANSFORM_FORMAT_NONE = 0,
350     OPTIX_TRANSFORM_FORMAT_MATRIX_FLOAT12 = 0x21E1,
351 } OptixTransformFormat;
352
353 typedef enum OptixDisplacementMicromapBiasAndScaleFormat
354 {
355     OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_NONE = 0,
356     OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_FLOAT2 = 0x2241,
357     OPTIX_DISPLACEMENT_MICROMAP_BIAS_AND_SCALE_FORMAT_HALF2 = 0x2242,
358 } OptixDisplacementMicromapBiasAndScaleFormat;
359
360 typedef enum OptixDisplacementMicromapDirectionFormat
361 {
362     OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_NONE = 0,
363     OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_FLOAT3 = 0x2261,
364     OPTIX_DISPLACEMENT_MICROMAP_DIRECTION_FORMAT_HALF3 = 0x2262,
365 } OptixDisplacementMicromapDirectionFormat;
366
367 typedef enum OptixOpacityMicromapFormat
368 {
369     OPTIX_OPACITY_MICROMAP_FORMAT_NONE = 0,
370     OPTIX_OPACITY_MICROMAP_FORMAT_2_STATE = 1,
371     OPTIX_OPACITY_MICROMAP_FORMAT_4_STATE = 2,
372 } OptixOpacityMicromapFormat;
373
374 typedef enum OptixOpacityMicromapArrayIndexingMode

```



```

402 {
404     OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_NONE = 0,
407     OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_LINEAR = 1,
411     OPTIX_OPACITY_MICROMAP_ARRAY_INDEXING_MODE_INDEXED = 2,
412 } OptixOpacityMicromapArrayIndexingMode;
413
418 typedef struct OptixOpacityMicromapUsageCount
419 {
422     unsigned int count;
424     unsigned int subdivisionLevel;
426     OptixOpacityMicromapFormat format;
427 } OptixOpacityMicromapUsageCount;
428
429 typedef struct OptixBuildInputOpacityMicromap
430 {
432     OptixOpacityMicromapArrayIndexingMode indexingMode;
433
438     CUdeviceptr opacityMicromapArray;
439
449     CUdeviceptr indexBuffer;
450
453     unsigned int indexSizeInBytes;
454
457     unsigned int indexStrideInBytes;
458
460     unsigned int indexOffset;
461
463     unsigned int numMicromapUsageCounts;
466     const OptixOpacityMicromapUsageCount* micromapUsageCounts;
467 } OptixBuildInputOpacityMicromap;
468
469 typedef struct OptixRelocateInputOpacityMicromap
470 {
474     CUdeviceptr opacityMicromapArray;
475 } OptixRelocateInputOpacityMicromap;
476
477
479 typedef enum OptixDisplacementMicromapFormat
480 {
481     OPTIX_DISPLACEMENT_MICROMAP_FORMAT_NONE = 0,
482     OPTIX_DISPLACEMENT_MICROMAP_FORMAT_64_MICRO_TRIS_64_BYTES = 1,
483     OPTIX_DISPLACEMENT_MICROMAP_FORMAT_256_MICRO_TRIS_128_BYTES = 2,
484     OPTIX_DISPLACEMENT_MICROMAP_FORMAT_1024_MICRO_TRIS_128_BYTES = 3,
485 } OptixDisplacementMicromapFormat;
486
488 typedef enum OptixDisplacementMicromapFlags
489 {
490     OPTIX_DISPLACEMENT_MICROMAP_FLAG_NONE = 0,
491
493     OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_TRACE = 1 << 0,
494
496     OPTIX_DISPLACEMENT_MICROMAP_FLAG_PREFER_FAST_BUILD = 1 << 1,
497
498 } OptixDisplacementMicromapFlags;
499
500 typedef enum OptixDisplacementMicromapTriangleFlags
501 {
502     OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_NONE = 0,
505     OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_01 = 1 << 0,
507     OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_12 = 1 << 1,
509     OPTIX_DISPLACEMENT_MICROMAP_TRIANGLE_FLAG_DECIMATE_EDGE_20 = 1 << 2,
510 } OptixDisplacementMicromapTriangleFlags;
511
512 typedef struct OptixDisplacementMicromapDesc
513 {
515     unsigned int byteOffset;
517     unsigned short subdivisionLevel;

```



```

519     unsigned short format;
520 } OptixDisplacementMicromapDesc;
521
526 typedef struct OptixDisplacementMicromapHistogramEntry
527 {
529     unsigned int          count;
531     unsigned int          subdivisionLevel;
533     OptixDisplacementMicromapFormat format;
534 } OptixDisplacementMicromapHistogramEntry;
535
537 typedef struct OptixDisplacementMicromapArrayBuildInput
538 {
540     OptixDisplacementMicromapFlags          flags;
542     CUdeviceptr displacementValuesBuffer;
545     CUdeviceptr perDisplacementMicromapDescBuffer;
549     unsigned int perDisplacementMicromapDescStrideInBytes;
551     unsigned int numDisplacementMicromapHistogramEntries;
554     const OptixDisplacementMicromapHistogramEntry* displacementMicromapHistogramEntries;
555 } OptixDisplacementMicromapArrayBuildInput;
556
561 typedef struct OptixDisplacementMicromapUsageCount
562 {
565     unsigned int          count;
567     unsigned int          subdivisionLevel;
569     OptixDisplacementMicromapFormat format;
570 } OptixDisplacementMicromapUsageCount;
571
573 typedef enum OptixDisplacementMicromapArrayIndexingMode
574 {
576     OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_NONE = 0,
579     OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_LINEAR = 1,
583     OPTIX_DISPLACEMENT_MICROMAP_ARRAY_INDEXING_MODE_INDEXED = 2,
584 } OptixDisplacementMicromapArrayIndexingMode;
585
587 typedef struct OptixBuildInputDisplacementMicromap
588 {
590     OptixDisplacementMicromapArrayIndexingMode indexingMode;
591
593     CUdeviceptr displacementMicromapArray;
595     CUdeviceptr displacementMicromapIndexBuffer;
597     CUdeviceptr vertexDirectionsBuffer;
599     CUdeviceptr vertexBiasAndScaleBuffer;
601     CUdeviceptr triangleFlagsBuffer;
602
604     unsigned int displacementMicromapIndexOffset;
607     unsigned int displacementMicromapIndexStrideInBytes;
609     unsigned int displacementMicromapIndexSizeInBytes;
610
612     OptixDisplacementMicromapDirectionFormat vertexDirectionFormat;
614     unsigned int vertexDirectionStrideInBytes;
615
617     OptixDisplacementMicromapBiasAndScaleFormat vertexBiasAndScaleFormat;
619     unsigned int vertexBiasAndScaleStrideInBytes;
620
622     unsigned int triangleFlagsStrideInBytes;
623
625     unsigned int numDisplacementMicromapUsageCounts;
628     const OptixDisplacementMicromapUsageCount* displacementMicromapUsageCounts;
629
630 } OptixBuildInputDisplacementMicromap;
631
632
636 typedef struct OptixBuildInputTriangleArray
637 {
645     const CUdeviceptr* vertexBuffers;
646
648     unsigned int numVertices;

```

```

649
651     OptixVertexFormat vertexFormat;
652
655     unsigned int vertexStrideInBytes;
656
660     CUdeviceptr indexBuffer;
661
663     unsigned int numIndexTriplets;
664
666     OptixIndicesFormat indexFormat;
667
670     unsigned int indexStrideInBytes;
671
675     CUdeviceptr preTransform;
676
680     const unsigned int* flags;
681
683     unsigned int numSbtRecords;
684
688     CUdeviceptr sbtIndexOffsetBuffer;
689
691     unsigned int sbtIndexOffsetSizeInBytes;
692
695     unsigned int sbtIndexOffsetStrideInBytes;
696
699     unsigned int primitiveIndexOffset;
700
702     OptixTransformFormat transformFormat;
703
705     OptixBuildInputOpacityMicromap opacityMicromap;
707     OptixBuildInputDisplacementMicromap displacementMicromap;
708
709 } OptixBuildInputTriangleArray;
710
714 typedef struct OptixRelocateInputTriangleArray
715 {
718     unsigned int numSbtRecords;
719
721     OptixRelocateInputOpacityMicromap opacityMicromap;
722 } OptixRelocateInputTriangleArray;
723
726 typedef enum OptixPrimitiveType
727 {
729     OPTIX_PRIMITIVE_TYPE_CUSTOM = 0x2500,
731     OPTIX_PRIMITIVE_TYPE_ROUND_QUADRATIC_BSPLINE = 0x2501,
733     OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BSPLINE = 0x2502,
735     OPTIX_PRIMITIVE_TYPE_ROUND_LINEAR = 0x2503,
737     OPTIX_PRIMITIVE_TYPE_ROUND_CATMULLROM = 0x2504,
739     OPTIX_PRIMITIVE_TYPE_FLAT_QUADRATIC_BSPLINE = 0x2505,
741     OPTIX_PRIMITIVE_TYPE_SPHERE = 0x2506,
743     OPTIX_PRIMITIVE_TYPE_ROUND_CUBIC_BEZIER = 0x2507,
745     OPTIX_PRIMITIVE_TYPE_TRIANGLE = 0x2531,
747     OPTIX_PRIMITIVE_TYPE_DISPLACED_MICROMESH_TRIANGLE = 0x2532,
748 } OptixPrimitiveType;
749
753 typedef enum OptixPrimitiveTypeFlags
754 {
756     OPTIX_PRIMITIVE_TYPE_FLAGS_CUSTOM = 1 « 0,
758     OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_QUADRATIC_BSPLINE = 1 « 1,
760     OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BSPLINE = 1 « 2,
762     OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_LINEAR = 1 « 3,
764     OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CATMULLROM = 1 « 4,
766     OPTIX_PRIMITIVE_TYPE_FLAGS_FLAT_QUADRATIC_BSPLINE = 1 « 5,
768     OPTIX_PRIMITIVE_TYPE_FLAGS_SPHERE = 1 « 6,
770     OPTIX_PRIMITIVE_TYPE_FLAGS_ROUND_CUBIC_BEZIER = 1 « 7,
772     OPTIX_PRIMITIVE_TYPE_FLAGS_TRIANGLE = 1 « 31,
774     OPTIX_PRIMITIVE_TYPE_FLAGS_DISPLACED_MICROMESH_TRIANGLE = 1 « 30,

```

```

775 } OptixPrimitiveTypeFlags;
776
779 typedef enum OptixCurveEndcapFlags
780 {
782     OPTIX_CURVE_ENDCAP_DEFAULT           = 0,
784     OPTIX_CURVE_ENDCAP_ON               = 1 « 0,
785 } OptixCurveEndcapFlags;
786
804 typedef struct OptixBuildInputCurveArray
805 {
808     OptixPrimitiveType curveType;
810     unsigned int numPrimitives;
811
816     const CUdeviceptr* vertexBuffers;
818     unsigned int numVertices;
821     unsigned int vertexStrideInBytes;
822
825     const CUdeviceptr* widthBuffers;
828     unsigned int widthStrideInBytes;
829
831     const CUdeviceptr* normalBuffers;
833     unsigned int normalStrideInBytes;
834
840     CUdeviceptr indexBuffer;
843     unsigned int indexStrideInBytes;
844
847     unsigned int flag;
848
851     unsigned int primitiveIndexOffset;
852
854     unsigned int endcapFlags;
855 } OptixBuildInputCurveArray;
856
869 typedef struct OptixBuildInputSphereArray
870 {
875     const CUdeviceptr* vertexBuffers;
876
879     unsigned int vertexStrideInBytes;
881     unsigned int numVertices;
882
885     const CUdeviceptr* radiusBuffers;
888     unsigned int radiusStrideInBytes;
891     int singleRadius;
892
896     const unsigned int* flags;
897
899     unsigned int numSbtRecords;
903     CUdeviceptr sbtIndexOffsetBuffer;
905     unsigned int sbtIndexOffsetSizeInBytes;
908     unsigned int sbtIndexOffsetStrideInBytes;
909
912     unsigned int primitiveIndexOffset;
913 } OptixBuildInputSphereArray;
914
916 typedef struct OptixAabb
917 {
918     float minX;
919     float minY;
920     float minZ;
921     float maxX;
922     float maxY;
923     float maxZ;
924 } OptixAabb;
925
929 typedef struct OptixBuildInputCustomPrimitiveArray
930 {
935     const CUdeviceptr* aabbBuffers;

```

```

936
939     unsigned int numPrimitives;
940
944     unsigned int strideInBytes;
945
949     const unsigned int* flags;
950
952     unsigned int numSbtRecords;
953
957     CUdeviceptr sbtIndexOffsetBuffer;
958
960     unsigned int sbtIndexOffsetSizeInBytes;
961
964     unsigned int sbtIndexOffsetStrideInBytes;
965
968     unsigned int primitiveIndexOffset;
969 } OptixBuildInputCustomPrimitiveArray;
970
974 typedef struct OptixBuildInputInstanceArray
975 {
983     CUdeviceptr instances;
984
986     unsigned int numInstances;
987
991     unsigned int instanceStride;
992 } OptixBuildInputInstanceArray;
993
997 typedef struct OptixRelocateInputInstanceArray
998 {
1001     unsigned int numInstances;
1002
1008     CUdeviceptr traversableHandles;
1009
1010 } OptixRelocateInputInstanceArray;
1011
1015 typedef enum OptixBuildInputType
1016 {
1018     OPTIX_BUILD_INPUT_TYPE_TRIANGLES = 0x2141,
1020     OPTIX_BUILD_INPUT_TYPE_CUSTOM_PRIMITIVES = 0x2142,
1022     OPTIX_BUILD_INPUT_TYPE_INSTANCES = 0x2143,
1024     OPTIX_BUILD_INPUT_TYPE_INSTANCE_POINTERS = 0x2144,
1026     OPTIX_BUILD_INPUT_TYPE_CURVES = 0x2145,
1028     OPTIX_BUILD_INPUT_TYPE_SPHERES = 0x2146
1029 } OptixBuildInputType;
1030
1036 typedef struct OptixBuildInput
1037 {
1039     OptixBuildInputType type;
1040
1041     union
1042     {
1044         OptixBuildInputTriangleArray triangleArray;
1046         OptixBuildInputCurveArray curveArray;
1048         OptixBuildInputSphereArray sphereArray;
1050         OptixBuildInputCustomPrimitiveArray customPrimitiveArray;
1052         OptixBuildInputInstanceArray instanceArray;
1053         char pad[1024];
1054     };
1055 } OptixBuildInput;
1056
1060 typedef struct OptixRelocateInput
1061 {
1063     OptixBuildInputType type;
1064
1065     union
1066     {
1068         OptixRelocateInputInstanceArray instanceArray;

```

```

1069
1071     OptixRelocateInputTriangleArray triangleArray;
1072 };
1073 } OptixRelocateInput;
1074
1075 // Some 32-bit tools use this header. This static_assert fails for them because
1076 // the default enum size is 4 bytes, rather than 8, under 32-bit compilers.
1077 // This #ifndef allows them to disable the static assert.
1078
1079 // TODO Define a static assert for C/pre-C++-11
1080 #if defined(__cplusplus) && __cplusplus >= 201103L
1081 static_assert(sizeof(OptixBuildInput) == 8 + 1024, "OptixBuildInput has wrong size");
1082 #endif
1083
1084 typedef enum OptixInstanceFlags
1085 {
1086     OPTIX_INSTANCE_FLAG_NONE = 0,
1087     OPTIX_INSTANCE_FLAG_DISABLE_TRIANGLE_FACE_CULLING = 1u << 0,
1088     OPTIX_INSTANCE_FLAG_FLIP_TRIANGLE_FACING = 1u << 1,
1089     OPTIX_INSTANCE_FLAG_DISABLE_ANYHIT = 1u << 2,
1090     OPTIX_INSTANCE_FLAG_ENFORCE_ANYHIT = 1u << 3,
1091     OPTIX_INSTANCE_FLAG_FORCE_OPACITY_MICROMAP_2_STATE = 1u << 4,
1092     OPTIX_INSTANCE_FLAG_DISABLE_OPACITY_MICROMAPS = 1u << 5,
1093 } OptixInstanceFlags;
1094
1095 typedef struct OptixInstance
1096 {
1097     float transform[12];
1098     unsigned int instanceId;
1099     unsigned int sbtOffset;
1100     unsigned int visibilityMask;
1101     unsigned int flags;
1102     OptixTraversableHandle traversableHandle;
1103     unsigned int pad[2];
1104 } OptixInstance;
1105
1106 typedef enum OptixBuildFlags
1107 {
1108     OPTIX_BUILD_FLAG_NONE = 0,
1109     OPTIX_BUILD_FLAG_ALLOW_UPDATE = 1u << 0,
1110     OPTIX_BUILD_FLAG_ALLOW_COMPACTION = 1u << 1,
1111     OPTIX_BUILD_FLAG_PREFER_FAST_TRACE = 1u << 2,
1112     OPTIX_BUILD_FLAG_PREFER_FAST_BUILD = 1u << 3,
1113     OPTIX_BUILD_FLAG_ALLOW_RANDOM_VERTEX_ACCESS = 1u << 4,
1114     OPTIX_BUILD_FLAG_ALLOW_RANDOM_INSTANCE_ACCESS = 1u << 5,
1115     OPTIX_BUILD_FLAG_ALLOW_OPACITY_MICROMAP_UPDATE = 1u << 6,

```

```

1192
1196     OPTIX_BUILD_FLAG_ALLOW_DISABLE_OPACITY_MICROMAPS = 1u « 7,
1197 } OptixBuildFlags;
1198
1199
1201 typedef enum OptixOpacityMicromapFlags
1202 {
1203     OPTIX_OPACITY_MICROMAP_FLAG_NONE = 0,
1204
1206     OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_TRACE = 1 « 0,
1207
1209     OPTIX_OPACITY_MICROMAP_FLAG_PREFER_FAST_BUILD = 1 « 1,
1210 } OptixOpacityMicromapFlags;
1211
1213 typedef struct OptixOpacityMicromapDesc
1214 {
1216     unsigned int    byteOffset;
1218     unsigned short subdivisionLevel;
1220     unsigned short format;
1221 } OptixOpacityMicromapDesc;
1222
1227 typedef struct OptixOpacityMicromapHistogramEntry
1228 {
1230     unsigned int    count;
1232     unsigned int    subdivisionLevel;
1234     OptixOpacityMicromapFormat format;
1235 } OptixOpacityMicromapHistogramEntry;
1236
1238 typedef struct OptixOpacityMicromapArrayBuildInput
1239 {
1241     unsigned int flags;
1242
1244     CUdeviceptr inputBuffer;
1245
1248     CUdeviceptr perMicromapDescBuffer;
1249
1253     unsigned int perMicromapDescStrideInBytes;
1254
1256     unsigned int numMicromapHistogramEntries;
1259     const OptixOpacityMicromapHistogramEntry* micromapHistogramEntries;
1260 } OptixOpacityMicromapArrayBuildInput;
1261
1263 typedef struct OptixMicromapBufferSizes
1264 {
1265     size_t outputSizeInBytes;
1266     size_t tempSizeInBytes;
1267 } OptixMicromapBufferSizes;
1268
1270 typedef struct OptixMicromapBuffers
1271 {
1273     CUdeviceptr output;
1275     size_t outputSizeInBytes;
1277     CUdeviceptr temp;
1279     size_t tempSizeInBytes;
1280 } OptixMicromapBuffers;
1281
1282
1294 typedef enum OptixBuildOperation
1295 {
1297     OPTIX_BUILD_OPERATION_BUILD = 0x2161,
1299     OPTIX_BUILD_OPERATION_UPDATE = 0x2162,
1300 } OptixBuildOperation;
1301
1305 typedef enum OptixMotionFlags
1306 {
1307     OPTIX_MOTION_FLAG_NONE = 0,
1308     OPTIX_MOTION_FLAG_START_VANISH = 1u « 0,

```

```

1309     OPTIX_MOTION_FLAG_END_VANISH    = 1u « 1
1310 } OptixMotionFlags;
1311
1312 typedef struct OptixMotionOptions
1313 {
1314     unsigned short numKeys;
1315     unsigned short flags;
1316     float timeBegin;
1317     float timeEnd;
1318 } OptixMotionOptions;
1319
1320 typedef struct OptixAccelBuildOptions
1321 {
1322     unsigned int buildFlags;
1323     OptixBuildOperation operation;
1324     OptixMotionOptions motionOptions;
1325 } OptixAccelBuildOptions;
1326
1327 typedef struct OptixAccelBufferSizes
1328 {
1329     size_t outputSizeInBytes;
1330     size_t tempSizeInBytes;
1331     size_t tempUpdateSizeInBytes;
1332 } OptixAccelBufferSizes;
1333
1334 typedef enum OptixAccelPropertyType
1335 {
1336     OPTIX_PROPERTY_TYPE_COMPACTED_SIZE = 0x2181,
1337     OPTIX_PROPERTY_TYPE_AABBS = 0x2182,
1338 } OptixAccelPropertyType;
1339
1340 typedef struct OptixAccelEmitDesc
1341 {
1342     CUdeviceptr result;
1343     OptixAccelPropertyType type;
1344 } OptixAccelEmitDesc;
1345
1346 typedef struct OptixRelocationInfo
1347 {
1348     unsigned long long info[4];
1349 } OptixRelocationInfo;
1350
1351 typedef struct OptixStaticTransform
1352 {
1353     OptixTraversableHandle child;
1354     unsigned int pad[2];
1355     float transform[12];
1356     float invTransform[12];
1357 } OptixStaticTransform;
1358
1359 typedef struct OptixMatrixMotionTransform
1360 {
1361     OptixTraversableHandle child;
1362     OptixMotionOptions motionOptions;

```

```

1461
1462     unsigned int pad[3];
1463
1464     float transform[2][12];
1465 } OptixMatrixMotionTransform;
1466
1467 //      [ sx  a  b  pvx ]
1468 // S = [  0  sy  c  pvy ]
1469 //      [  0  0  sz  pvz ]
1470 //      [  1  0  0  tx  ]
1471 // T = [  0  1  0  ty  ]
1472 //      [  0  0  1  tz  ]
1473
1474 typedef struct OptixSRTData
1475 {
1476     float sx, a, b, pvx, sy, c, pvy, sz, pvz, qx, qy, qz, qw, tx, ty, tz;
1477 } OptixSRTData;
1478
1479 // TODO Define a static assert for C/pre-C++-11
1480 #if defined(__cplusplus) && __cplusplus >= 201103L
1481 static_assert(sizeof(OptixSRTData) == 16 * 4, "OptixSRTData has wrong size");
1482 #endif
1483
1484 typedef struct OptixSRTMotionTransform
1485 {
1486     OptixTraversableHandle child;
1487
1488     OptixMotionOptions motionOptions;
1489
1490     unsigned int pad[3];
1491
1492     OptixSRTData srtData[2];
1493 } OptixSRTMotionTransform;
1494
1495 // TODO Define a static assert for C/pre-C++-11
1496 #if defined(__cplusplus) && __cplusplus >= 201103L
1497 static_assert(sizeof(OptixSRTMotionTransform) == 8 + 12 + 12 + 2 * 16 * 4, "OptixSRTMotionTransform has
wrong size");
1498 #endif
1499
1500 typedef enum OptixTraversableType
1501 {
1502     OPTIX_TRAVERSABLE_TYPE_STATIC_TRANSFORM = 0x21C1,
1503     OPTIX_TRAVERSABLE_TYPE_MATRIX_MOTION_TRANSFORM = 0x21C2,
1504     OPTIX_TRAVERSABLE_TYPE_SRT_MOTION_TRANSFORM = 0x21C3,
1505 } OptixTraversableType;
1506
1507 typedef enum OptixPixelFormat
1508 {
1509     OPTIX_PIXEL_FORMAT_HALF1 = 0x220a,
1510     OPTIX_PIXEL_FORMAT_HALF2 = 0x2207,
1511     OPTIX_PIXEL_FORMAT_HALF3 = 0x2201,
1512     OPTIX_PIXEL_FORMAT_HALF4 = 0x2202,
1513     OPTIX_PIXEL_FORMAT_FLOAT1 = 0x220b,
1514     OPTIX_PIXEL_FORMAT_FLOAT2 = 0x2208,
1515     OPTIX_PIXEL_FORMAT_FLOAT3 = 0x2203,
1516     OPTIX_PIXEL_FORMAT_FLOAT4 = 0x2204,
1517     OPTIX_PIXEL_FORMAT_UCHAR3 = 0x2205,
1518     OPTIX_PIXEL_FORMAT_UCHAR4 = 0x2206,
1519     OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER = 0x2209
1520 } OptixPixelFormat;
1521
1522 typedef struct OptixImage2D
1523 {
1524     CUdeviceptr data;
1525     unsigned int width;
1526     unsigned int height;
1527     unsigned int rowStrideInBytes;

```



```

1605     unsigned int pixelStrideInBytes;
1607     OptixPixelFormat format;
1608 } OptixImage2D;
1609
1613 typedef enum OptixDenoiserModelKind
1614 {
1616     OPTIX_DENOISER_MODEL_KIND_LDR = 0x2322,
1617
1619     OPTIX_DENOISER_MODEL_KIND_HDR = 0x2323,
1620
1622     OPTIX_DENOISER_MODEL_KIND_AOV = 0x2324,
1623
1625     OPTIX_DENOISER_MODEL_KIND_TEMPORAL = 0x2325,
1626
1628     OPTIX_DENOISER_MODEL_KIND_TEMPORAL_AOV = 0x2326,
1629
1631     OPTIX_DENOISER_MODEL_KIND_UPSCALE2X = 0x2327,
1632
1635     OPTIX_DENOISER_MODEL_KIND_TEMPORAL_UPSCALE2X = 0x2328
1636 } OptixDenoiserModelKind;
1637
1641 typedef enum OptixDenoiserAlphaMode
1642 {
1644     OPTIX_DENOISER_ALPHA_MODE_COPY = 0,
1645
1647     OPTIX_DENOISER_ALPHA_MODE_DENOISE = 1
1648 } OptixDenoiserAlphaMode;
1649
1653 typedef struct OptixDenoiserOptions
1654 {
1655     // if nonzero, albedo image must be given in OptixDenoiserGuideLayer
1656     unsigned int guideAlbedo;
1657
1658     // if nonzero, normal image must be given in OptixDenoiserGuideLayer
1659     unsigned int guideNormal;
1660
1662     OptixDenoiserAlphaMode denoiseAlpha;
1663 } OptixDenoiserOptions;
1664
1668 typedef struct OptixDenoiserGuideLayer
1669 {
1670     // image with three components: R, G, B.
1671     OptixImage2D albedo;
1672
1673     // image with two or three components: X, Y, Z.
1674     // (X, Y) camera space. (X, Y, Z) world space, depending on model.
1675     OptixImage2D normal;
1676
1677     // image with two components: X, Y.
1678     // pixel movement from previous to current frame for each pixel in screen space.
1679     OptixImage2D flow;
1680
1681     // Internal images used in temporal AOV denoising modes,
1682     // pixel format OPTIX_PIXEL_FORMAT_INTERNAL_GUIDE_LAYER.
1683     OptixImage2D previousOutputInternalGuideLayer;
1684     OptixImage2D outputInternalGuideLayer;
1685
1686     // image with a single component value that specifies how trustworthy the flow vector at x,y
position in
1687     // OptixDenoiserGuideLayer::flow is. Range 0..1 (low->high trustworthiness).
1688     // Ignored if data pointer in the image is zero.
1689     OptixImage2D flowTrustworthiness;
1690
1691 } OptixDenoiserGuideLayer;
1692
1695 typedef enum OptixDenoiserAOVType
1696 {

```

```

1698     OPTIX_DENOISER_AOV_TYPE_NONE           = 0,
1699
1700     OPTIX_DENOISER_AOV_TYPE_BEAUTY         = 0x7000,
1701     OPTIX_DENOISER_AOV_TYPE_SPECULAR      = 0x7001,
1702     OPTIX_DENOISER_AOV_TYPE_REFLECTION    = 0x7002,
1703     OPTIX_DENOISER_AOV_TYPE_REFRACTION    = 0x7003,
1704     OPTIX_DENOISER_AOV_TYPE_DIFFUSE       = 0x7004
1705
1706 } OptixDenoiserAOVType;
1707
1711 typedef struct OptixDenoiserLayer
1712 {
1713     // input image (beauty or AOV)
1714     OptixImage2D input;
1715
1716     // denoised output image from previous frame if temporal model kind selected
1717     OptixImage2D previousOutput;
1718
1719     // denoised output for given input
1720     OptixImage2D output;
1721
1722     // Type of AOV, used in temporal AOV modes as a hint to improve image quality.
1723     OptixDenoiserAOVType type;
1724 } OptixDenoiserLayer;
1725
1731
1732 typedef struct OptixDenoiserParams
1733 {
1734     CUdeviceptr  hdrIntensity;
1735
1736     float        blendFactor;
1737
1738     CUdeviceptr  hdrAverageColor;
1739
1740     unsigned int temporalModeUsePreviousLayers;
1741 } OptixDenoiserParams;
1742
1743
1744 typedef struct OptixDenoiserSizes
1745 {
1746     size_t stateSizeInBytes;
1747
1748     size_t withOverlapScratchSizeInBytes;
1749
1750     size_t withoutOverlapScratchSizeInBytes;
1751
1752     unsigned int overlapWindowSizeInPixels;
1753
1754     size_t computeAverageColorSizeInBytes;
1755
1756     size_t computeIntensitySizeInBytes;
1757
1758     size_t internalGuideLayerPixelSizeInBytes;
1759 } OptixDenoiserSizes;
1760
1761
1762 typedef enum OptixRayFlags
1763 {
1764     OPTIX_RAY_FLAG_NONE = 0u,
1765
1766     OPTIX_RAY_FLAG_DISABLE_ANYHIT = 1u « 0,
1767
1768     OPTIX_RAY_FLAG_ENFORCE_ANYHIT = 1u « 1,
1769
1770     OPTIX_RAY_FLAG_TERMINATE_ON_FIRST_HIT = 1u « 2,
1771
1772     OPTIX_RAY_FLAG_DISABLE_CLOSESTHIT = 1u « 3,
1773
1774     OPTIX_RAY_FLAG_CULL_BACK_FACING_TRIANGLES = 1u « 4,

```

```

1824
1829     OPTIX_RAY_FLAG_CULL_FRONT_FACING_TRIANGLES = 1u « 5,
1830
1836     OPTIX_RAY_FLAG_CULL_DISABLED_ANYHIT = 1u « 6,
1837
1843     OPTIX_RAY_FLAG_CULL_ENFORCED_ANYHIT = 1u « 7,
1844
1846     OPTIX_RAY_FLAG_FORCE_OPACITY_MICROMAP_2_STATE = 1u « 10,
1847 } OptixRayFlags;
1848
1854 typedef enum OptixTransformType
1855 {
1856     OPTIX_TRANSFORM_TYPE_NONE = 0,
1857     OPTIX_TRANSFORM_TYPE_STATIC_TRANSFORM = 1,
1858     OPTIX_TRANSFORM_TYPE_MATRIX_MOTION_TRANSFORM = 2,
1859     OPTIX_TRANSFORM_TYPE_SRT_MOTION_TRANSFORM = 3,
1860     OPTIX_TRANSFORM_TYPE_INSTANCE = 4,
1861 } OptixTransformType;
1862
1865 typedef enum OptixTraversableGraphFlags
1866 {
1869     OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_ANY = 0,
1870
1874     OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_GAS = 1u « 0,
1875
1880     OPTIX_TRAVERSABLE_GRAPH_FLAG_ALLOW_SINGLE_LEVEL_INSTANCING = 1u « 1,
1881 } OptixTraversableGraphFlags;
1882
1886 typedef enum OptixCompileOptimizationLevel
1887 {
1889     OPTIX_COMPILE_OPTIMIZATION_DEFAULT = 0,
1891     OPTIX_COMPILE_OPTIMIZATION_LEVEL_0 = 0x2340,
1893     OPTIX_COMPILE_OPTIMIZATION_LEVEL_1 = 0x2341,
1895     OPTIX_COMPILE_OPTIMIZATION_LEVEL_2 = 0x2342,
1897     OPTIX_COMPILE_OPTIMIZATION_LEVEL_3 = 0x2343,
1898 } OptixCompileOptimizationLevel;
1899
1903 typedef enum OptixCompileDebugLevel
1904 {
1906     OPTIX_COMPILE_DEBUG_LEVEL_DEFAULT = 0,
1908     OPTIX_COMPILE_DEBUG_LEVEL_NONE = 0x2350,
1911     OPTIX_COMPILE_DEBUG_LEVEL_MINIMAL = 0x2351,
1913     OPTIX_COMPILE_DEBUG_LEVEL_MODERATE = 0x2353,
1915     OPTIX_COMPILE_DEBUG_LEVEL_FULL = 0x2352,
1916 } OptixCompileDebugLevel;
1917
1921 typedef enum OptixModuleCompileState
1922 {
1924     OPTIX_MODULE_COMPILE_STATE_NOT_STARTED = 0x2360,
1925
1927     OPTIX_MODULE_COMPILE_STATE_STARTED = 0x2361,
1928
1930     OPTIX_MODULE_COMPILE_STATE_IMPENDING_FAILURE = 0x2362,
1931
1933     OPTIX_MODULE_COMPILE_STATE_FAILED = 0x2363,
1934
1936     OPTIX_MODULE_COMPILE_STATE_COMPLETED = 0x2364,
1937 } OptixModuleCompileState;
1938
1939
1940
1973 typedef struct OptixModuleCompileBoundValueEntry {
1974     size_t pipelineParamOffsetInBytes;
1975     size_t sizeInBytes;
1976     const void* boundValuePtr;
1977     const char* annotation; // optional string to display, set to 0 if unused. If unused,
1978                           // OptiX will report the annotation as "No annotation"

```

```

1979 } OptixModuleCompileBoundValueEntry;
1980
1982 typedef enum OptixPayloadTypeID {
1983     OPTIX_PAYLOAD_TYPE_DEFAULT = 0,
1984     OPTIX_PAYLOAD_TYPE_ID_0 = (1 « 0u),
1985     OPTIX_PAYLOAD_TYPE_ID_1 = (1 « 1u),
1986     OPTIX_PAYLOAD_TYPE_ID_2 = (1 « 2u),
1987     OPTIX_PAYLOAD_TYPE_ID_3 = (1 « 3u),
1988     OPTIX_PAYLOAD_TYPE_ID_4 = (1 « 4u),
1989     OPTIX_PAYLOAD_TYPE_ID_5 = (1 « 5u),
1990     OPTIX_PAYLOAD_TYPE_ID_6 = (1 « 6u),
1991     OPTIX_PAYLOAD_TYPE_ID_7 = (1 « 7u)
1992 } OptixPayloadTypeID;
1993
2007 typedef enum OptixPayloadSemantics
2008 {
2009     OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_NONE = 0,
2010     OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ = 1u « 0,
2011     OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_WRITE = 2u « 0,
2012     OPTIX_PAYLOAD_SEMANTICS_TRACE_CALLER_READ_WRITE = 3u « 0,
2013
2014     OPTIX_PAYLOAD_SEMANTICS_CH_NONE = 0,
2015     OPTIX_PAYLOAD_SEMANTICS_CH_READ = 1u « 2,
2016     OPTIX_PAYLOAD_SEMANTICS_CH_WRITE = 2u « 2,
2017     OPTIX_PAYLOAD_SEMANTICS_CH_READ_WRITE = 3u « 2,
2018
2019     OPTIX_PAYLOAD_SEMANTICS_MS_NONE = 0,
2020     OPTIX_PAYLOAD_SEMANTICS_MS_READ = 1u « 4,
2021     OPTIX_PAYLOAD_SEMANTICS_MS_WRITE = 2u « 4,
2022     OPTIX_PAYLOAD_SEMANTICS_MS_READ_WRITE = 3u « 4,
2023
2024     OPTIX_PAYLOAD_SEMANTICS_AH_NONE = 0,
2025     OPTIX_PAYLOAD_SEMANTICS_AH_READ = 1u « 6,
2026     OPTIX_PAYLOAD_SEMANTICS_AH_WRITE = 2u « 6,
2027     OPTIX_PAYLOAD_SEMANTICS_AH_READ_WRITE = 3u « 6,
2028
2029     OPTIX_PAYLOAD_SEMANTICS_IS_NONE = 0,
2030     OPTIX_PAYLOAD_SEMANTICS_IS_READ = 1u « 8,
2031     OPTIX_PAYLOAD_SEMANTICS_IS_WRITE = 2u « 8,
2032     OPTIX_PAYLOAD_SEMANTICS_IS_READ_WRITE = 3u « 8,
2033 } OptixPayloadSemantics;
2034
2036 typedef struct OptixPayloadType
2037 {
2038     unsigned int numPayloadValues;
2039
2040     const unsigned int *payloadSemantics;
2041 } OptixPayloadType;
2042
2044 typedef struct OptixModuleCompileOptions
2045 {
2046     int maxRegisterCount;
2047
2048     OptixCompileOptimizationLevel optLevel;
2049
2050     OptixCompileDebugLevel debugLevel;
2051
2052     const OptixModuleCompileBoundValueEntry* boundValues;
2053
2054     unsigned int numBoundValues;
2055
2056     unsigned int numPayloadTypes;
2057
2058     const OptixPayloadType* payloadTypes;
2059 } OptixModuleCompileOptions;
2060

```

```

2076 typedef enum OptixProgramGroupKind
2077 {
2080     OPTIX_PROGRAM_GROUP_KIND_RAYGEN = 0x2421,
2081
2084     OPTIX_PROGRAM_GROUP_KIND_MISS = 0x2422,
2085
2088     OPTIX_PROGRAM_GROUP_KIND_EXCEPTION = 0x2423,
2089
2092     OPTIX_PROGRAM_GROUP_KIND_HITGROUP = 0x2424,
2093
2096     OPTIX_PROGRAM_GROUP_KIND_CALLABLES = 0x2425
2097 } OptixProgramGroupKind;
2098
2100 typedef enum OptixProgramGroupFlags
2101 {
2103     OPTIX_PROGRAM_GROUP_FLAGS_NONE = 0
2104 } OptixProgramGroupFlags;
2105
2112 typedef struct OptixProgramGroupSingleModule
2113 {
2115     OptixModule module;
2117     const char* entryFunctionName;
2118 } OptixProgramGroupSingleModule;
2119
2125 typedef struct OptixProgramGroupHitgroup
2126 {
2128     OptixModule moduleCH;
2130     const char* entryFunctionNameCH;
2132     OptixModule moduleAH;
2134     const char* entryFunctionNameAH;
2136     OptixModule moduleIS;
2138     const char* entryFunctionNameIS;
2139 } OptixProgramGroupHitgroup;
2140
2146 typedef struct OptixProgramGroupCallables
2147 {
2149     OptixModule moduleDC;
2151     const char* entryFunctionNameDC;
2153     OptixModule moduleCC;
2155     const char* entryFunctionNameCC;
2156 } OptixProgramGroupCallables;
2157
2159 typedef struct OptixProgramGroupDesc
2160 {
2162     OptixProgramGroupKind kind;
2163
2165     unsigned int flags;
2166
2167     union
2168     {
2170         OptixProgramGroupSingleModule raygen;
2172         OptixProgramGroupSingleModule miss;
2174         OptixProgramGroupSingleModule exception;
2176         OptixProgramGroupCallables callables;
2178         OptixProgramGroupHitgroup hitgroup;
2179     };
2180 } OptixProgramGroupDesc;
2181
2185 typedef struct OptixProgramGroupOptions
2186 {
2199     const OptixPayloadType* payloadType;
2200 } OptixProgramGroupOptions;
2201
2203 typedef enum OptixExceptionCodes
2204 {
2207     OPTIX_EXCEPTION_CODE_STACK_OVERFLOW = -1,
2208

```

```

2211     OPTIX_EXCEPTION_CODE_TRACE_DEPTH_EXCEEDED = -2,
2212
2213
2214 } OptixExceptionCodes;
2215
2219 typedef enum OptixExceptionFlags
2220 {
2222     OPTIX_EXCEPTION_FLAG_NONE = 0,
2223
2230     OPTIX_EXCEPTION_FLAG_STACK_OVERFLOW = 1u « 0,
2231
2238     OPTIX_EXCEPTION_FLAG_TRACE_DEPTH = 1u « 1,
2239
2242     OPTIX_EXCEPTION_FLAG_USER = 1u « 2,
2243
2244 } OptixExceptionFlags;
2245
2251 typedef struct OptixPipelineCompileOptions
2252 {
2254     int usesMotionBlur;
2255
2257     unsigned int traversableGraphFlags;
2258
2261     int numPayloadValues;
2262
2265     int numAttributeValues;
2266
2268     unsigned int exceptionFlags;
2269
2273     const char* pipelineLaunchParamsVariableName;
2274
2277     unsigned int usesPrimitiveTypeFlags;
2278
2280     int allowOpacityMicromaps;
2281 } OptixPipelineCompileOptions;
2282
2286 typedef struct OptixPipelineLinkOptions
2287 {
2290     unsigned int maxTraceDepth;
2291
2292 } OptixPipelineLinkOptions;
2293
2297 typedef struct OptixShaderBindingTable
2298 {
2301     CUdeviceptr raygenRecord;
2302
2305     CUdeviceptr exceptionRecord;
2306
2310     CUdeviceptr missRecordBase;
2311     unsigned int missRecordStrideInBytes;
2312     unsigned int missRecordCount;
2314
2318     CUdeviceptr hitgroupRecordBase;
2319     unsigned int hitgroupRecordStrideInBytes;
2320     unsigned int hitgroupRecordCount;
2322
2327     CUdeviceptr callablesRecordBase;
2328     unsigned int callablesRecordStrideInBytes;
2329     unsigned int callablesRecordCount;
2331
2332 } OptixShaderBindingTable;
2333
2337 typedef struct OptixStackSizes
2338 {
2340     unsigned int cssRG;
2342     unsigned int cssMS;
2344     unsigned int cssCH;

```

```

2346     unsigned int cssAH;
2348     unsigned int cssIS;
2350     unsigned int cssCC;
2352     unsigned int dssDC;
2353
2354 } OptixStackSizes;
2355
2357 typedef enum OptixQueryFunctionTableOptions
2358 {
2360     OPTIX_QUERY_FUNCTION_TABLE_OPTION_DUMMY = 0
2361
2362 } OptixQueryFunctionTableOptions;
2363
2365 typedef OptixResult(OptixQueryFunctionTable_t)(int          abiId,
2366                                                unsigned int numOptions,
2367                                                OptixQueryFunctionTableOptions* /*optionKeys*/,
2368                                                const void** /*optionValues*/,
2369                                                void* functionTable,
2370                                                size_t sizeOfTable);
2371
2376 typedef struct OptixBuiltinISOptions
2377 {
2378     OptixPrimitiveType    builtinISModuleType;
2380     int                   usesMotionBlur;
2382     unsigned int          buildFlags;
2384     unsigned int          curveEndcapFlags;
2385 } OptixBuiltinISOptions;
2386
2387 #if defined(__CUDACC__)
2392 typedef struct OptixInvalidRayExceptionDetails
2393 {
2394     float3 origin;
2395     float3 direction;
2396     float tmin;
2397     float tmax;
2398     float time;
2399 } OptixInvalidRayExceptionDetails;
2400
2407 typedef struct OptixParameterMismatchExceptionDetails
2408 {
2410     unsigned int expectedParameterCount;
2412     unsigned int passedArgumentCount;
2414     unsigned int sbtIndex;
2416     char* callableName;
2417 } OptixParameterMismatchExceptionDetails;
2418 #endif
2419
2420 // end group optix_types
2422
2423 #endif // OPTIX_OPTIX_TYPES_H

```

## 8.27 main.dox File Reference